
pytorch-pfn-extras

Preferred Networks, Inc.

Aug 31, 2023

CONTENTS

1 User Guide	3
1.1 Quick Start	3
1.2 Trainer	9
1.3 Extensions	15
1.4 Utilities	19
2 API Reference	37
2.1 Package	37
2.2 Training Loop	514
2.3 Distributed Training	516
2.4 Check Pointing	516
2.5 Lazy Modules	516
2.6 ONNX	517
2.7 Datasets	517
2.8 Config	517
2.9 NumPy/CuPy Compatibility	518
Python Module Index	519
Index	521

pytorch-pfn-extras (PPE) is a collection of supplementary components to accelerate research and development in PyTorch.

USER GUIDE

1.1 Quick Start

1.1.1 Quick Start

First, pytorch-pfn-extras organizes the training code implemented using PyTorch using the Trainer/Evaluator classes.

Next, it provides the following interfaces for training PyTorch models.

1. Addition of extensions for analysis and visualization
2. Runtime changes
3. Addition of custom training steps
4. Custom data handling

Step 1: Use Trainer

First, pass to the Trainer the Model and Optimizer you want to train.

Listing 1: quick_start_trainer.py

```
import pytorch_pfn_extras as ppe
import torch

class Model(torch.nn.Module):
    def __init__(self, *args, **kwargs) -> None:
        super().__init__(*args, **kwargs)
        self.linear = torch.nn.Linear(in_features=64, out_features=2)
        self.criterion = torch.nn.NLLLoss()

    def forward(self, x, target):
        y = self.linear.forward(x).log_softmax(dim=1)
        loss = self.criterion.forward(y, target)
        return {"loss": loss}

model = Model()
optimizer = torch.optim.SGD(model.parameters(), lr=0.01)
```

(continues on next page)

(continued from previous page)

```
device = (
    "cuda:0"  # or any other PyTorch devices ('cpu', etc.) or PPE runtime names
)
epochs = 3
# Create a trainer with the defined model, optimizer, and other parameters
trainer = ppe.engine.create_trainer(
    models=model,
    optimizers=optimizer,
    max_epochs=epochs,
    evaluator=ppe.engine.create_evaluator(
        models=model,
        device=device,
    ),
    device=device,
)

# Send the model to device(GPU) for computation
ppe.to(model, device=device)

batch_size = 10
# Create 10 batches of random training data with dimension (batch_size x 64)
training_data = [
    {
        "x": torch.rand((batch_size, 64)),
        "target": torch.ones((batch_size,), dtype=torch.long),
    }
    for _ in range(10)
]
# Create 10 batches of random validation data with dimension (batch_size x 64)
validation_data = [
    {
        "x": torch.rand((batch_size, 64)),
        "target": torch.ones((batch_size,), dtype=torch.long),
    }
    for _ in range(10)
]

# Start the training and validation of the model
trainer.run(train_loader=training_data, val_loader=validation_data)

print("Finish training!")
```

Step 2: Get Log

Next, collect the logs of the training progress.

Listing 2: quick_start_log.py

```
import pytorch_pfn_extras as ppe
import torch

class Model(torch.nn.Module):
    def __init__(self, *args, **kwargs) -> None:
        super().__init__(*args, **kwargs)
        self.linear = torch.nn.Linear(in_features=64, out_features=2)
        self.criterion = torch.nn.NLLLoss()

    def forward(self, x, target):
        y = self.linear.forward(x).log_softmax(dim=1)
        loss = self.criterion.forward(y, target)
        return {"loss": loss}

model = Model()
optimizer = torch.optim.SGD(model.parameters(), lr=0.01)

device = "cuda:0"
epochs = 3
trainer = ppe.engine.create_trainer(
    models=model,
    optimizers=optimizer,
    max_epochs=epochs,
    evaluator=ppe.engine.create_evaluator(
        models=model,
        device=device,
        options={
            "eval_report_keys": [
                "loss"
            ], # Let the value of the loss be notified to the LogReport.
        },
    ),
    device=device,
    options={
        "train_report_keys": [
            "loss"
        ], # Let the value of the loss be notified to the LogReport.
    },
)
trainer.extend(
    ppe.training.extensions.LogReport()
) # It is an extension to collect parameters reported during training.

ppe.to(model, device=device)
```

(continues on next page)

(continued from previous page)

```
batch_size = 10
training_data = [
    {
        "x": torch.rand((batch_size, 64)),
        "target": torch.ones((batch_size,), dtype=torch.long),
    }
    for _ in range(10)
]
validation_data = [
    {
        "x": torch.rand((batch_size, 64)),
        "target": torch.ones((batch_size,), dtype=torch.long),
    }
    for _ in range(10)
]

trainer.run(train_loader=training_data, val_loader=validation_data)

print("Finish training!")
```

The logs of the collected learning progress are output to `./result/log`.

Step 3: Display of progress

Make it possible to check the progress of the learning.

Listing 3: quick_start_progress.py

```
import pytorch_pfn_extras as ppe
import torch

class Model(torch.nn.Module):
    def __init__(self, *args, **kwargs) -> None:
        super().__init__(*args, **kwargs)
        self.linear = torch.nn.Linear(in_features=64, out_features=2)
        self.criterion = torch.nn.NLLLoss()

    def forward(self, x, target):
        y = self.linear.forward(x).log_softmax(dim=1)
        loss = self.criterion.forward(y, target)
        return {"loss": loss}

model = Model()
optimizer = torch.optim.SGD(model.parameters(), lr=0.01)

device = "cuda:0"
epochs = 3
trainer = ppe.engine.create_trainer(
    models=model,
```

(continues on next page)

(continued from previous page)

```

optimizers=optimizer,
max_epochs=epochs,
evaluator=ppe.engine.create_evaluator(
    models=model,
    device=device,
    options={
        "eval_report_keys": ["loss"],
    },
),
device=device,
options={
    "train_report_keys": ["loss"],
},
)
)

trainer.extend(ppe.training.extensions.LogReport())
trainer.extend(ppe.training.extensions.ProgressBar())
trainer.extend(
    ppe.training.extensions.PrintReport( # Displays the collected logs interactively.
        [
            "epoch", # epoch, iteration, elapsed_time are automatically collected by LogReport.
            "iteration",
            "elapsed_time",
            "train/loss", # The parameters specified by train_report_keys are collected under keys with the 'train/' prefix.
            "val/loss", # The parameters specified by eval_report_keys are collected under keys with the 'val/' prefix.
        ],
    ),
)
)

ppe.to(model, device=device)

batch_size = 10
training_data = [
    {
        "x": torch.rand((batch_size, 64)),
        "target": torch.ones((batch_size,), dtype=torch.long),
    }
    for _ in range(10)
]
validation_data = [
    {
        "x": torch.rand((batch_size, 64)),
        "target": torch.ones((batch_size,), dtype=torch.long),
    }
    for _ in range(10)
]

trainer.run(train_loader=training_data, val_loader=validation_data)

```

(continues on next page)

(continued from previous page)

```
print("Finish training!")
```

Step 4: Save Model

Finally, save the trained model.

Listing 4: quick_start_save.py

```
import pytorch_pfn_extras as ppe
import torch

class Model(torch.nn.Module):
    def __init__(self, *args, **kwargs) -> None:
        super().__init__(*args, **kwargs)
        self.linear = torch.nn.Linear(in_features=64, out_features=2)
        self.criterion = torch.nn.NLLLoss()

    def forward(self, x, target):
        y = self.linear.forward(x).log_softmax(dim=1)
        loss = self.criterion.forward(y, target)
        return {"loss": loss}

model = Model()
optimizer = torch.optim.SGD(model.parameters(), lr=0.01)

device = "cuda:0"
epochs = 3
trainer = ppe.engine.create_trainer(
    models=model,
    optimizers=optimizer,
    max_epochs=epochs,
    evaluator=ppe.engine.create_evaluator(
        models=model,
        device=device,
        options={
            "eval_report_keys": ["loss"],
        },
    ),
    device=device,
    options={
        "train_report_keys": ["loss"],
    },
)

trainer.extend(ppe.training.extensions.LogReport())
trainer.extend(ppe.training.extensions.ProgressBar())
trainer.extend(
    ppe.training.extensions.PrintReport( # Displays the collected logs interactively.

```

(continues on next page)

(continued from previous page)

```

[  

    "epoch", # epoch, iteration, elapsed_time are automatically collected by  

    ↵LogReport.  

    "iteration",  

    "elapsed_time",  

    "train/loss", # The parameters specified by train_report_keys are collected  

    ↵under keys with the 'train/' prefix.  

    "val/loss", # The parameters specified by eval_report_keys are collected  

    ↵under keys with the 'val/' prefix.  

    ],  

)  

)  

trainer.extend(  

    ppe.training.extensions.snapshot(target=model)  

) # Save the model parameters after each epoch.  

  

ppe.to(model, device=device)  

  

batch_size = 10  

training_data = [  

    {  

        "x": torch.rand((batch_size, 64)),  

        "target": torch.ones((batch_size,), dtype=torch.long),  

    }  

    for _ in range(10)  

]  

validation_data = [  

    {  

        "x": torch.rand((batch_size, 64)),  

        "target": torch.ones((batch_size,), dtype=torch.long),  

    }  

    for _ in range(10)  

]  

  

trainer.run(train_loader=training_data, val_loader=validation_data)  

print("Finish training!")

```

The model parameters are stored with a file name that includes the time they were saved under `./result`.

Snapshots are generated using `state_dict()`. Please refer to the official PyTorch [docs](#) for how to load the model.

1.2 Trainer

1.2.1 Trainer and Evaluator

The Trainer and Evaluator provide the device-agnostic training framework for PyTorch. These APIs abstract the training process using different *runtimes*, handlers, and *logics*.

Concepts

- **Trainer** (`ppe.engine.create_trainer()`) abstracts the training loop, built on top of the `ExtensionsManager`.
- **Evaluator** (`ppe.engine.create_evaluator()`) abstracts the evaluation step and invoked from the Trainer (usually once in every epoch).
- **Runtime** (`ppe.runtime.BaseRuntime`) represents an environment used to execute models. Device-specific implementations will reside here. PPE provides the default Runtime that supports the PyTorch-native devices (`ppe.runtime.PyTorchRuntime`).
- **Handler** (`ppe.handler.Handler`) is a layer to support device-agnostic training. This is considered as a low-level API and in most cases users can just use the Handler provided by PPE.
- **Logic** (`ppe.handler.Logic`) is a set of callback functions that define the training logic (`optimizer.zero_grad()`, forward, backward, `optimizer.step()`). You can inherit the class and define your own training flow in case you need more complex training processes such as GAN.
- **Model** is a `torch.nn.Module` used for training and evaluation, whose inputs are dicts or keyword arguments and outputs of the `forward` pass is a dict.

Note that the default logic will perform backward in tensors returned by `model.forward` so you will need to perform the loss calculation inside the model itself.

Trainer at a glance

```
import torch
import torch.nn.functional as F

import pytorch_pfn_extras as ppe

class MyModel(torch.nn.Module):
    def __init__(self):
        super().__init__()
        self.w = torch.nn.LazyLinear(1)

    def forward(self, *, x, target):
        y = self.w(x)
        loss = F.nll_loss(y, target)
        prefix = 'train' if self.training else 'val'
        ppe.reporting.report({f'{prefix}/loss': loss.item()})
        return {'loss': loss}

model = MyModel()
optim = torch.optim.SGD(model.parameters(), lr=0.01)

extensions = [
    ppe.training.extensions.LogReport(),
    ppe.training.extensions.ProgressBar(),
    ppe.training.extensions.PrintReport(
        ['epoch', 'iteration', 'train/loss', 'val/loss']),
]
```

(continues on next page)

(continued from previous page)

```

device = 'cuda:0' # or any other PyTorch devices ('cpu', etc.) or PPE runtime names
epochs = 10
trainer = ppe.engine.create_trainer(
    model,
    optim,
    epochs,
    evaluator=ppe.engine.create_evaluator(
        model,
        device=device,
        progress_bar=True,
    ),
    device=device,
    extensions=extensions,
)

# Move the model to the device. This is almost equivalent to
# `model.to(device)`, but supports PPE runtimes as well as the PyTorch's
# built-in devices.
ppe.to(model, device)

# Using dummy data to illustrate the minimal working example.
# Notice that dict keys match with the kwargs of the forward method.
train_loader = torch.utils.data.DataLoader(
    [{'x': torch.rand(10, 64), 'target': torch.tensor([1])} for _ in range(1)],
    num_workers=8)
val_loader = torch.utils.data.DataLoader(
    [{'x': torch.rand(10, 64), 'target': torch.tensor([1])} for _ in range(1)],
    num_workers=8)

trainer.run(train_loader, val_loader)

```

Snapshot

To obtain and save the trained model for later use you can use the *Snapshot* extension, or directly invoke *state_dict* on the trainer itself.

Handler

The `ppe.handler.Handler` object is used to help the trainer and evaluator objects in the *Logic* and *Runtime* manipulation. This class should ideally never be overridden by the user if the desired functionality can be achieved through subclassing `BaseLogic` or `BaseRuntime`.

The handler object's main responsibility is to inspect all the submodules of a module to obtain the runtimes they have associated, and then execute their callbacks accordingly. In addition, it drives the actual model execution by using the user provided Logic object and deals with asynchronous execution in runtimes that provide support for it.

Runtime

By inheriting `ppe.runtime.BaseRuntime` and implementing your own runtime, you can use your non-standard devices with the training loop.

```
class MyRuntime(BaseRuntime):
    ...
    # Register MyRuntime with device name "mydev"
    ppe.runtime.runtime_registry.register('mydev', MyRuntime)

    ppe.to(module_or_tensor, 'mydev')
```

See [Runtimes for Custom Devices](#) if you are interested in implementing your own runtime.

1.2.2 Logic for Custom Training and Evaluation

In the training and evaluation engines, `ppe.handler.BaseLogic` API is in charge of abstracting the algorithmic details of the training and evaluation loops.

Logic is an object that defines multiple callbacks used through the training and evaluation processes. With logic, we can implement training of complex models such as GANs.

Users wanting to define their own Logic for training can inherit from `ppe.handler.Logic` which implements the training and evaluation steps to train a single module.

Logic functions are not expected to be directly called by the user. They will be invoked by the Trainer and Evaluator engines.

Default Logic (`ppe.handler.Logic`)

PPE provides a default logic that performs the forward/backward/optimizer loop for a single model. This logic allows using some torch features such as AMP autocast and GradScaler and performs the backward pass on the outputs specified by the config option `backward_outputs`.

CodeBlock Logic (`ppe.handler.Logic`)

With the CodeBlock API, we provide a basic logic that uses it to perform the training of a single model. Similarly to the default logic AMP features are supported but by means of the Runtime. For more information check the codeblock documentation.

1.2.3 Runtimes for Custom Devices

Note: This documentation is intended for those implementing the own device backend for PPE training framework. Most users can just skip this chapter.

The `ppe.runtime.BaseRuntime` API is in charge of abstracting the device details and performing the movement of data and modules to the corresponding device.

A runtime is an object that defines multiple callbacks used through the training, evaluation, and regular model calls. With runtimes, we can implement training in devices other than cpus or gpus with minimal changes to the user code.

Users wanting to override only a few callbacks can inherit from `ppe.runtime.PyTorchRuntime` which implements the basic functionality for cpu and gpu devices.

Runtimes must be registered by calling the `ppe.runtime.runtime_registry.register(device_name, runtime_class)` function for them to be discoverable.

Use of `ppe.to` to transfer modules and batches to custom devices

If you have defined a new runtime for a custom device the `ppe.to` function allows moving a module or a tensor to the new device by invoking the `Runtime.move_tensor` and `Runtime.move_module` when needed.

The module will be tagged by adding a attribute named `_ppe_runtime` that holds the needed runtime. It is the responsibility of the user custom runtime to perform the actual movement to the device and apply all the transformations needed to a module so it can be correctly executed.

Usually, runtime writers will need to replace the given module forward function by a new one that performs the actual device execution.

```
class MyModule(torch.nn.Module):
    def __init__(self):
        super().__init__()
        self.layer = torch.nn.Linear(10, 10)

    def forward(x):
        return self.layer(x)

class MyMagicDeviceRuntime(ppe.runtime.BaseRuntime):
    def _device_forward(self, args):
        return run_batch_in_my_device(args)

    def move_module(self, module):
        # Registers a hook to initialize the module on the first batch
        # execution
        def hook(module, *args):
            module._ppe_runtime.initialize_module(module, args)

        self.hook = module.register_forward_pre_hook(hook)
        # Change the module forward to do the computation in the device
        module.forward = self._device_forward

    def initialize_module(self, module, loader_or_batch, optimizer=None):
        create_the_module_in_my_device(module, loader_or_batch, optimizer)

# Register the runtime class
ppe.runtime.runtime_registry.register('my_device', MyMagicDeviceRuntime)

# Create a regular module
module = MyModule()
# Move the module to the device
ppe.to(module, device='my_device')

for x in my_dataloader:
    # The first iteration will create the module in the device
    # and the next ones will directly execute the module in the device instead
```

(continues on next page)

(continued from previous page)

```
# of executing the regular pytorch `forward` call.  
y = model(x)
```

Please note that this is an oversimplified description and that developing a runtime that is 100% compatible with PyTorch requires to wrap the substitute forward function with `torch.autograd.Function` among several other concerns such as `state_dict` manipulation to ensure correctness.

Runtime Registry

When creating a new Runtime class for custom needs, they need to be registered in a global `runtime_registry` object as detailed above. This object is of the `_RuntimeRegistry` type and it maintains a map of strings and Runtime types. The keys are the devices passed to `ppe.to` and the types will be the type of the Runtime object that `ppe.to` will use to treat the module or tensor. Beware that users are not supposed to interact directly with this class, only with the `runtime_registry.register` to register new runtimes.

1.2.4 CodeBlocks for Abstracting Logic Steps

The `ppe.handler.CodeBlock` API provides a mean of abstracting the actions that are possible to be done in a model in a device agnostic way.

Currently there is support for two different actions using CodeBlock.

- `:function:`ppe.handler.update_parameters <pytorch_pfn_extras.handler.update_parameters>``
takes a model, an optimizer and returns a CodeBlock object that performs the forward, backward and optimizer step at once.
- `:function:`ppe.handler.forward <pytorch_pfn_extras.handler.forward>``
takes a model and returns a CodeBlock object that performs only the forward pass.

Executing CodeBlocks

For executing CodeBlock objects we need to add an `:method:`ppe.runtime.BaseRuntime.execute <pytorch_pfn_extras.runtime.BaseRuntime.execute`` to the corresponding Runtime class. This method takes a CodeBlock and uses the information in the object to execute the CodeBlock in the device. Note that the `:method:`ppe.runtime.PyTorchRuntime.execute <pytorch_pfn_extras.runtime.PyTorchRuntime.execute`` method provides support for using PyTorch AMP with autocast or gradient scaling if needed.

Moreover, you can execute CodeBlock objects outside the training API.

```
ppe.to(model, "cuda:0")  
cblock = ppe.handler.update_parameters(model, optimizer)  
outs = cblock(input_batch)
```

The only requirement is that the associated model has been assigned a device using `ppe.to`.

1.3 Extensions

1.3.1 Extensions Manager

Extensions Manager provides an interface to extend your training loop, by integrating it into your manual training loop or Ignite.

Extensions

See the [API Reference](#) for the list of built-in extensions.

How to use

Create an `ExtensionsManager` object and then wrap the iteration of your training loop inside the `manager.run_iteration()` context manager.

An example follows:

```
import pytorch_pfn_extras as ppe
from pytorch_pfn_extras.training import extensions

import time
import math

max_epoch = 10
iters_per_epoch = 938

# manager.extend(...) also works
my_extensions = [extensions.LogReport(),
                 extensions.ProgressBar(),
                 extensions.PrintReport(['epoch', 'iteration', 'sin', 'cos'])]

models = {}
optimizers = []
manager = ppe.training.ExtensionsManager(
    models, optimizers, max_epoch,
    extensions=my_extensions,
    iters_per_epoch=iters_per_epoch)

for epoch in range(max_epoch):
    for i in range(iters_per_epoch):
        with manager.run_iteration():
            ppe.reporting.report({
                'sin': math.sin(i * 2 * math.pi / iters_per_epoch),
                'cos': math.cos(i * 2 * math.pi / iters_per_epoch),
            })
            time.sleep(0.001)
```

In the examples folder there is a mnist using all the available extensions.

Usage with Ignite

Ignite is supported by using the `IgniteExtensionsManager` with the trainer as the first argument.

The user needs to define an ignite event to report the appropriated metrics for the extensions to use them.

```
manager = ppe.training.IgniteExtensionsManager(  
    trainer, models, optimizers, epochs,  
    extensions=my_extensions)  
  
@trainer.on(Events.ITERATION_COMPLETED)  
def report_loss(engine):  
    ppe.reporting.report({'train/loss':engine.state.output})
```

Using Evaluators

Regular PyTorch

In order to report the results of the evaluation so they can be accessed by other extensions, an `Evaluation` extension needs to be created with the argument `eval_func` set to a function that gets the current data and target batches as parameters and reports the needed metrics. [Example](#)

The test function looks has the following signature

```
def test(args, model, device, data, target):
```

and is invoked once per batch in the validation dataloader. It is important to report the current validation loss or accuracy in order to the log report to see it.

```
def test(args, model, device, data, target):  
    ...  
    # Final result will be average of averages of the same size  
    test_loss += F.nll_loss(output, target, reduction='mean').item()  
    ppe.reporting.report({'val/loss': test_loss})  
    pred = output.argmax(dim=1, keepdim=True)  
    correct += pred.eq(target.view_as(pred)).sum().item()  
    ppe.reporting.report({'val/acc': correct/len(data)})
```

Ignite

Just use the `IgniteEvaluator` extension with the ignite created evaluator as the first parameter and you are ready to go. [Example](#) The metrics defined when creating the evaluator with `create_supervised_evaluator` will be automatically reported

```
create_supervised_evaluator(model, metrics={'acc': Accuracy(), 'loss': Loss(F.nll_loss)}  
                           , device)
```

Snapshots

It is possible to take snapshots by using the `snapshot` training extension just as in chainer.

Whenever the extension is triggered, it saves the status of the optimizer, model and extensions to the output folder in the same way as chainer. To load the snapshot and continue the training call `torch.load` and use the `ExtensionsManager.load_state_dict` example to resume the training. The snapshots can be used outside the pytorch-pfn-extras module just by accessing the models, or optimizers fields of the loaded state.

Extensions execution order

The supported extensions honours the chainer priorities for execution. However, when using Ignite. Chainer extensions are executed after any user-defined ignite events. The idea is to use ignite events to report the metrics of the model, and after this, Chainer extensions will be executed in the chainer defined order.

If you want to execute an event-handler in between chainer extensions, create a Chainer-like extension and access the ignite engine on the `.engine` attribute of the manager object passed as a parameter when your extension is called.

1.3.2 Creating Extensions

It is possible to create an extension just by passing a function which receives the manager object as an argument to the manager `extend` call

```
def my_extension(manager):
    print('Epoch-Iteration: {}-{}'.format(manager.epoch, manager.iteration))

manager.extend(my_extension, trigger=(1, 'iteration'))
```

It is also possible to create extensions using the `ppe.training.extension.make_extension` decorator to add a specific `trigger`, `default_name`, `priority`. In addition, `initializer`, `finalizer` and `on_error` functions can be specified as well.

```
@ppe.training.extension.make_extension(finalizer=lambda: print('done'))
def my_extension(manager):
    print('Epoch-Iteration: {}-{}'.format(manager.epoch, manager.iteration))
```

Finally, it is possible to create an extension by subclassing the `ppe.training.extensions.Extension` class as shown below.

```
import pytorch_pfn_extras as ppe

class MyExtension(ppe.training.extension.Extension):
    def __init__(self, args):
        self.args = args

    def initialize(self, manager):
        """
        Automatically called before training. Optional.
        """
        pass

    def __call__(self, manager):
        """
```

(continues on next page)

(continued from previous page)

```
Called when the associated trigger is fired.  
"""  
    print('Epoch-Iteration: {}-{}'.format(manager.epoch, manager.iteration))  
  
def state_dict(self):  
    """  
        Used to serialize the state. Optional.  
    """  
    return {'args': self.args}  
  
def load_state_dict(self, state):  
    """  
        Used to deserialize the state. Optional.  
    """  
    self.args = state['args']
```

1.3.3 Reporting

`reporting.Reporter` is used to collect values that users want to watch. The reporter object holds a mapping from value names to the actually observed values. We call this mapping observations.

When a value is passed to the reporter, an object called observer can be optionally attached. In this case, the name of the observer is added as the prefix of the value name. The observer name should be registered beforehand.

```
import pytorch_pfn_extras as ppe  
  
reporter = ppe.reporting.Reporter()  
observer = object()  
reporter.add_observer('my_observer', observer)  
observation = {}  
  
with reporter.scope(observation):  
    reporter.report({'x': 1}, observer)  
  
print(observation)  
# outputs: {my_observer/x': 1}
```

There is also a global API to add values:

```
import pytorch_pfn_extras as ppe  
  
reporter = ppe.reporting.Reporter()  
observer = object()  
reporter.add_observer('my_observer', observer)  
  
observation = {}  
with reporter:  
    with ppe.reporting.report_scope(observation):  
        ppe.reporting.report({'x': 1}, observer)  
  
print(observation)  
# outputs: {my_observer/x': 1}
```

The most important application of Reporter is to report observed values from different parts of the model in the training and validation procedures. `ExtensionsManager` objects hold their own `Reporter` object with the parameters of the target module registered as observers. `report()` can be used inside the modules to report the observed values (e.g., training loss, accuracy, activation statistics, etc.).

1.3.4 Distributed Snapshot

To take snapshots when using `torch.distributed` the only needed step is to provide the `saver_rank` keyword argument to the regular snapshot extension.

```
# saver_rank is the MPI rank which will write the actual snapshot.
snapshot = extensions.snapshot(saver_rank=saver_rank)
```

To resume the training, snapshots are loaded in every worker by using the `ExtensionsManager.load_state_dict` method, or the `extensions.snapshot autoload` keyword argument.

1.4 Utilities

1.4.1 Lazy Modules

Lazy modules can automatically infer shapes of parameters based on the shape of the data given to the first forward invocation.

Following modules are provided:

- `ppe.nn.LazyBatchNorm1d`, `ppe.nn.LazyBatchNorm2d`, `ppe.nn.LazyBatchNorm3d`
 - Module that behaves as `torch.nn.BatchNorm[123]d` but `num_features` can be set to None.
 - These modles are now included as a part of PyTorch 1.9 release (`torch.nn.LazyBatchNormXd`, pull-request).

The following modules are now considered deprecated as now included as a part of PyTorch 1.8 release:

- `ppe.nn.LazyLinear`
 - Module that behaves as `torch.nn.Linear` but `in_features` can be set to None.
 - PyTorch-native implementation: (`torch.nn.LazyLinear`, pull-request)
- `ppe.nn.LazyConv1d`, `ppe.nn.LazyConv2d`, `ppe.nn.LazyConv3d`
 - Module that behaves as `torch.nn.Conv[123]d` but `in_channels` can be set to None.
 - PyTorch-native implementation: (`torch.nn.LazyConvXd`, pull-request)

Now that all lazy modules are merged to the upstream, we encourage you to migrate to PyTorch's lazy modules. We will keep these implementaions only for backward compatibility.

Note that you need to run a “dummy” forward to initialize lazy parameters. See the example below:

```
import torch
import torch.nn.functional as F

import pytorch_pfn_extras as ppe

class Net(torch.nn.Module):
```

(continues on next page)

(continued from previous page)

```

def __init__(self):
    super().__init__()
    self.conv1 = ppe.nn.LazyConv2d(None, 20, 5, 1)
    self.conv2 = ppe.nn.LazyConv2d(None, 50, 5, 1)
    self.fc1 = ppe.nn.LazyLinear(None, 500)
    self.fc2 = ppe.nn.LazyLinear(None, 10)

def forward(self, x):
    x = F.relu(self.conv1(x))
    x = F.max_pool2d(x, 2, 2)
    x = F.relu(self.conv2(x))
    x = F.max_pool2d(x, 2, 2)
    x = x.flatten(start_dim=1)
    x = F.relu(self.fc1(x))
    x = self.fc2(x)
    return F.log_softmax(x, dim=1)

model = Net()

# Initialize lazy parameters.
dummy_input = ...
model(dummy_input)

# Pass parameters to the optimizer.
optimizer = torch.optim.SGD(
    model.parameters(), lr=args.lr, momentum=args.momentum)

# Run training loop.
# ...

```

You need to run a dummy forward before passing parameters to optimizers; otherwise optimizers cannot refer to lazily-initialized parameters. You will get a warning if you pass uninitialized lazy parameters to optimizers:

```

>>> model = ppe.nn.LazyLinear(None, 10)
>>> optimizer = torch.optim.SGD(model.parameters(), lr=0.1)
.../pytorch-pfn-extras/pytorch_pfn_extras/nn/modules/lazy.py:127: UserWarning:
  Use of uninitialized lazy parameter in Optimizer has been detected.
  Maybe you forgot to run forward before passing `module.parameters()` to the
  optimizer?

```

- *Config*
 - *Basic*
 - *Substitution*
 - * *Callable Substitution*
 - * *Substitution by Path*
 - * *Substitution by Attribute*
 - * *Default Value by Path Substitution*
 - * *Ignore Substitution*

* *Lazy Evaluation*

1.4.2 Config

Basic

```
from pytorch_pfn_extras.config import Config
import yaml
pre_eval_config = yaml.load('''
foo:
    bar: 'bar_value'
    ls:
        - 'first'
        - key0: 'value0'
          key1: 'value1'
baz: 'baz_value'
''')
config = Config(pre_eval_config)
```

Accessing config values:

```
print(config['/foo/ls/0'])
# 'first'
print(config['/foo/ls/1/key0'])
# 'value0'
print(config['/foo/ls'])
# ['first', {'key0': 'value0', 'key1': 'value1'}]
print(config['/baz'])
# 'baz_value'
```

Substitution

Callable Substitution

You could replace a value as the return value of a callable.

- `types` is an additional input to `Config`. `types` is a mapping from a callable's name to the actual callable.
- A sub-dictionary containing the key `type` invokes callable substitution.

```
pre_eval_config = yaml.load('''
name:
    type: concat
    x0: 'First'
    x1: 'Last'
''')

types = {
    'concat': lambda x0, x1: x0 + ' ' + x1
}

config = Config(pre_eval_config, types)
```

(continues on next page)

(continued from previous page)

```
# the value returned by
# concat(x0='First', x1='Last')
print(config['/name'])
# 'First Last'
```

Nested

```
pre_eval_config = yaml.load('''
name:
  type: concat
  x0: 'First'
  x1:
    type: concat
    x0: 'Middle'
    x1: 'Last'
''')
types = {
  'concat': lambda x0, x1: x0 + ' ' + x1
}
config = Config(pre_eval_config, types)
print(config['/name'])
# First Middle Last
```

Class

```
pre_eval_config = yaml.load('''
dataset:
  type: Dataset
  n_class: 10
''')

class Dataset(object):

  def __init__(self, n_class):
    self.n_class = n_class

types = {
  'Dataset': Dataset,
}

config = Config(pre_eval_config, types)
print(isinstance(config['/dataset'], Dataset))
# True
```

Substitution by Path

Absolute

@/absolute/path is replaced by the value at /absolute/path.

```
pre_eval_config = yaml.load('''
foo: 'FOO'
boo:
  baz: '@/foo'
''')
config = Config(pre_eval_config)
print(config['/boo/baz'])
# FOO
```

Relative

Relative path is also possible using @relative/path.

```
pre_eval_config = yaml.load('''
foo: 'FOO'
boo:
  baz: '@../foo'
''')
config = Config(pre_eval_config)
print(config['/boo/baz'])
# FOO
```

Substitution by Attribute

@/path/to/obj.attr_name is replaced by:

1. Use substitution by path to get an object at /path/to/obj.
2. Replace the config value by getattr(obj, attr_name), where obj is obtained at step 1.

```
pre_eval_config = yaml.load('''
dataset:
  type: Dataset
  n_class: 10
n_data: '@/dataset.n_data'
''')

class Dataset(object):

  def __init__(self, n_class):
    self.n_class = n_class
    self.n_data = 4

types = {
  'Dataset': Dataset,
```

(continues on next page)

(continued from previous page)

```
}
```

```
config = Config(pre_eval_config, types)
print(config['/n_data'])
# 4
```

Default Value by Path Substitution

`customize_type` is a decorator that sets default argument values by path substitution.

```
from pytorch_pfn_extras.config import customize_type

pre_eval_config = yaml.load('''
dataset:
    type: Dataset
n_class: 5
''')

# If n_class is not passed, the value would be config[/n_class].
# Both absolute and relative paths are allowed.
@customize_type(n_class='/n_class')
class Dataset(object):

    def __init__(self, n_class):
        self.n_class = n_class

types = {
    'Dataset': Dataset,
}

config = Config(pre_eval_config, types)
print(config['/dataset'].n_class)
# 5
```

Ignore Substitution

Access using `config['!/path']` instead of `config['/path']`.

```
pre_eval_config = yaml.load('''
name:
    type: concat
    x0: 'First'
    x1: 'Last'
''')

types = {
    'concat': lambda x0, x1: x0 + ' ' + x1
}
```

(continues on next page)

(continued from previous page)

```
config = Config(pre_eval_config, types)
print(config['!/name'])
# {'type': 'concat', 'x0': 'First', 'x1': 'Last'}
```

Lazy Evaluation

Callable substitution is lazily executed. This means that callables that are not dependent on the accessed value do not get executed.

```
pre_eval_config = yaml.load('''
foo:
  - type: f0
  - '@/bar'
bar:
  type: f1
baz:
  type: f2
''')

def f0():
    print('f0 called')
    return 'f0_return'

def f1():
    print('f1 called')
    return 'f1_return'

def f2():
    print('f2 called')
    return 'f2_return'

types = {
    'f0': f0,
    'f1': f1,
    'f2': f2,
}

config = Config(pre_eval_config, types)
config['/foo']  # f2 does not get called
# f0 called
# f1 called
```

1.4.3 pytorch_pfn_extras.onnx

Extensions to `torch.onnx.export`.

Installation

```
pip3 install "pytorch-pfn-extras[onnx]"
```

Or

1. Install pytorch-pfn-extras normally
2. Install onnx with `pip install onnx==1.7.0`

API

`pytorch_pfn_extras.onnx.export_testcase`

Instead of specifying file name in `torch.onnx.export`, `pytorch_pfn_extra.onnx.export_testcase` specifies directory to output ONNX model and test case in/out.

```
import torch
import torch.nn as nn
model = nn.Sequential(nn.Linear(5, 10, bias=False))
x = torch.zeros((2, 5))

import pytorch_pfn_extras.onnx as tou
tou.export_testcase(model, x, '/path/to/output')
```

Directory structure with following will be generated to `/path/to/output`:

```
$ tree /path/to/output
/path/to/output
├── meta.json
├── model.onnx
└── test_data_set_0
    ├── input_0.pb
    └── output_0.pb
```

- This directory structure format is inspired by ONNX official test data set: (Example: [node](#)). PyTorch's ONNX tests use this format too. (Reference: `export_onnx_tests_generator.py`)
 - There are scripts in `chainer-compiler/utils` to run inference in major runtime with the directory structure. For example to inference with ONNXRuntime, run `$ python run_onnx_onnxruntime.py /path/to/output` to use `input_N.pb` as input and compare numerically with its output `output_N.pb`(N is the index of test case).
- By default `meta.json` is generated too to track git infos, date times, etc. Add `metadata=False` argument to suppress this.

out_grad option

If `out_grad=True` is specified gradient will be dumped too, which is useful for debugging backward. `gradient_N.pb` and `gradient_input_N.pb` would be dumped to test case directory with in/out data. `gradient_input_N.pb` is the initial value of backward, and it's default value is ones tensor with same shape of output. Use `out_grad` to specify custom initial value (`torch.Tensor` type) for it.

```
model = nn.Sequential(nn.Linear(5, 10, bias=False))
x = torch.zeros((5))

import pytorch_pfn_extras.onnx as tou
tou.export_testcase(model, x, '/path/to/output', out_grad=True)
```

```
$ tree /path/to/output
/path/to/output
├── meta.json
└── model.onnx
    └── test_data_set_0
        ├── gradient_0.pb
        ├── gradient_input_0.pb
        ├── input_0.pb
        └── output_0.pb
```

model_overwrite option

Use `model_overwrite` option to create multiple data set like following:

```
import pytorch_pfn_extras.onnx as tou
tou.export_testcase(model, x1, '/path/to/output')
tou.export_testcase(model, x2, '/path/to/output', model_overwrite=False)
```

Following is the generated test cases of the above. `test_data_set_0` is the input `x1` and its output, `test_data_set_1` is the input `x2` and its output.

```
$ tree /path/to/output
/path/to/output
├── meta.json
└── model.onnx
    └── test_data_set_0
        ├── input_0.pb
        └── output_0.pb
    └── test_data_set_1
        ├── input_0.pb
        └── output_0.pb
```

strip_large_tensor_data option

This option strips large tensor in dumped files which is useful to reduce file size in usage such as benchmarking. Not only `model.onnx`, in/out, gradient data would be affected too. `large_tensor_threshold` could be used to specify threshold of large tensor size.

```
import torchvision
model = torchvision.models.resnet50(pretrained=True)
x = torch.zeros((1, 3, 224, 224))

import pytorch_pfn_extras.onnx as tou
tou.export_testcase(model, x, '/path/to/output')
tou.export_testcase(model, x, '/path/to/output2', strip_large_tensor_data=True)
```

```
$ ls -lh /path/to/output/model.onnx
-rwxrwxrwx 1 user user 98M Jun 24 23:34 /path/to/output/model.onnx
$ ls -lh /path/to/output2/model.onnx
-rwxrwxrwx 1 user user 64K Jun 24 23:34 /path/to/output2/model.onnx
```

This feature could be called from CLI:

```
$ python -m pytorch_pfn_extras.onnx.strip_large_tensor resnet50.onnx --out_onnx_path_
˓resnet50_slim.onnx
$ ls -lh
-rwxrwxrwx 1 user user 98M Jun 30 09:13 resnet50.onnx
-rwxrwxrwx 1 user user 64K Jun 30 09:16 resnet50_slim.onnx
```

See `$ python -m pytorch_pfn_extras.onnx.strip_large_tensor -h` for help

Notes:

If an ONNX runtime does not support no `raw_data` tensor, `unstrip_tensor.py` will resolve. See `$ python -m pytorch_pfn_extras.onnx.unstrip_tensor -h` for help

`pytorch_pfn_extras.onnx.export`

Function with same interface like `torch.onnx.export`. Unlike `torch.onnx.export`, you can use annotation feature (described below), `strip_large_tensor_data` options, or other `torch.onnx` extensions.

- `strip_large_tensor_data`: Same as `export_TestCase`. Useful reducing file sizes.
- `return_output`: Returns output value of model execution. Note: Most output type would be `torch.Tensor`(not `onnx.TensorProto`)

```
model = nn.Sequential(nn.Linear(5, 10, bias=False))
x = torch.zeros((2, 5))

import io, onnx
bytesio = io.BytesIO()
pytorch_pfn_extras.onnx.export(model, x, bytesio)
onnx_proto = onnx.load(io.BytesIO(bytesio.getvalue()))
```

annotate

Feature to add custom ONNX attribute to specified `nn.Module`.

Notes:

- Annotated ONNX would be invalid ONNX format that doesn't pass check of `onnx.checker.check_model`.
- Only valid with `pytorch_pfn_extras.onnx.export_testcase` or `pytorch_pfn_extras.onnx.export`.
- **Only** the first ONNX node of modules like `nn.Linear`, `nn.GroupNorm`, etc. with multiple ONNX node would be annotated
 - For example `nn.Linear` with bias is split to `MatMul` -> `Add` graph. Only `MatMul` would be annotated. This is same in `apply_annotation` (described later) too.
- Use `apply_annotation` instead when the annotation target isn't `nn.Module`.

```
import pytorch_pfn_extras.onnx as tou

class Net(nn.Module):
    def __init__(self):
        super(Net, self).__init__()

        self.conv = nn.Conv2d(6, 9, 3)
        self.conv2 = nn.Conv2d(9, 12, 3)
        self.linear = nn.Linear(28, 20)
        self.linear2 = nn.Linear(20, 15)

    def forward(self, x):
        h = self.conv(x)
        with tou.annotate(key='value'):
            h = self.conv2(h)
            h = self.linear(h)
        h = self.linear2(h)
        return h

model = Net()
x = torch.randn((1, 6, 32, 32))
tou.export_testcase(model, x, '/path/to/output')
onnx_proto = onnx.load(os.path.join('/path/to/output', 'model.onnx'))
print(onnx.helper.printable_graph(onnx_proto.graph))
```

```
graph torch-jit-export (
    %input.1[FLOAT, 1x6x32x32]
) initializers (
    %17[FLOAT, 28x20]
    %18[FLOAT, 20x15]
    %conv.bias[FLOAT, 9]
    %conv.weight[FLOAT, 9x6x3x3]
    %conv2.bias[FLOAT, 12]
    %conv2.weight[FLOAT, 12x9x3x3]
    %linear.bias[FLOAT, 20]
    %linear2.bias[FLOAT, 15]
) {
```

(continues on next page)

(continued from previous page)

```
%9 = Conv[dilations = [1, 1], group = 1, kernel_shape = [3, 3], pads = [0, 0, 0, 0],  
→ strides = [1, 1]](%input.1, %conv.weight, %conv.bias)  
%10 = Conv[dilations = [1, 1], group = 1, kernel_shape = [3, 3], key = 'value', pads =  
→ [0, 0, 0, 0], strides = [1, 1]](%9, %conv2.weight, %conv2.bias)  
%12 = MatMul[key = 'value'](%10, %17)  
%13 = Add(%12, %linear.bias)  
%15 = MatMul(%13, %18)  
%16 = Add(%15, %linear2.bias)  
return %16  
}
```

In above example `%10 = Conv` and `%12 = MatMul` has `key='value'` attribute annotated.

apply_annotation

This annotates function call instead of annotating it with `with`.

The annotate target is `nn.Module`, so `torch.nn.functional` couldn't be annotated

```
import torch.nn.functional as F
import pytorch_pfn_extras.onnx as tou

class Net(nn.Module):
    def __init__(self):
        super(Net, self).__init__()

        self.conv = nn.Conv2d(6, 9, 3)
        self.conv2 = nn.Conv2d(9, 12, 3)
        self.linear = nn.Linear(28, 20)
        self.linear2 = nn.Linear(20, 15)

    def forward(self, x):
        h = self.conv(x)
        with tou.annotate(key='value'):
            h = self.conv2(h)
            h = F.relu(h)
            h = self.linear(h)
        h = self.linear2(h)
        return h

model = Net()
x = torch.randn((1, 6, 32, 32))
tou.export_testcase(model, x, '/path/to/output')
onnx_proto = onnx.load(os.path.join('/path/to/output', 'model.onnx'))
print(onnx.helper.printable_graph(onnx_proto.graph))
```

```
graph torch-jit-export (
    %input.1[FLOAT, 1x6x32x32]
) initializers (
    %18[FLOAT, 28x20]
    %19[FLOAT, 20x15]
```

(continues on next page)

(continued from previous page)

```
%conv.bias[FLOAT, 9]
%conv.weight[FLOAT, 9x6x3x3]
%conv2.bias[FLOAT, 12]
%conv2.weight[FLOAT, 12x9x3x3]
%linear.bias[FLOAT, 20]
%linear2.bias[FLOAT, 15]
)
{
%9 = Conv[dilations = [1, 1], group = 1, kernel_shape = [3, 3], pads = [0, 0, 0, 0],  

→ strides = [1, 1]](%input.1, %conv.weight, %conv.bias)
%10 = Conv[dilations = [1, 1], group = 1, kernel_shape = [3, 3], key = 'value', pads =  

→ [0, 0, 0, 0], strides = [1, 1]](%9, %conv2.weight, %conv2.bias)
%11 = Relu(%10)
%13 = MatMul[key = 'value'](%11, %18)
%14 = Add(%13, %linear.bias)
%16 = MatMul(%14, %19)
%17 = Add(%16, %linear2.bias)
return %17
}
```

%10 = Conv and %13 = MatMul has key='value' attribute but %11 = Relu hasn't. By using apply_annotation all node in the function is annotated.

```
import pytorch_pfn_extras.onnx as tou

class Net(nn.Module):
    def __init__(self):
        super(Net, self).__init__()

        self.conv = nn.Conv2d(6, 9, 3)
        self.conv2 = nn.Conv2d(9, 12, 3)
        self.linear = nn.Linear(28, 20)
        self.linear2 = nn.Linear(20, 15)

    def forward(self, x):
        h = self.conv(x)
        def _f(x):
            h = self.conv2(x)
            h = F.relu(h)
            h = self.linear(h)
            return h
        h = tou.apply_annotation(_f, h, key='value')
        h = self.linear2(h)
        return h

model = Net()
x = torch.randn((1, 6, 32, 32))
tou.export_testcase(model, x, '/path/to/outout')
onnx_proto = onnx.load(os.path.join('/path/to/output', 'model.onnx'))
print(onnx.helper.printable_graph(onnx_proto.graph))
```

```
graph torch-jit-export (
    %input.1[FLOAT, 1x6x32x32]
```

(continues on next page)

(continued from previous page)

```

) initializers (
    %18[FLOAT, 28x20]
    %19[FLOAT, 20x15]
    %conv.bias[FLOAT, 9]
    %conv.weight[FLOAT, 9x6x3x3]
    %conv2.bias[FLOAT, 12]
    %conv2.weight[FLOAT, 12x9x3x3]
    %linear.bias[FLOAT, 20]
    %linear2.bias[FLOAT, 15]
)
{
    %9 = Conv[dilations = [1, 1], group = 1, kernel_shape = [3, 3], pads = [0, 0, 0, 0], ↵
    ↵strides = [1, 1]](%input.1, %conv.weight, %conv.bias)
    %10 = Conv[dilations = [1, 1], group = 1, kernel_shape = [3, 3], key = 'value', pads = ↵
    ↵[0, 0, 0, 0], strides = [1, 1]](%9, %conv2.weight, %conv2.bias)
    %11 = Relu[key = 'value'](%10)
    %13 = MatMul[key = 'value'](%11, %18)
    %14 = Add(%13, %linear.bias)
    %16 = MatMul(%14, %19)
    %17 = Add(%16, %linear2.bias)
    return %17
}

```

Now %11 = Relu is annotated with key='value' attribute too.

scoped_anchor

This annotates scope's beginning and end of one or modules by adding Anchor node. Node would be named Anchor_N_start or Anchor_N_end (N is a index) and with op_type Identity.

- Adding custom parameter would add ONNX attribute and this will generate invalid ONNX in checker.
- Use this with `pytorch_pfn_extras.onnx.export_testcase` or `pytorch_pfn_extras.onnx.export`.
- When scope has multiple input/output only first input/output will get Anchor node added.
- N of node name is the index of pair beginning/end Anchor node like `Anchor_0_start`, `Anchor_0_end`.

```

import pytorch_pfn_extras.onnx as tou

class Net(nn.Module):
    def __init__(self):
        super(Net, self).__init__()

        self.conv = nn.Conv2d(6, 9, 3)
        self.conv2 = nn.Conv2d(9, 12, 3)
        self.linear = nn.Linear(28, 20)
        self.linear2 = nn.Linear(20, 15)

    def forward(self, x):
        h = self.conv(x)
        with tou.scoped_anchor(key='value'):
            h = self.conv2(h)
            h = self.linear(h)

```

(continues on next page)

(continued from previous page)

```

    h = self.linear2(h)
    return h

    def forward(self, x):
        with annotate(key='value'):
            return self.add(x)

model = Net()
x = torch.randn((1, 6, 32, 32))
out_dir = tou.export_testcase(model, x, '/path/to/output')
onnx_proto = onnx.load(os.path.join('/path/to/output', 'model.onnx'))
print(onnx.helper.printable_graph(onnx_proto.graph))

```

```

graph torch-jit-export (
    %input.1[FLOAT, 1x6x32x32]
) initializers (
    %23[FLOAT, 28x20]
    %24[FLOAT, 20x15]
    %conv.bias[FLOAT, 9]
    %conv.weight[FLOAT, 9x6x3x3]
    %conv2.bias[FLOAT, 12]
    %conv2.weight[FLOAT, 12x9x3x3]
    %linear.bias[FLOAT, 20]
    %linear2.bias[FLOAT, 15]
) {
    %9 = Conv[dilations = [1, 1], group = 1, kernel_shape = [3, 3], pads = [0, 0, 0, 0],  

    ↵ strides = [1, 1]](%input.1, %conv.weight, %conv.bias)
    %11 = Identity[key = 'value'](%9)
    %12 = Conv[dilations = [1, 1], group = 1, kernel_shape = [3, 3], pads = [0, 0, 0, 0],  

    ↵ strides = [1, 1]](%11, %conv2.weight, %conv2.bias)
    %16 = MatMul(%12, %23)
    %17 = Add(%16, %linear.bias)
    %19 = Identity[key = 'value'](%17)
    %21 = MatMul(%19, %24)
    %22 = Add(%21, %linear2.bias)
    return %22
}

```

%11 = Identity (node name = Anchor_0_start) and %19 = Identity (node name = Anchor_0_end) is added.
key='value' is added as ONNX attribute.

non-nn.Module

The target of scope is only nn.Module. You can add adding sub nn.Module instead, if scope bound doesn't match nn.Module.

```

import pytorch_pfn_extras.onnx as tou

class Net(nn.Module):
    def __init__(self):
        super(Net, self).__init__()

```

(continues on next page)

(continued from previous page)

```

class _Net(nn.Module):
    def forward(self, x):
        return x + torch.ones((1,))
    self.add = _Net()

    def forward(self, x):
        with tpu.scoped_anchor(key='value'):
            return self.add(x)

model = Net()
x = torch.randn((1, 6, 32, 32))
out_dir = tpu.export_testcase(model, x, '/path/to/output')
onnx_proto = onnx.load(os.path.join('/path/to/output', 'model.onnx'))
print(onnx.helper.printable_graph(onnx_proto.graph))

```

```

graph torch-jit-export (
    %x.1[FLOAT, 1x6x32x32]
) {
    %2 = Identity[key = 'value'](x.1)
    %3 = Constant[value = <Tensor>]()
    %4 = Add(%2, %3)
    %6 = Identity[key = 'value'](%4)
    return %6
}

```

Or you can use anchor (described below) instead.

anchor (Future work)

Inserts Anchor node per each arbitrarily position of `nn.Module`. Node name would be Anchor and op_type would be Identity.

- Note: adding extra parameter would make extended ONNX format because it would be attribute.
- Please use it with `pytorch_pfn_extras.onnx.export_testcase` or `pytorch_pfn_extras.onnx.export`.

1.4.4 CUDA (CuPy Interoperability)

- `pytorch_pfn_extras.cuda.stream(stream)`
 - Context-manager that selects a given stream. This context manager also changes the CuPy's default stream if CuPy is available. When CuPy is not available, the functionality is the same as the PyTorch's counterpart, `torch.cuda.stream()`.
- `pytorch_pfn_extras.cuda.use_torch_mempool_in_cupy()`
 - Use PyTorch's memory pool in CuPy. If you want to use PyTorch's memory pool and non-default CUDA streams, streams must be created and managed using PyTorch (using `torch.cuda.Stream()` and `pytorch_pfn_extras.cuda.stream(stream)`). This feature requires CuPy v8.0+ and PyTorch v1.5+.
- `pytorch_pfn_extras.cuda.use_default_mempool_in_cupy()`
 - Use CuPy's default memory pool in CuPy.

- `pytorch_pfn_extras.from_ndarray(ndarray)`
 - Creates a Tensor from NumPy/CuPy ndarray.
- `pytorch_pfn_extras.as_ndarray(tensor)`
 - Creates a NumPy/CuPy ndarray from Tensor.
- `pytorch_pfn_extras.get_xp(tensor_device_or_ndarray)`
 - Returns `numpy` or `cupy` module for the given object.
- `pytorch_pfn_extras.as_numpy_dtype(torch_dtype)`
 - Returns NumPy dtype for the given torch dtype.
- `pytorch_pfn_extras.from_numpy_dtype(numpy_dtype)`
 - Returns torch dtype for the given NumPy dtype.

API REFERENCE

- genindex

2.1 Package

`pytorch_pfn_extras`

2.1.1 pytorch_pfn_extras

Functions

<code>pytorch_pfn_extras.as_ndarray(tensor)</code>	Creates a <code>numpy.ndarray</code> or <code>cupy.ndarray</code> from <code>torch.Tensor</code> .
<code>pytorch_pfn_extras.as_numpy_dtype(torch_dtype)</code>	Returns NumPy dtype for the given PyTorch dtype.
<code>pytorch_pfn_extras.compile(module[, ...])</code>	Compiles a module and an optimizer in a single graph using the provided backend.
<code>pytorch_pfn_extras.from_ndarray(ndarray)</code>	Creates a <code>torch.Tensor</code> from a <code>numpy.ndarray</code> or <code>cupy.ndarray</code> .
<code>pytorch_pfn_extras.from_numpy_dtype(numpy_dtype)</code>	Returns PyTorch dtype for the given NumPy dtype.
<code>pytorch_pfn_extras.get_xp(obj)</code>	Returns a module of ndarray implementation (<code>numpy</code> or <code>cupy</code>) for the given <code>obj</code> .
<code>pytorch_pfn_extras.map(func, iterable[, ...])</code>	
<code>pytorch_pfn_extras.requires(version[, package])</code>	
<code>pytorch_pfn_extras.to(module_or_tensor, ...)</code>	A function to transfer the given object to the given device.

[pytorch_pfn_extras.as_ndarray](#)

`pytorch_pfn_extras.as_ndarray(tensor)`

Creates a `numpy.ndarray` or `cupy.ndarray` from `torch.Tensor`.

This method returns a tensor as a NumPy or CuPy ndarray depending on where the given `tensor` resides in. The `tensor` and the returned `ndarray` share the same underlying storage. Changes to the tensor will be reflected in the `ndarray` and vice versa. Note that changes made to `ndarray` cannot be tracked in the computational graph.

Parameters

`tensor (Tensor) –`

Return type

`Any`

[pytorch_pfn_extras.as_numpy_dtype](#)

`pytorch_pfn_extras.as_numpy_dtype(torch_dtype)`

Returns NumPy dtype for the given PyTorch dtype.

Parameters

`torch_dtype (dtype) – PyTorch’s dtype object.`

Returns

`NumPy type object.`

Return type

`Any`

[pytorch_pfn_extras.compile](#)

`pytorch_pfn_extras.compile(module, optimizer=None, backend=None)`

Compiles a module and an optimizer in a single graph using the provided backend.

Note: The backend object needs to be a callable accepting a `torch.fx.GraphModule` and a list of `torch.Tensor` and return a Callable as specified by <https://pytorch.org/docs/2.0/dynamo/custom-backends.html#custom-backends>

Note: Modules that are split in multiple graphs are not supported. `torch.compiled` is called with the `fullgraph=True` argument.

Parameters

- `module (Module) –` `torch.nn.Module` to be compiled
- `optimizer (Optional[Optimizer]) –` Optimizer object associated to the module. It will be traced and its operations included in the module graph. Some dry run operations may be performed to fully initialize the optimizer status.
- `backend (optional) –` Object to process the graph and compile it for custom devices, will use PyTorch dynamo by default if not specified.

Return type

`Callable[[...], Any]`

pytorch_pfn_extras.from_ndarray

`pytorch_pfn_extras.from_ndarray(ndarray)`

Creates a `torch.Tensor` from a `numpy.ndarray` or `cupy.ndarray`.

Unlike `torch.from_numpy`, this method may make a copy when needed, e.g. when the given `ndarray` contains the negative strides which is not supported by PyTorch.

Parameters

`ndarray (Any) –`

Return type

`Tensor`

pytorch_pfn_extras.from_numpy_dtype

`pytorch_pfn_extras.from_numpy_dtype(numpy_dtype)`

Returns PyTorch dtype for the given NumPy dtype.

Parameters

`numpy_dtype (Any) – NumPy’s dtype object.`

Returns

PyTorch type object.

Return type

`dtype`

pytorch_pfn_extras.get_xp

`pytorch_pfn_extras.get_xp(obj)`

Returns a module of ndarray implementation (`numpy` or `cupy`) for the given `obj`.

The `obj` can be `torch.Tensor`, `torch.device` or NumPy/CuPy `ndarray`.

Parameters

`obj (Union[Any, Tensor]) –`

Return type

`Any`

pytorch_pfn_extras.map

`pytorch_pfn_extras.map(func, iterable, out_keys=None, device='cpu')`

Parameters

- `func (Callable[[Any], Any]) –`
- `iterable (Sequence[Any]) –`
- `out_keys (Optional[Set[str]]) –`
- `device (Any) –`

Return type

`Sequence[Any]`

[pytorch_pfn_extras.requires](#)

`pytorch_pfn_extras.requires(version, package='torch')`

Parameters

- **version** (*str*) –
- **package** (*str*) –

Return type

`bool`

[pytorch_pfn_extras.to](#)

`pytorch_pfn_extras.to(module_or_tensor, device, *, options=None, runtime_class=None, config=None)`

A function to transfer the given object to the given device.

If PyTorch’s device type is given as the `device` argument, the behavior of this function is equivalent to `module_or_tensor.to(module_or_tensor, device)`.

Otherwise, this function uses the **Runtime** mechanism. This function looks for the Runtime for the device from the `RuntimeRegistry` and delegates the actual transfer operation to it.

See also the documentation of `ppe.runtime.BaseRuntime` for details.

Parameters

- **module_or_tensor** (`torch.nn.Module or torch.Tensor`) – An object to be transferred.
- **device** (`torch.device or str`) – The device that the input object is transferred to.
- **options** (`dict, optional`) – An options of dictionary type that is passed to `runtime_class.__init__` as an argument.
- **runtime_class** (`Optional[Type[BaseRuntime]]`) – A runtime class inherited from `BaseRuntime` class. If `None`, a runtime class is automatically selected based on the `device` argument from the runtime registry.
- **config** (`dict, optional`) – DEPRECATED. Use `options`.

Returns

A `torch.Tensor` with the specified device.

Return type

`ModuleOrTensor`

Modules

`pytorch_pfn_extras.config`

`pytorch_pfn_extras.config_types`

`pytorch_pfn_extras.cuda`

`pytorch_pfn_extras.dataloaders`

`pytorch_pfn_extras.dataset`

`pytorch_pfn_extras.distributed`

`pytorch_pfn_extras.engine`

`pytorch_pfn_extras.handler`

`pytorch_pfn_extras.logging`

`pytorch_pfn_extras.nn`

`pytorch_pfn_extras.onnx`

`pytorch_pfn_extras.profiler`

`pytorch_pfn_extras.reporting`

`pytorch_pfn_extras.runtime`

`pytorch_pfn_extras.testing`

`pytorch_pfn_extras.torchscript`

`pytorch_pfn_extras.training`

`pytorch_pfn_extras.utils`

`pytorch_pfn_extras.writing`

pytorch_pfn_extras.config**Functions**

`pytorch_pfn_extras.config.
customize_type(...)`

[pytorch_pfn_extras.config.customize_type](#)

```
pytorch_pfn_extras.config.customize_type(**default_kwargs)
```

Parameters

`default_kwargs (Any) –`

Return type

`Callable[[Callable[[...], Any]], Callable[[...], Any]]`

Classes

```
pytorch_pfn_extras.config.Config(config[,  
types])
```

[pytorch_pfn_extras.config.Config](#)

```
class pytorch_pfn_extras.config.Config(config, types=None)  
Bases: object
```

Methods

```
__init__(config[, types])
```

```
load_path(path, *[, loader, types])
```

```
update_via_args(args)
```

Parameters

- `config (Any) –`
- `types (Optional[Mapping[str, Callable[[...], Any]]]) –`

```
__init__(config, types=None)
```

Parameters

- `config (Any) –`
- `types (Optional[Mapping[str, Callable[[...], Any]]]) –`

Return type

`None`

```
classmethod load_path(path, *, loader=None, types=None)
```

Parameters

- `path (str) –`
- `loader (Optional[Callable[[str], Any]]) –`
- `types (Optional[Mapping[str, Callable[[...], Any]]]) –`

Return type
Config

update_via_args(args)

Parameters
args (*Sequence[Tuple[str, Any]]*) –

Return type
None

pytorch_pfn_extras.config_types

Functions

`pytorch_pfn_extras.config_types.`
`load_path_with_optuna_types(...)`

`pytorch_pfn_extras.config_types.`
`optuna_types(trial)`

pytorch_pfn_extras.config_types.load_path_with_optuna_types

`pytorch_pfn_extras.config_types.load_path_with_optuna_types(path, trial, loader=None,`
`types=None)`

Parameters

- **path** (*str*) –
- **trial** (*optuna.trial.Trial*) –
- **loader** (*Optional[Callable[[str], Any]]*) –
- **types** (*Optional[Dict[str, Callable[..., Any]]]*) –

Return type
Config

pytorch_pfn_extras.config_types.optuna_types

`pytorch_pfn_extras.config_types.optuna_types(trial)`

Parameters
trial (*optuna.trial.Trial*) –

Return type
Dict[str, Any]

[pytorch_pfn_extras.cuda](#)

Functions

<code>pytorch_pfn_extras.cuda.stream(stream)</code>	Context-manager that selects a given stream.
<code>pytorch_pfn_extras.cuda.use_default_mempool_in_cupy()</code>	Use the default memory pool in CuPy.
<code>pytorch_pfn_extras.cuda.use_torch_mempool_in_cupy()</code>	Use the PyTorch memory pool in CuPy.

[pytorch_pfn_extras.cuda.stream](#)

`pytorch_pfn_extras.cuda.stream(stream)`

Context-manager that selects a given stream.

This context manager also changes the CuPy’s default stream if CuPy is available. When CuPy is not available, the functionality is the same as the PyTorch’s counterpart, `torch.cuda.stream()`.

Parameters

`stream (Optional[Stream]) –`

Return type

`Generator[None, None, None]`

[pytorch_pfn_extras.cuda.use_default_mempool_in_cupy](#)

`pytorch_pfn_extras.cuda.use_default_mempool_in_cupy()`

Use the default memory pool in CuPy.

Return type

`None`

[pytorch_pfn_extras.cuda.use_torch_mempool_in_cupy](#)

`pytorch_pfn_extras.cuda.use_torch_mempool_in_cupy()`

Use the PyTorch memory pool in CuPy.

If you want to use PyTorch’s memory pool and non-default CUDA streams, streams must be created and managed using PyTorch (using `torch.cuda.Stream()` and `pytorch_pfn_extras.cuda.stream(stream)`).

Return type

`None`

pytorch_pfn_extras.dataloaders

Classes

<code>pytorch_pfn_extras.dataloaders. DataLoader(dataset)</code>	Data loader.
--	--------------

pytorch_pfn_extras.dataloaders.DataLoader

```
class pytorch_pfn_extras.dataloaders.DataLoader(dataset, batch_size=1, shuffle=None, sampler=None,  
                                                batch_sampler=None, num_workers=0,  
                                                collate_fn=None, pin_memory=False,  
                                                drop_last=False, timeout=0, worker_init_fn=None,  
                                                multiprocessing_context=None, generator=None, *,  
                                                prefetch_factor=None, persistent_workers=False,  
                                                pin_memory_device="")
```

Bases: `Generic[T_co]`

Data loader. Combines a dataset and a sampler, and provides an iterable over the given dataset.

The `DataLoader` supports both map-style and iterable-style datasets with single- or multi-process loading, customizing loading order and optional automatic batching (collation) and memory pinning.

See `torch.utils.data` documentation page for more details.

Parameters

- **dataset** (`Dataset`) – dataset from which to load the data.
- **batch_size** (`int, optional`) – how many samples per batch to load (default: 1).
- **shuffle** (`bool, optional`) – set to True to have the data reshuffled at every epoch (default: False).
- **sampler** (`Sampler or Iterable, optional`) – defines the strategy to draw samples from the dataset. Can be any `Iterable` with `__len__` implemented. If specified, `shuffle` must not be specified.
- **batch_sampler** (`Sampler or Iterable, optional`) – like `sampler`, but returns a batch of indices at a time. Mutually exclusive with `batch_size`, `shuffle`, `sampler`, and `drop_last`.
- **num_workers** (`int, optional`) – how many subprocesses to use for data loading. 0 means that the data will be loaded in the main process. (default: 0)
- **collate_fn** (`Callable, optional`) – merges a list of samples to form a mini-batch of Tensor(s). Used when using batched loading from a map-style dataset.
- **pin_memory** (`bool, optional`) – If True, the data loader will copy Tensors into device/CUDA pinned memory before returning them. If your data elements are a custom type, or your `collate_fn` returns a batch that is a custom type, see the example below.
- **drop_last** (`bool, optional`) – set to True to drop the last incomplete batch, if the dataset size is not divisible by the batch size. If False and the size of dataset is not divisible by the batch size, then the last batch will be smaller. (default: False)
- **timeout** (`numeric, optional`) – if positive, the timeout value for collecting a batch from workers. Should always be non-negative. (default: 0)

- **worker_init_fn** (*Callable, optional*) – If not None, this will be called on each worker subprocess with the worker id (an int in [0, num_workers - 1]) as input, after seeding and before data loading. (default: None)
- **generator** (*torch.Generator, optional*) – If not None, this RNG will be used by RandomSampler to generate random indexes and multiprocessing to generate *base_seed* for workers. (default: None)
- **prefetch_factor** (*int, optional, keyword-only arg*) – Number of batches loaded in advance by each worker. 2 means there will be a total of 2 * num_workers batches prefetched across all workers. (default value depends on the set value for num_workers. If value of num_workers=0 default is None. Otherwise if value of num_workers>0 default is 2).
- **persistent_workers** (*bool, optional*) – If True, the data loader will not shutdown the worker processes after a dataset has been consumed once. This allows to maintain the workers *Dataset* instances alive. (default: False)
- **pin_memory_device** (*str, optional*) – the data loader will copy Tensors into device pinned memory before returning them if pin_memory is set to true.

Warning: If the spawn start method is used, `worker_init_fn` cannot be an unpickleable object, e.g., a lambda function. See [multiprocessing-best-practices](#) on more details related to multiprocessing in PyTorch.

Warning: `len(dataloader)` heuristic is based on the length of the sampler used. When `dataset` is an `IterableDataset`, it instead returns an estimate based on `len(dataset) / batch_size`, with proper rounding depending on `drop_last`, regardless of multi-process loading configurations. This represents the best guess PyTorch can make because PyTorch trusts user `dataset` code in correctly handling multi-process loading to avoid duplicate data.

However, if sharding results in multiple workers having incomplete last batches, this estimate can still be inaccurate, because (1) an otherwise complete batch can be broken into multiple ones and (2) more than one batch worth of samples can be dropped when `drop_last` is set. Unfortunately, PyTorch can not detect such cases in general.

See '[Dataset Types](#)' for more details on these two types of datasets and how `IterableDataset` interacts with '[Multi-process data loading](#)' .

Warning: See [reproducibility](#), and [dataloader-workers-random-seed](#), and [data-loading-randomness](#) notes for random seed related questions.

Methods

`__init__(dataset[, batch_size, shuffle, ...])`

`check_worker_number_rationality()`

Attributes

`multiprocessing_context`

`dataset`

`batch_size`

`num_workers`

`pin_memory`

`drop_last`

`timeout`

`sampler`

`pin_memory_device`

`prefetch_factor`

```
__init__(dataset, batch_size=1, shuffle=None, sampler=None, batch_sampler=None, num_workers=0,
        collate_fn=None, pin_memory=False, drop_last=False, timeout=0, worker_init_fn=None,
        multiprocessing_context=None, generator=None, *, prefetch_factor=None,
        persistent_workers=False, pin_memory_device="")
```

Parameters

- **dataset** (`Dataset[T_co]`) –
- **batch_size** (`Optional[int]`) –
- **shuffle** (`Optional[bool]`) –
- **sampler** (`Optional[Union[Sampler, Iterable]]`) –
- **batch_sampler** (`Optional[Union[Sampler[Sequence], Iterable[Sequence]]]`) –
- **num_workers** (`int`) –
- **collate_fn** (`Optional[Callable[[List[T]], Any]]`) –
- **pin_memory** (`bool`) –
- **drop_last** (`bool`) –
- **timeout** (`float`) –
- **worker_init_fn** (`Optional[Callable[[int], None]]`) –
- **prefetch_factor** (`Optional[int]`) –
- **persistent_workers** (`bool`) –
- **pin_memory_device** (`str`) –

```
batch_size: Optional[int]
check_worker_number_rationality()
dataset: Dataset[T_co]
drop_last: bool
property multiprocessing_context
num_workers: int
pin_memory: bool
pin_memory_device: str
prefetch_factor: Optional[int]
sampler: Union[Sampler, Iterable]
timeout: float
```

Modules

[pytorch_pfn_extras.dataloaders.dataloader](#)

[pytorch_pfn_extras.dataloaders.utils](#)

[pytorch_pfn_extras.dataloaders.dataloader](#)

Functions

pytorch_pfn_extras.dataloaders.dataloader.default_collate (batch)	Function that takes in a batch of data and puts the elements within the batch into a tensor with an additional outer dimension - batch size.
pytorch_pfn_extras.dataloaders.dataloader.default_convert (data)	Function that converts each NumPy array element into a <code>torch.Tensor</code> .
pytorch_pfn_extras.dataloaders.dataloader.get_worker_info ()	Returns the information about the current DataLoader iterator worker process.

[pytorch_pfn_extras.dataloaders.dataloader.default_collate](#)

`pytorch_pfn_extras.dataloaders.dataloader.default_collate(batch)`

Function that takes in a batch of data and puts the elements within the batch into a tensor with an additional outer dimension - batch size. The exact output type can be a `torch.Tensor`, a *Sequence* of `torch.Tensor`, a Collection of `torch.Tensor`, or left unchanged, depending on the input type. This is used as the default function for collation when `batch_size` or `batch_sampler` is defined in `DataLoader`.

Here is the general input type (based on the type of the element within the batch) to output type mapping:

- `torch.Tensor` -> `torch.Tensor` (with an added outer dimension batch size)

- NumPy Arrays -> `torch.Tensor`
- `float` -> `torch.Tensor`
- `int` -> `torch.Tensor`
- `str` -> `str` (unchanged)
- `bytes` -> `bytes` (unchanged)
- `Mapping[K, V_i]` -> `Mapping[K, default_collate([V_1, V_2, ...])]`
- `NamedTuple[V1_i, V2_i, ...]` -> `NamedTuple[default_collate([V1_1, V1_2, ...]), default_collate([V2_1, V2_2, ...]), ...]`
- `Sequence[V1_i, V2_i, ...]` -> `Sequence[default_collate([V1_1, V1_2, ...]), default_collate([V2_1, V2_2, ...]), ...]`

Parameters

`batch` – a single batch to be collated

Examples

```
>>> # xdoctest: +SKIP
>>> # Example with a batch of `int`s:
>>> default_collate([0, 1, 2, 3])
tensor([0, 1, 2, 3])
>>> # Example with a batch of `str`s:
>>> default_collate(['a', 'b', 'c'])
['a', 'b', 'c']
>>> # Example with `Map` inside the batch:
>>> default_collate([{ 'A': 0, 'B': 1}, { 'A': 100, 'B': 100}])
{'A': tensor([ 0, 100]), 'B': tensor([-1, 100])}
>>> # Example with `NamedTuple` inside the batch:
>>> Point = namedtuple('Point', ['x', 'y'])
>>> default_collate([Point(0, 0), Point(1, 1)])
Point(x=tensor([0, 1]), y=tensor([0, 1]))
>>> # Example with `Tuple` inside the batch:
>>> default_collate([(0, 1), (2, 3)])
[tensor([0, 2]), tensor([1, 3])]
>>> # Example with `List` inside the batch:
>>> default_collate([[0, 1], [2, 3]])
[tensor([0, 2]), tensor([1, 3])]
>>> # Two options to extend `default_collate` to handle specific type
>>> # Option 1: Write custom collate function and invoke `default_collate`
>>> def custom_collate(batch):
...     elem = batch[0]
...     if isinstance(elem, CustomType): # Some custom condition
...         return ...
...     else: # Fall back to `default_collate`
...         return default_collate(batch)
>>> # Option 2: In-place modify `default_collate_fn_map`
>>> def collate_customtype_fn(batch, *, collate_fn_map=None):
...     return ...
>>> default_collate_fn_map.update(CustomType, collate_customtype_fn)
>>> default_collate(batch) # Handle `CustomType` automatically
```

[pytorch_pfn_extras.dataloaders.dataloader.default_convert](#)

`pytorch_pfn_extras.dataloaders.dataloader.default_convert(data)`

Function that converts each NumPy array element into a `torch.Tensor`. If the input is a *Sequence*, *Collection*, or *Mapping*, it tries to convert each element inside to a `torch.Tensor`. If the input is not an NumPy array, it is left unchanged. This is used as the default function for collation when both `batch_sampler` and `batch_size` are NOT defined in `DataLoader`.

The general input type to output type mapping is similar to that of `default_collate()`. See the description there for more details.

Parameters

`data` – a single data point to be converted

Examples

```
>>> # xdoctest: +SKIP
>>> # Example with `int`
>>> default_convert(0)
0
>>> # Example with NumPy array
>>> default_convert(np.array([0, 1]))
tensor([0, 1])
>>> # Example with NamedTuple
>>> Point = namedtuple('Point', ['x', 'y'])
>>> default_convert(Point(0, 0))
Point(x=0, y=0)
>>> default_convert(Point(np.array(0), np.array(0)))
Point(x=tensor(0), y=tensor(0))
>>> # Example with List
>>> default_convert([np.array([0, 1]), np.array([2, 3])])
[tensor([0, 1]), tensor([2, 3])]
```

[pytorch_pfn_extras.dataloaders.dataloader.get_worker_info](#)

`pytorch_pfn_extras.dataloaders.dataloader.get_worker_info()`

Returns the information about the current `DataLoader` iterator worker process.

When called in a worker, this returns an object guaranteed to have the following attributes:

- `id`: the current worker id.
- `num_workers`: the total number of workers.
- `seed`: the random seed set for the current worker. This value is determined by main process RNG and the worker id. See `DataLoader`'s documentation for more details.
- `dataset`: the copy of the dataset object in `this` process. Note that this will be a different object in a different process than the one in the main process.

When called in the main process, this returns `None`.

Note: When used in a `worker_init_fn` passed over to `DataLoader`, this method can be useful to set up each worker process differently, for instance, using `worker_id` to configure the `dataset` object to only read a specific

fraction of a sharded dataset, or use `seed` to seed other libraries used in dataset code.

Return type

Optional[WorkerInfo]

Classes

`pytorch_pfn_extras.dataloaders.dataloader`. `DataLoader`. Data loader.
`DataLoader(dataset)`

pytorch_pfn_extras.dataloaders.dataloader.DataLoader

```
class pytorch_pfn_extras.dataloaders.dataloader.DataLoader(dataset, batch_size=1, shuffle=None,
                                                               sampler=None, batch_sampler=None,
                                                               num_workers=0, collate_fn=None,
                                                               pin_memory=False, drop_last=False,
                                                               timeout=0, worker_init_fn=None,
                                                               multiprocessing_context=None,
                                                               generator=None, *,
                                                               prefetch_factor=None,
                                                               persistent_workers=False,
                                                               pin_memory_device="")
```

Bases: `Generic[T_co]`

Data loader. Combines a dataset and a sampler, and provides an iterable over the given dataset.

The `DataLoader` supports both map-style and iterable-style datasets with single- or multi-process loading, customizing loading order and optional automatic batching (collation) and memory pinning.

See `torch.utils.data` documentation page for more details.

Parameters

- **dataset** (`Dataset`) – dataset from which to load the data.
- **batch_size** (`int, optional`) – how many samples per batch to load (default: 1).
- **shuffle** (`bool, optional`) – set to True to have the data reshuffled at every epoch (default: False).
- **sampler** (`Sampler or Iterable, optional`) – defines the strategy to draw samples from the dataset. Can be any `Iterable` with `__len__` implemented. If specified, `shuffle` must not be specified.
- **batch_sampler** (`Sampler or Iterable, optional`) – like `sampler`, but returns a batch of indices at a time. Mutually exclusive with `batch_size`, `shuffle`, `sampler`, and `drop_last`.
- **num_workers** (`int, optional`) – how many subprocesses to use for data loading. 0 means that the data will be loaded in the main process. (default: 0)
- **collate_fn** (`Callable, optional`) – merges a list of samples to form a mini-batch of Tensor(s). Used when using batched loading from a map-style dataset.

- **pin_memory** (*bool, optional*) – If True, the data loader will copy Tensors into device/CUDA pinned memory before returning them. If your data elements are a custom type, or your `collate_fn` returns a batch that is a custom type, see the example below.
- **drop_last** (*bool, optional*) – set to True to drop the last incomplete batch, if the dataset size is not divisible by the batch size. If False and the size of dataset is not divisible by the batch size, then the last batch will be smaller. (default: False)
- **timeout** (*numeric, optional*) – if positive, the timeout value for collecting a batch from workers. Should always be non-negative. (default: 0)
- **worker_init_fn** (*Callable, optional*) – If not None, this will be called on each worker subprocess with the worker id (an int in [0, num_workers - 1]) as input, after seeding and before data loading. (default: None)
- **generator** (*torch.Generator, optional*) – If not None, this RNG will be used by RandomSampler to generate random indexes and multiprocessing to generate *base_seed* for workers. (default: None)
- **prefetch_factor** (*int, optional, keyword-only arg*) – Number of batches loaded in advance by each worker. 2 means there will be a total of $2 * \text{num_workers}$ batches prefetched across all workers. (default value depends on the set value for num_workers. If value of num_workers=0 default is None. Otherwise if value of num_workers>0 default is 2).
- **persistent_workers** (*bool, optional*) – If True, the data loader will not shutdown the worker processes after a dataset has been consumed once. This allows to maintain the workers *Dataset* instances alive. (default: False)
- **pin_memory_device** (*str, optional*) – the data loader will copy Tensors into device pinned memory before returning them if pin_memory is set to true.

Warning: If the `spawn` start method is used, `worker_init_fn` cannot be an unpicklable object, e.g., a lambda function. See [multiprocessing-best-practices](#) on more details related to multiprocessing in PyTorch.

Warning: `len(dataloader)` heuristic is based on the length of the sampler used. When `dataset` is an `IterableDataset`, it instead returns an estimate based on `len(dataset) / batch_size`, with proper rounding depending on `drop_last`, regardless of multi-process loading configurations. This represents the best guess PyTorch can make because PyTorch trusts user `dataset` code in correctly handling multi-process loading to avoid duplicate data.

However, if sharding results in multiple workers having incomplete last batches, this estimate can still be inaccurate, because (1) an otherwise complete batch can be broken into multiple ones and (2) more than one batch worth of samples can be dropped when `drop_last` is set. Unfortunately, PyTorch can not detect such cases in general.

See [`Dataset Types`](#) for more details on these two types of datasets and how `IterableDataset` interacts with [`Multi-process data loading`](#).

Warning: See reproducibility, and dataloader-workers-random-seed, and data-loading-randomness notes for random seed related questions.

Methods

`__init__(dataset[, batch_size, shuffle, ...])`

`check_worker_number_rationality()`

Attributes

`multiprocessing_context`

`dataset`

`batch_size`

`num_workers`

`pin_memory`

`drop_last`

`timeout`

`sampler`

`pin_memory_device`

`prefetch_factor`

`__init__(dataset, batch_size=1, shuffle=None, sampler=None, batch_sampler=None, num_workers=0, collate_fn=None, pin_memory=False, drop_last=False, timeout=0, worker_init_fn=None, multiprocessing_context=None, generator=None, *, prefetch_factor=None, persistent_workers=False, pin_memory_device='')`

Parameters

- `dataset` (`Dataset[T_co]`) –
- `batch_size` (`Optional[int]`) –
- `shuffle` (`Optional[bool]`) –
- `sampler` (`Optional[Union[Sampler, Iterable]]`) –
- `batch_sampler` (`Optional[Union[Sampler[Sequence], Iterable[Sequence]]]`) –
- `num_workers` (`int`) –
- `collate_fn` (`Optional[Callable[[List[T]], Any]]`) –
- `pin_memory` (`bool`) –
- `drop_last` (`bool`) –

- **timeout** (*float*) –
- **worker_init_fn** (*Optional[Callable[[int], None]]*) –
- **prefetch_factor** (*Optional[int]*) –
- **persistent_workers** (*bool*) –
- **pin_memory_device** (*str*) –

batch_size: *Optional[int]*

check_worker_number_rationality()

dataset: *Dataset[T_co]*

drop_last: *bool*

property multiprocessing_context

num_workers: *int*

pin_memory: *bool*

pin_memory_device: *str*

prefetch_factor: *Optional[int]*

sampler: *Union[Sampler, Iterable]*

timeout: *float*

[pytorch_pfn_extras.dataloaders.utils](#)

Classes

pytorch_pfn_extras.dataloaders.utils.CollateAsDict(names)	Creates a collate function that converts inputs to a dict of tensors.
---	---

[pytorch_pfn_extras.dataloaders.utils.CollateAsDict](#)

class [pytorch_pfn_extras.dataloaders.utils.CollateAsDict](#)(*names, collate_fn=<function default_collate>*)

Bases: *object*

Creates a collate function that converts inputs to a dict of tensors.

An instantiated callable object can be feeded to `torch.utils.data.DataLoader` as a `collate_fn` option.

Parameters

- **names** (*list of str*) – Names of keys of output dict.
- **collate_fn** (*function*) – A function preprocesses inputs.

Methods

`__init__(names[, collate_fn])`

`__call__(*args, **kwargs)`

Converts inputs the dataset generated to a dictionary of tensors.

Returns (dict of Tensor):

A dictionary with keys that specified as names option, and values as input tensors.

Parameters

- **args** (*Any*) –
- **kwargs** (*Any*) –

Return type

Dict[str, Any]

`__init__(names, collate_fn=<function default_collate>)`

Parameters

- **names** (*Sequence[str]*) –
- **collate_fn** (*Callable[[], Any]*) –

Return type

None

pytorch_pfn_extras.dataset

Classes

<code>pytorch_pfn_extras.dataset. SharedDataset(sm_size)</code>	Dataset that caches the load samples in shared memory
<code>pytorch_pfn_extras.dataset. TabularDataset(...)</code>	An abstract class that represents tabular dataset.

pytorch_pfn_extras.dataset.SharedDataset

```
class pytorch_pfn_extras.dataset.SharedDataset(sm_size, cache_type=<class 'py-  
torch_pfn_extras.dataset.shared_dataset.InfiniteCache'>)
```

Bases: `Dataset`

Dataset that caches the load samples in shared memory

Args

Methods

```
__init__(sm_size[, cache_type])  
cache_item(idx, x)  
is_cached(idx)
```

```
__init__(sm_size, cache_type=<class 'pytorch_pfn_extras.dataset.shared_dataset.InfiniteCache'>)  
cache_item(idx, x)  
is_cached(idx)
```

pytorch_pfn_extras.dataset.TabularDataset

```
class pytorch_pfn_extras.dataset.TabularDataset(*args, **kwds)
```

Bases: *Dataset*

An abstract class that represents tabular dataset.

This class represents a tabular dataset. In a tabular dataset, all examples have the same number of elements. For example, all examples of the dataset below have three elements ($a[i]$, $b[i]$, and $c[i]$).

	a	b	c
0	$a[0]$	$b[0]$	$c[0]$
1	$a[1]$	$b[1]$	$c[1]$
2	$a[2]$	$b[2]$	$c[2]$
3	$a[3]$	$b[3]$	$c[3]$

Since an example can be represented by both tuple and dict ($(a[i], b[i], c[i])$ and $\{'a': a[i], 'b': b[i], 'c': c[i]\}$), this class uses *mode* to indicate which representation will be used. If there is only one column, an example also can be represented by a value ($a[i]$). In this case, *mode* is `None`.

An inheritance should implement `__len__()`, `keys`, `mode` and `get_examples()`.

```
>>> import numpy as np  
>>>  
>>> from pytorch_pfn_extras import dataset  
>>>  
>>> class MyDataset(dataset.TabularDataset):  
...     def __len__(self):  
...         return 4  
...     @property  
...     def keys(self):  
...         return ('a', 'b', 'c')  
...     @property  
...     def mode(self):
```

(continues on next page)

(continued from previous page)

```

...
    return tuple

...
def get_examples(self, indices, key_indices):
    data = np.arange(12).reshape((4, 3))
    if indices is not None:
        data = data[indices]
    if key_indices is not None:
        data = data[:, list(key_indices)]
    return tuple(data.transpose())
...

>>> dataset = MyDataset()
>>> len(dataset)
4
>>> dataset.keys
('a', 'b', 'c')
>>> dataset.astuple()[0]
(0, 1, 2)
>>> sorted(dataset.asdict()[0].items())
[('a', 0), ('b', 1), ('c', 2)]
>>>
>>> view = dataset.slice[[3, 2], ('c', 0)]
>>> len(view)
2
>>> view.keys
('c', 'a')
>>> view.astuple()[1]
(8, 6)
>>> sorted(view.asdict()[1].items())
[('a', 6), ('c', 8)]

```

Methods

`__init__()`

<code>asdict()</code>	Return a view with dict mode.
<code>astuple()</code>	Return a view with tuple mode.
<code>concat(*datasets)</code>	Stack datasets along rows.
<code>convert(data)</code>	Convert fetched data.
<code>fetch()</code>	Fetch data.
<code>get_example(i)</code>	

<code>get_examples(indices, key_indices)</code>	Return a part of data.
<code>join(*datasets)</code>	Stack datasets along columns.
<code>transform(keys, transform)</code>	Apply a transform to each example.
<code>transform_batch(keys, transform_batch)</code>	Apply a transform to examples.
<code>with_converter(converter)</code>	Override the behaviour of <code>convert()</code> .

Attributes

<code>keys</code>	Names of columns.
<code>mode</code>	Mode of representation.
<code>slice</code>	Get a slice of dataset.

`asdict()`

Return a view with dict mode.

Returns

A view whose `mode` is `dict`.

`astuple()`

Return a view with tuple mode.

Returns

A view whose `mode` is `tuple`.

`concat(*datasets)`

Stack datasets along rows.

Parameters

`datasets` (iterable of `TabularDataset`) – Datasets to be concatenated. All datasets must have the same `keys`.

Returns

A concatenated dataset.

`convert(data)`

Convert fetched data.

This method takes data fetched by `fetch()` and pre-process them before passing them to models. The default behaviour is converting each column into an ndarray. This behaviour can be overridden by `with_converter()`. If the dataset is constructed by `concat()` or `join()`, the converter of the first dataset is used.

Parameters

`data (tuple or dict)` – Data from `fetch()`.

Returns

A tuple or dict. Each value is an ndarray.

`fetch()`

Fetch data.

This method fetches all data of the dataset/view. Note that this method returns a column-major data (i.e. `[a[0], ..., a[3]], ..., [c[0], ..., c[3]]`), `{'a': [a[0], ..., a[3]], ..., 'c': [c[0], ..., c[3]]}`, or `[a[0], ..., a[3]]`).

Returns

If `mode` is `tuple`, this method returns a tuple of lists/arrays. If `mode` is `dict`, this method returns a dict of lists/arrays.

`get_example(i)`

`get_examples(indices, key_indices)`

Return a part of data.

Parameters

- **indices** (*list of ints or slice*) – Indices of requested rows. If this argument is `None`, it indicates all rows.
- **key_indices** (*tuple of ints*) – Indices of requested columns. If this argument is `None`, it indicates all columns.

Returns

tuple of lists/arrays

join(*datasets)

Stack datasets along columns.

Args: datasets (iterable of `TabularDataset`):

Datasets to be concatenated. All datasets must have the same length

Returns

A joined dataset.

property keys

Names of columns.

A tuple of strings that indicate the names of columns.

property mode

Mode of representation.

This indicates the type of value returned by `fetch()` and `__getitem__()`. `tuple`, `dict`, and `None` are supported.

property slice

Get a slice of dataset.

Parameters

- **indices** (*list/array of ints/bools or slice*) – Requested rows.
- **keys** (*tuple of ints/strs or int or str*) – Requested columns.

Returns

A view of specified range.

transform(keys, transform)

Apply a transform to each example.

The transformations are a list where each element is a tuple that holds the transformation signature and a callable that is the transformation itself.

The transformation signature is a tuple of 2 elements with the first one being the keys of the dataset that are taken as inputs. And the last one the outputs it produces for the transformation `keys` argument.

When multiple transformations are specified, the outputs must be disjoint or `ValueError` will be risen.

Parameters

- **keys** (*tuple of strs*) – The keys of transformed examples.
- **transform** (*list of tuples*) – A list where each element specifies a transformation with a tuple with the transformation signature and a callable that takes an example and returns transformed example. `mode` of transformed dataset is determined by the transformed examples.

Returns

A transfromed dataset.

transform_batch(*keys*, *transform_batch*)

Apply a transform to examples.

The transformations are a list where each element is a tuple that holds the transformation signature and a callable that is the transformation itself.

The transformation signature is a tuple of 2 elements with the first one being the keys of the dataset that are taken as inputs. And the last one the outputs it produces for the transformation *keys* argument.

When multiple transformations are specified, the outputs must be disjoint or *ValueError* will be risen.

Parameters

- **keys** (*tuple of strs*) – The keys of transformed examples.
- **transform_batch** (*list of tuples*) – A list where each element specifies a transformation with a tuple with the transformation signature and a callable that takes a batch of examples and returns a batch of transformed examples. *mode* of transformed dataset is determined by the transformed examples.

Returns

A transfromed dataset.

with_converter(*converter*)

Override the behaviour of *convert()*.

This method overrides *convert()*.

Parameters

converter (*callable*) – A new converter.

Returns

A dataset with the new converter.

Exceptions

pytorch_pfn_extras.dataset.

ItemNotFoundException

pytorch_pfn_extras.dataset.ItemNotFoundException

exception `pytorch_pfn_extras.dataset.ItemNotFoundException`

Modules

pytorch_pfn_extras.dataset.shared_dataset

pytorch_pfn_extras.dataset.tabular

pytorch_pfn_extras.dataset.shared_dataset

Classes

```
pytorch_pfn_extras.dataset.shared_dataset.  
Cache()  
pytorch_pfn_extras.dataset.shared_dataset.  
InfiniteCache(sm_size)  
pytorch_pfn_extras.dataset.shared_dataset. Dataset that caches the load samples in shared memory  
SharedDataset(sm_size)
```

pytorch_pfn_extras.dataset.shared_dataset.Cache

```
class pytorch_pfn_extras.dataset.shared_dataset.Cache  
Bases: object
```

Methods

```
__init__()  
add_to_cache(idx, x)  
get_value(idx)  
is_cached(idx)
```

```
add_to_cache(idx, x)  
get_value(idx)  
is_cached(idx)
```

pytorch_pfn_extras.dataset.shared_dataset.InfiniteCache

```
class pytorch_pfn_extras.dataset.shared_dataset.InfiniteCache(sm_size)  
Bases: Cache
```

Methods

```
__init__(sm_size)  
add_to_cache(idx, x)  
get_value(idx)  
is_cached(idx)
```

```
__init__(sm_size)
add_to_cache(idx, x)
get_value(idx)
is_cached(idx)
```

[pytorch_pfn_extras.dataset.shared_dataset.SharedDataset](#)

```
class pytorch_pfn_extras.dataset.shared_dataset.SharedDataset(sm_size, cache_type=<class 'py-
torch_pfn_extras.dataset.shared_dataset.InfiniteCache')
```

Bases: [Dataset](#)

Dataset that caches the load samples in shared memory

Args

Methods

```
__init__(sm_size[, cache_type])
```

```
cache_item(idx, x)
```

```
is_cached(idx)
```

```
__init__(sm_size, cache_type=<class 'pytorch_pfn_extras.dataset.shared_dataset.InfiniteCache'>)
```

```
cache_item(idx, x)
```

```
is_cached(idx)
```

Exceptions

```
pytorch\_pfn\_extras.dataset.shared\_dataset.
ItemNotFoundException
```

[pytorch_pfn_extras.dataset.shared_dataset.ItemNotFoundException](#)

```
exception pytorch_pfn_extras.dataset.shared_dataset.ItemNotFoundException
```

pytorch_pfn_extras.dataset.tabular

Functions

<code>pytorch_pfn_extras.dataset.tabular. from_data(data, *)</code>	Create a TabularDataset from lists/arrays/callables.
---	--

pytorch_pfn_extras.dataset.tabular.from_data

`pytorch_pfn_extras.dataset.tabular.from_data(data, *, size=None)`

Create a TabularDataset from lists/arrays/callables.

```
>>> from pytorch_pfn_extras.dataset import tabular
>>>
>>> dataset = tabular.from_data([0, 1, 2])
>>> dataset[0]
0
>>> dataset = tabular.from_data(([0, 1, 2], [3, 4, 5]))
>>> dataset[0]
(0, 3)
>>> dataset = tabular.from_data(({'a': [0, 1, 2]}, {'b': [3, 4, 5]}))
>>> dataset.keys
('a', 'b')
>>> dataset[0]
(0, 3)
>>> dataset = tabular.from_data({'a': [0, 1, 2], 'b': [3, 4, 5]})
>>> sorted(dataset[0].items())
[('a', 0), ('b', 3)]
>>> dataset = tabular.from_data('a', lambda i: i * i), size=10)
>>> dataset[5]
25
```

Parameters

- **data** (*list, array, tuple, or dict*) – Data in following format.
 - *list/array*
 - *(str, list/array/callable)*
 - *((str, ...), callable)*
 - *((list/array)/(str, list/array/callable) /((key, ...), callable), ...)*
 - *{str: (list/array/callable)/(str, ...): callable, ...}*
- **size** (*int*) – The length of the dataset. This argument is required when no lists/arrays exist in data.

Returns

A `TabularDataset`.

Classes

<code>pytorch_pfn_extras.dataset.tabular. DelegateDataset(dataset)</code>	A helper class to implement a TabularDataset.
---	---

`pytorch_pfn_extras.dataset.tabular.DelegateDataset`

`class pytorch_pfn_extras.dataset.tabular.DelegateDataset(dataset)`

Bases: `TabularDataset`

A helper class to implement a TabularDataset.

This class wraps an instance of `TabularDataset` and provides methods of `TabularDataset`. This class is useful to create a custom dataset class by inheriting it.

```
>>> import numpy as np
>>>
>>> from pytorch_pfn_extras.dataset import tabular
>>>
>>> class MyDataset(tabular.DelegateDataset):
...     ...
...     def __init__(self):
...         super().__init__(tabular.from_data((
...             ('a', np.arange(10)),
...             ('b', self.get_b),
...             ('c', [3, 1, 4, 5, 9, 2, 6, 8, 7, 0]),
...             (('d', 'e'), self.get_de))))
...
...     def get_b(self, i):
...         return 'b[{}]'.format(i)
...
...     def get_de(self, i):
...         return {'d': 'd[{}]'.format(i), 'e': 'e[{}]'.format(i)}
...
...
>>> dataset = MyDataset()
>>> len(dataset)
10
>>> dataset.keys
('a', 'b', 'c', 'd', 'e')
>>> dataset[0]
(0, 'b[0]', 3, 'd[0]', 'e[0]')
```

Parameters

`dataset` (`pytorch_pfn_extras.dataset.TabularDataset`) – An underlying dataset.

Methods

<code>__init__(dataset)</code>	
<code>asdict()</code>	Return a view with dict mode.
<code>astuple()</code>	Return a view with tuple mode.
<code>concat(*datasets)</code>	Stack datasets along rows.
<code>convert(data)</code>	Convert fetched data.
<code>fetch()</code>	Fetch data.
<code>get_example(i)</code>	
<code>get_examples(indices, key_indices)</code>	Return a part of data.
<code>join(*datasets)</code>	Stack datasets along columns.
<code>transform(keys, transform)</code>	Apply a transform to each example.
<code>transform_batch(keys, transform_batch)</code>	Apply a transform to examples.
<code>with_converter(converter)</code>	Override the behaviour of <code>convert()</code> .

Attributes

<code>keys</code>	Names of columns.
<code>mode</code>	Mode of representation.
<code>slice</code>	Get a slice of dataset.

`__init__(dataset)`

`get_examples(indices, key_indices)`

Return a part of data.

Parameters

- `indices (list of ints or slice)` – Indices of requested rows. If this argument is `None`, it indicates all rows.
- `key_indices (tuple of ints)` – Indices of requested columns. If this argument is `None`, it indicates all columns.

Returns

tuple of lists/arrays

property keys

Names of columns.

A tuple of strings that indicate the names of columns.

property mode

Mode of representation.

This indicates the type of value returned by `fetch()` and `__getitem__()`. `tuple`, `dict`, and `None` are supported.

Modules

<code>pytorch_pfn_extras.dataset.tabular. delegate_dataset</code>	
<code>pytorch_pfn_extras.dataset.tabular. from_data(data, *)</code>	Create a TabularDataset from lists/arrays/callables.
<code>pytorch_pfn_extras.dataset.tabular. tabular_dataset</code>	

`pytorch_pfn_extras.dataset.tabular.delegate_dataset`

Classes

<code>pytorch_pfn_extras.dataset.tabular. delegate_dataset.DelegateDataset(dataset)</code>	A helper class to implement a TabularDataset.
--	---

`pytorch_pfn_extras.dataset.tabular.delegate_dataset.DelegateDataset`

`class pytorch_pfn_extras.dataset.tabular.delegate_dataset.DelegateDataset(dataset)`

Bases: `TabularDataset`

A helper class to implement a TabularDataset.

This class wraps an instance of `TabularDataset` and provides methods of `TabularDataset`. This class is useful to create a custom dataset class by inheriting it.

```
>>> import numpy as np
>>>
>>> from pytorch_pfn_extras.dataset import tabular
>>>
>>> class MyDataset(tabular.DelegateDataset):
...
...     def __init__(self):
...         super().__init__(tabular.from_data((
...             ('a', np.arange(10)),
...             ('b', self.get_b),
...             ('c', [3, 1, 4, 5, 9, 2, 6, 8, 7, 0]),
...             ('d', 'e'), self.get_de))))
...
...     def get_b(self, i):
...         return 'b[{}]'.format(i)
...
...     def get_de(self, i):
...         return {'d': 'd[{}]'.format(i), 'e': 'e[{}]'.format(i)}
...
...
>>> dataset = MyDataset()
>>> len(dataset)
10
>>> dataset.keys
('a', 'b', 'c', 'd', 'e')
```

(continues on next page)

(continued from previous page)

```
>>> dataset[0]
(0, 'b[0]', 3, 'd[0]', 'e[0]')
```

Parameters**dataset** (`pytorch_pfn_extras.dataset.TabularDataset`) – An underlying dataset.**Methods**[__init__\(dataset\)](#)

<code>asdict()</code>	Return a view with dict mode.
<code>astuple()</code>	Return a view with tuple mode.
<code>concat(*datasets)</code>	Stack datasets along rows.
<code>convert(data)</code>	Convert fetched data.
<code>fetch()</code>	Fetch data.
<code>get_example(i)</code>	
<code>get_examples(indices, key_indices)</code>	Return a part of data.
<code>join(*datasets)</code>	Stack datasets along columns.
<code>transform(keys, transform)</code>	Apply a transform to each example.
<code>transform_batch(keys, transform_batch)</code>	Apply a transform to examples.
<code>with_converter(converter)</code>	Override the behaviour of <code>convert()</code> .

Attributes

<code>keys</code>	Names of columns.
<code>mode</code>	Mode of representation.
<code>slice</code>	Get a slice of dataset.

[__init__\(dataset\)](#)[get_examples\(indices, key_indices\)](#)

Return a part of data.

Parameters

- **indices** (*list of ints or slice*) – Indices of requested rows. If this argument is `None`, it indicates all rows.
- **key_indices** (*tuple of ints*) – Indices of requested columns. If this argument is `None`, it indicates all columns.

Returns

tuple of lists/arrays

property keys

Names of columns.

A tuple of strings that indicate the names of columns.

property mode

Mode of representation.

This indicates the type of value returned by `fetch()` and `__getitem__()`. `tuple`, `dict`, and `None` are supported.

[pytorch_pfn_extras.dataset.tabular.tabular_dataset](#)

Classes

<code>pytorch_pfn_extras.dataset.tabular.tabular_dataset.Dataset(...)</code>	An abstract class representing a Dataset .
<code>pytorch_pfn_extras.dataset.tabular.tabular_dataset.TabularDataset(...)</code>	An abstract class that represents tabular dataset.

[pytorch_pfn_extras.dataset.tabular.tabular_dataset.Dataset](#)

`class pytorch_pfn_extras.dataset.tabular.tabular_dataset.Dataset(*args, **kwds)`

Bases: `Generic[T_co]`

An abstract class representing a [Dataset](#).

All datasets that represent a map from keys to data samples should subclass it. All subclasses should overwrite `__getitem__()`, supporting fetching a data sample for a given key. Subclasses could also optionally overwrite `__len__()`, which is expected to return the size of the dataset by many `Sampler` implementations and the default options of `DataLoader`.

Note: `DataLoader` by default constructs a index sampler that yields integral indices. To make it work with a map-style dataset with non-integral indices/keys, a custom sampler must be provided.

Methods

`__init__()`

[pytorch_pfn_extras.dataset.tabular.tabular_dataset.TabularDataset](#)

`class pytorch_pfn_extras.dataset.tabular.tabular_dataset.TabularDataset(*args, **kwds)`

Bases: `Dataset`

An abstract class that represents tabular dataset.

This class represents a tabular dataset. In a tabular dataset, all examples have the same number of elements. For example, all examples of the dataset below have three elements (`a[i]`, `b[i]`, and `c[i]`).

	a	b	c
0	a[0]	b[0]	c[0]
1	a[1]	b[1]	c[1]
2	a[2]	b[2]	c[2]
3	a[3]	b[3]	c[3]

Since an example can be represented by both tuple and dict ((a[i], b[i], c[i]) and {'a': a[i], 'b': b[i], 'c': c[i]}), this class uses `mode` to indicate which representation will be used. If there is only one column, an example also can be represented by a value (a[i]). In this case, `mode` is None.

An inheritance should implement `__len__()`, `keys`, `mode` and `get_examples()`.

```
>>> import numpy as np
>>>
>>> from pytorch_pfn_extras import dataset
>>>
>>> class MyDataset(dataset.TabularDataset):
...
...     def __len__(self):
...         return 4
...
...     @property
...     def keys(self):
...         return ('a', 'b', 'c')
...
...     @property
...     def mode(self):
...         return tuple
...
...     def get_examples(self, indices, key_indices):
...         data = np.arange(12).reshape((4, 3))
...         if indices is not None:
...             data = data[indices]
...         if key_indices is not None:
...             data = data[:, list(key_indices)]
...         return tuple(data.transpose())
...
...
>>> dataset = MyDataset()
>>> len(dataset)
4
>>> dataset.keys
('a', 'b', 'c')
>>> dataset.astuple()[0]
(0, 1, 2)
>>> sorted(dataset.asdict()[0].items())
[('a', 0), ('b', 1), ('c', 2)]
>>>
>>> view = dataset.slice[[3, 2], ('c', 0)]
>>> len(view)
2
>>> view.keys
('c', 'a')
>>> view.astuple()[1]
```

(continues on next page)

(continued from previous page)

```
(8, 6)
>>> sorted(view.asdict()[1].items())
[('a', 6), ('c', 8)]
```

Methods

`__init__()`

<code>asdict()</code>	Return a view with dict mode.
<code>astuple()</code>	Return a view with tuple mode.
<code>concat(*datasets)</code>	Stack datasets along rows.
<code>convert(data)</code>	Convert fetched data.
<code>fetch()</code>	Fetch data.
<code>get_example(i)</code>	
<code>get_examples(indices, key_indices)</code>	Return a part of data.
<code>join(*datasets)</code>	Stack datasets along columns.
<code>transform(keys, transform)</code>	Apply a transform to each example.
<code>transform_batch(keys, transform_batch)</code>	Apply a transform to examples.
<code>with_converter(converter)</code>	Override the behaviour of <code>convert()</code> .

Attributes

<code>keys</code>	Names of columns.
<code>mode</code>	Mode of representation.
<code>slice</code>	Get a slice of dataset.

`asdict()`

Return a view with dict mode.

Returns

A view whose `mode` is `dict`.

`astuple()`

Return a view with tuple mode.

Returns

A view whose `mode` is `tuple`.

`concat(*datasets)`

Stack datasets along rows.

Parameters

`datasets` (iterable of `TabularDataset`) – Datasets to be concatenated. All datasets must have the same `keys`.

Returns

A concatenated dataset.

convert(*data*)

Convert fetched data.

This method takes data fetched by `fetch()` and pre-process them before passing them to models. The default behaviour is converting each column into an ndarray. This behaviour can be overridden by `with_converter()`. If the dataset is constructed by `concat()` or `join()`, the converter of the first dataset is used.

Parameters

`data (tuple or dict)` – Data from `fetch()`.

Returns

A tuple or dict. Each value is an ndarray.

fetch()

Fetch data.

This method fetches all data of the dataset/view. Note that this method returns a column-major data (i.e. `([a[0], ..., a[3]], ..., [c[0], ..., c[3]])`, `{'a': [a[0], ..., a[3]], ..., 'c': [c[0], ..., c[3]]}`, or `[a[0], ..., a[3]]`).

Returns

If `mode` is `tuple`, this method returns a tuple of lists/arrays. If `mode` is `dict`, this method returns a dict of lists/arrays.

get_example(*i*)**get_examples(*indices*, *key_indices*)**

Return a part of data.

Parameters

- `indices (list of ints or slice)` – Indices of requested rows. If this argument is `None`, it indicates all rows.
- `key_indices (tuple of ints)` – Indices of requested columns. If this argument is `None`, it indicates all columns.

Returns

tuple of lists/arrays

join(*datasets)

Stack datasets along columns.

Args: datasets (iterable of `TabularDataset`):

Datasets to be concatenated. All datasets must have the same length

Returns

A joined dataset.

property keys

Names of columns.

A tuple of strings that indicate the names of columns.

property mode

Mode of representation.

This indicates the type of value returned by `fetch()` and `__getitem__()`. `tuple`, `dict`, and `None` are supported.

property slice

Get a slice of dataset.

Parameters

- **indices** (*list/array of ints/bools or slice*) – Requested rows.
- **keys** (*tuple of ints/strs or int or str*) – Requested columns.

Returns

A view of specified range.

transform(keys, transform)

Apply a transform to each example.

The transformations are a list where each element is a tuple that holds the transformation signature and a callable that is the transformation itself.

The transformation signature is a tuple of 2 elements with the first one being the keys of the dataset that are taken as inputs. And the last one the outputs it produces for the transformation *keys* argument.

When multiple transformations are specified, the outputs must be disjoint or *ValueError* will be risen.

Parameters

- **keys** (*tuple of strs*) – The keys of transformed examples.
- **transform** (*list of tuples*) – A list where each element specifies a transformation with a tuple with the transformation signature and a callable that takes an example and returns transformed example. *mode* of transformed dataset is determined by the transformed examples.

Returns

A transfromed dataset.

transform_batch(keys, transform_batch)

Apply a transform to examples.

The transformations are a list where each element is a tuple that holds the transformation signature and a callable that is the transformation itself.

The transformation signature is a tuple of 2 elements with the first one being the keys of the dataset that are taken as inputs. And the last one the outputs it produces for the transformation *keys* argument.

When multiple transformations are specified, the outputs must be disjoint or *ValueError* will be risen.

Parameters

- **keys** (*tuple of strs*) – The keys of transformed examples.
- **transform_batch** (*list of tuples*) – A list where each element specifies a transformation with a tuple with the transformation signature and a callable that takes a batch of examples and returns a batch of transformed examples. *mode* of transformed dataset is determined by the transformed examples.

Returns

A transfromed dataset.

with_converter(converter)

Override the behaviour of *convert()*.

This method overrides *convert()*.

Parameters

- **converter** (*callable*) – A new converter.

Returns

A dataset with the new converter.

pytorch_pfn_extras.distributed**Functions**

<code>pytorch_pfn_extras.distributed.create_distributed_subset_indices(...)</code>	Returns a indices of a dataset to be used for the current process.
<code>pytorch_pfn_extras.distributed.initialize_ompi_environment(*)</code>	Initialize <code>torch.distributed</code> environments with values taken from OpenMPI.

pytorch_pfn_extras.distributed.create_distributed_subset_indices

`pytorch_pfn_extras.distributed.create_distributed_subset_indices(num_total_samples, num_replicas=None, rank=None, shuffle=True, seed=None)`

Returns a indices of a dataset to be used for the current process.

Parameters

- **num_total_samples** (*int*) – The size of the dataset.
- **num_replicas** (*Optional[int]*) – Number of processes participating in the training. By default, `torch.distributed.get_world_size()` is used.
- **rank** (*Optional[int]*) – Rank of the current process within `num_replicas`. By default, `torch.distributed.get_rank()` is used.
- **shuffle** (*bool*) – If True (default), shuffle the indices.
- **seed** (*Optional[int]*) – Random seed used to shuffle.

Return type

`List[int]`

pytorch_pfn_extras.distributed.initialize_ompi_environment

`pytorch_pfn_extras.distributed.initialize_ompi_environment(*, backend='gloo', init_method='tcp', world_size=1, rank=0, local_rank=0, addr='localhost', port='1234')`

Initialize `torch.distributed` environments with values taken from OpenMPI.

Parameters

- **backend** (*str*) – The backend to be used, only "gloo" and "nccl" are supported. Defaults to "gloo".
- **init_method** (*str*) – Initialization method used by torch, only "tcp" and "env" are supported. Defaults to "tcp".
- **world_size** (*int*) – The total world size to be used in case it is not specified in MPI env vars. Defaults to 1.

- **rank** (*int*) – The process rank to be used in case it is not specified in MPI env vars. Defaults to 0.
- **local_rank** (*int*) – The process local rank to be used in case it is not specified in MPI env vars. Defaults to 0.
- **addr** (*str*) – The address of the master process of *torch.distributed*. Defaults to "localhost"
- **port** (*str*) – The port of the master process of *torch.distributed*. Defaults to "1234"

Return type

Tuple[int, int, int]

Classes

<code>pytorch_pfn_extras.distributed. DistributedValidationSampler</code> (dataset)	Distributed sampler without duplication
---	---

`pytorch_pfn_extras.distributed.DistributedValidationSampler`

```
class pytorch_pfn_extras.distributed.DistributedValidationSampler(dataset, num_replicas=None,  
                                                               rank=None, shuffle=True,  
                                                               seed=0)
```

Bases: Sampler

Distributed sampler without duplication

This sampler splits the input dataset to each worker process in distributed setup without allowing repetition. It is for evaluation purpose such as `DistributedEvaluator`. This does not guarantee each worker to get the same number of samples, so for training do not use this sampler (use PyTorch `DistributedSampler` instead).

Methods

```
__init__(dataset[, num_replicas, rank, ...])
```

```
__init__(dataset, num_replicas=None, rank=None, shuffle=True, seed=0)
```

Parameters

- **dataset** (*Sized*) –
- **num_replicas** (*Optional[int]*) –
- **rank** (*Optional[int]*) –
- **shuffle** (*bool*) –
- **seed** (*int*) –

Return type

None

pytorch_pfn_extras.engine

Functions

<code>pytorch_pfn_extras.engine.cast(typ, val)</code>	Cast a value to a type.
<code>pytorch_pfn_extras.engine.create_evaluator(...)</code>	Creates an evaluator object.
<code>pytorch_pfn_extras.engine.create_trainer(...)</code>	Creates a trainer object.
<code>pytorch_pfn_extras.engine.default_transform_model(n, x)</code>	
<code>pytorch_pfn_extras.engine.filter_state_objects(args)</code>	
<code>pytorch_pfn_extras.engine.filter_state_objects_dict(args)</code>	

pytorch_pfn_extras.engine.cast

`pytorch_pfn_extras.engine.cast(typ, val)`

Cast a value to a type.

This returns the value unchanged. To the type checker this signals that the return value has the designated type, but at runtime we intentionally don't check anything (we want this to be as fast as possible).

pytorch_pfn_extras.engine.create_evaluator

`pytorch_pfn_extras.engine.create_evaluator(models, *, progress_bar=False, device='cpu', metrics=None, logic=None, handler_class=None, options=None, runtime_options=None, profile=None)`

Creates an evaluator object. The return value of this function is expected to be fed to `ppe.engine.create_trainer` as an argument.

Parameters

- **models** (`Union[Module, Mapping[str, Module]]`) – Map of string to `torch.nn.Module` or an actual `Module`. In most cases, this argument is the same as the `model` argument of `ppe.engine.create_trainer`.
- **progress_bar** (`bool`) – If `True`, a progress bar is enabled in evaluation.
- **device** (`str or torch.device`) – Device name used for selecting a corresponding runtime class.
- **metrics** (`list of metrics`) – List of metrics, which computes various quantities and update output for the reporting.
- **logic** (`Optional[Logic]`) – A logic object. If `None` is given, an logic object is instantiated from the default logic class.
- **handler_class** (`Optional[Type[Handler]]`) – A handler class that instantiates a handler object. If `None` is given, `ppe.handler.Handler` is used as a default handler class.
- **options** (`Optional[Dict[str, Any]]`) – Options that are set to the handler and logic object. See the documentation of `ppe.handler.Handler` and `ppe.handler.Logic` for details.

- **runtime_options** (*Optional[Mapping[str, Any]]*) – Options that are set to the runtime object. See the documentation of `ppe.handler.Handler` for details.
- **profile** (*Optional[profile]*) – A `torch.profiler.profile` object to collect the performance metrics.

Return type

Evaluator

pytorch_pfn_extras.engine.create_trainer

```
pytorch_pfn_extras.engine.create_trainer(models, optimizers, max_epochs, *, extensions=None,
                                         out_dir='result', stop_trigger=None, writer=None,
                                         evaluator=None, device='cpu', logic=None,
                                         transform_model=<function default_transform_model>,
                                         handler_class=None, options=None, runtime_options=None,
                                         profile=None, **kwargs)
```

Creates a trainer object.

Parameters

- **models** (*Union[Module, Mapping[str, Module]]*) – Map of string to Module or an actual Module.
- **optimizers** (*Union[Optimizer, Mapping[str, Optimizer]]*) – Map of string to Optimizer or an actual Optimizer.
- **max_epochs** (*int*) – Number of epochs in the whole training loop. Ignored if `stop_trigger` is passed as a kwarg.
- **extensions** (*Optional[Sequence[Union[extension.ExtensionLike, extension.ExtensionEntry]]]*) – List of extensions to be registered to the trainer.
- **out_dir** (*str*) – Output directory (default: `result`).
- **stop_trigger** (*trigger, optional*) – Trigger that can be consulted to determine whether training has concluded. The default is an interval trigger set to `max_epochs`.
- **writer** (*Optional[writing.Writer]*) – Writer that can be used by extensions to write data to custom filesystems.
- **evaluator** (*Optional[Union[Evaluator, Tuple[Evaluator, TriggerLike], Mapping[str, Union[Evaluator, Tuple[Evaluator, TriggerLike]]]]]*) – Evaluator that is used in evaluation phase. If `None` is given, the evaluation is skipped. Evaluators can be created with `pytorch_pfn_extras.engine.create_evaluator()`.
- **device** (*str or torch.device*) – Device name used for selecting a corresponding runtime class.
- **logic** (*Optional[BaseLogic]*) – A logic object. If `None` is given, an logic object is instantiated from the default logic class.
- **transform_model** (*Callable[[str, Module], Module]*) – A function to transform a model structure, often used to unwrap the a module from DDP module.
- **handler_class** (*Optional[Type[Handler]]*) – A handler class that instantiates a handler object. If `None` is given, `ppe.handler.Handler` is used as a default handler class.
- **options** (*Optional[Dict[str, Any]]*) – Options that are set to the handler and logic object. See the documentation of `ppe.handler.Handler` and `ppe.handler.Logic` for details.

- **runtime_options** (*Optional[Mapping[str, Any]]*) – Options that are set to the runtime object. See the documentation of `ppe.runtime.PyTorchRuntime` for details.
- **profile** (*Optional[profile]*) – A `torch.profiler.profile` object to collect the performance metrics.
- **kwargs** (*Any*) –

Return type

Trainer

`pytorch_pfn_extras.engine.default_transform_model`

`pytorch_pfn_extras.engine.default_transform_model(n, x)`

Parameters

- **n** (*str*) –
- **x** (*Module*) –

Return type

Module

`pytorch_pfn_extras.engine.filter_state_objects`

`pytorch_pfn_extras.engine.filter_state_objects(args, key_name="")`

Parameters

- **args** (*Any*) –
- **key_name** (*str*) –

Return type

List[Tuple[str, StateObjectProtocol]]

`pytorch_pfn_extras.engine.filter_state_objects_dict`

`pytorch_pfn_extras.engine.filter_state_objects_dict(args, key_name='option')`

Parameters

- **args** (*Dict[str, Any]*) –
- **key_name** (*str*) –

Return type

List[Tuple[str, StateObjectProtocol]]

Classes

<code>pytorch_pfn_extras.engine.</code>	Typed version of namedtuple.
<code>NamedTuple(typename)</code>	
<code>pytorch_pfn_extras.engine.</code>	

`pytorch_pfn_extras.engine.NamedTuple`

`class pytorch_pfn_extras.engine.NamedTuple(typename, fields=None, /, **kwargs)`

Bases: `object`

Typed version of namedtuple.

Usage in Python versions >= 3.6:

```
class Employee(NamedTuple):
    name: str
    id: int
```

This is equivalent to:

```
Employee = collections.namedtuple('Employee', ['name', 'id'])
```

The resulting class has an extra `__annotations__` attribute, giving a dict that maps field names to types. (The field names are also in the `_fields` attribute, which is part of the namedtuple API.) Alternative equivalent keyword syntax is also accepted:

```
Employee = NamedTuple('Employee', name=str, id=int)
```

In Python versions <= 3.5 use:

```
Employee = NamedTuple('Employee', [('name', str), ('id', int)])
```

Methods

```
__init__()
```

`pytorch_pfn_extras.engine.StateObjectProtocol`

`class pytorch_pfn_extras.engine.StateObjectProtocol(*args, **kwargs)`

Bases: `Protocol`

Methods

`__init__(*args, **kwargs)`

`load_state_dict(state_dict)`

`state_dict()`

`__init__(*args, **kwargs)`

`load_state_dict(state_dict)`

Parameters

`state_dict (Dict[str, Any]) –`

Return type

`None`

`state_dict()`

Return type

`Dict[str, Any]`

pytorch_pfn_extras.handler

Functions

<code>pytorch_pfn_extras.handler.forward(block)</code>	Returns a CodeBlock that performs the forward pass for the given <code>torch.nn.Module</code> or another CodeBlock.
--	---

<code>pytorch_pfn_extras.handler. torch_autocast(...)</code>	Returns a CodeBlock that performs the forward, backward passes and applies the optimizer step for the given <code>torch.nn.Module</code> or another CodeBlock.
--	--

pytorch_pfn_extras.handler.forward

`pytorch_pfn_extras.handler.forward(block)`

Returns a CodeBlock that performs the forward pass for the given `torch.nn.Module` or another CodeBlock.

Parameters

`block (Callable) – torch.nn.Module or CodeBlock to update the parameters.`

Return type

`CodeBlock`

Returns: A CodeBlock object.

[pytorch_pfn_extras.handler.torch_autocast](#)

`pytorch_pfn_extras.handler.torch_autocast(enabled=True)`

Parameters

`enabled (bool) –`

Return type

`Generator[None, None, None]`

[pytorch_pfn_extras.handler.update_parameters](#)

`pytorch_pfn_extras.handler.update_parameters(block, optimizers, backprop_from=None, backprop_to=None)`

Returns a CodeBlock that performs the forward, backward passes and applies the optimizer step for the given `torch.nn.Module` or another CodeBlock.

Parameters

- `block (Callable) – torch.nn.Module or CodeBlock to update the parameters.`
- `optimizers (List[Optimizer]) – The list of Optimizer that will be used for parameter update.`
- `backprop_from (Optional[str]) – Select a single output from the block execution to perform the gradient calculation.`
- `backprop_to (Optional[Set[str]]) – Name of the values where backpropagation will be stopped.`

Return type

`CodeBlock`

Returns: A CodeBlock object.

Classes

<code>pytorch_pfn_extras.handler.BaseHandler(...)</code>	Base class of Handler.
<code>pytorch_pfn_extras.handler. BaseLogic([options])</code>	
<code>pytorch_pfn_extras.handler. ClosureLogic(...)</code>	A set of methods that defines the training logic.
<code>pytorch_pfn_extras.handler.CodeBlock(func, ...)</code>	Class that is used to specify and apply actions to a callable.
<code>pytorch_pfn_extras.handler. CodeBlockLogic(...)</code>	A set of methods that defines the training logic.
<code>pytorch_pfn_extras.handler.Handler(logic, ...)</code>	A set of callback functions to perform device-specific operations.
<code>pytorch_pfn_extras.handler.Logic(...)</code>	A set of methods that defines the training logic.

pytorch_pfn_extras.handler.BaseHandler

```
class pytorch_pfn_extras.handler.BaseHandler(logic, options, *args, **kwargs)
```

Bases: object

Base class of Handler.

Parameters

- **logic** ([Logic](#)) – A logic.
- **options** ([Dict\[str, Any\]](#)) –
- **args** ([Any](#)) –
- **kwargs** ([Any](#)) –

Methods

__init__(logic, options, *args, **kwargs)	Base class of Handler.
consume_options(options)	A method to update options of Handler.
eval_loop_begin(evaluator)	A method called before each evaluation step.
eval_loop_end(evaluator)	A method called after running all steps of the evaluation.
eval_post_step(evaluator, batch_idx, batch, ...)	A method called after each evaluation step.
eval_setup(evaluator, loader)	A method called only once when starting a training run.
eval_step(evaluator, batch_idx, batch, ...)	Evaluation iteration.
train_cleanup(trainer)	A method called only once when completing a training run.
train_epoch_begin(trainer, loader)	A method called when starting a new epoch.
train_epoch_end(trainer)	A method called when finishing an epoch.
train_post_step(trainer, batch_idx, batch, ...)	A method called after each training step.
train_setup(trainer, loader)	A method called only once when starting a training run.
train_step(trainer, batch_idx, batch, ...)	A training step.
train_validation_begin(trainer, evaluator)	A method called when starting a validation.
train_validation_end(trainer, evaluator)	A method called after validation.

```
__init__(logic, options, *args, **kwargs)
```

Base class of Handler.

Parameters

- **logic** ([Logic](#)) – A logic.
- **options** ([Dict\[str, Any\]](#)) –
- **args** ([Any](#)) –
- **kwargs** ([Any](#)) –

Return type

None

consume_options(*options*)

A method to update options of Handler.

Note that the given dict will be modified.

Parameters

options (*dict*) – Option key-values to be set.

Return type

None

eval_loop_begin(*evaluator*)

A method called before each evaluation step.

Parameters

evaluator ([Evaluator](#)) – The evaluator.

Return type

None

eval_loop_end(*evaluator*)

A method called after running all steps of the evaluation.

Parameters

evaluator ([Evaluator](#)) –

Return type

None

eval_post_step(*evaluator, batch_idx, batch, outputs*)

A method called after each evaluation step.

Parameters

- **evaluator** ([Evaluator](#)) –
- **batch_idx** (*int*) –
- **batch** (*Any*) –
- **outputs** (*Any*) –

Return type

None

eval_setup(*evaluator, loader*)

A method called only once when starting a training run. When evaluator is not given, this method is not called.

Parameters

- **evaluator** ([Evaluator](#)) –
- **loader** (*Iterable[Any]*) –

Return type

None

eval_step(*evaluator, batch_idx, batch, complete_fn*)

Evaluation iteration.

Parameters

- **evaluator** ([Evaluator](#)) –

- **batch_idx** (*int*) –
- **batch** (*Any*) –
- **complete_fn** (*Callable[[int, Any], None]*) –

Return type

None

train_cleanup(*trainer*)

A method called only once when completing a training run.

Parameters**trainer** (*Trainer*) –**Return type**

None

train_epoch_begin(*trainer, loader*)

A method called when starting a new epoch.

Parameters

- **trainer** (*Trainer*) –
- **loader** (*Iterable[Any]*) –

Return type

None

train_epoch_end(*trainer*)

A method called when finishing an epoch.

Parameters**trainer** (*Trainer*) –**Return type**

None

train_post_step(*trainer, batch_idx, batch, outputs*)

A method called after each training step.

Parameters

- **trainer** (*Trainer*) –
- **batch_idx** (*int*) –
- **batch** (*Any*) –
- **outputs** (*Any*) –

Return type

None

train_setup(*trainer, loader*)

A method called only once when starting a training run.

Parameters

- **trainer** (*Trainer*) –
- **loader** (*Iterable[Any]*) –

Return type

None

train_step(*trainer*, *batch_idx*, *batch*, *complete_fn*)

A training step.

Parameters

- **trainer** ([Trainer](#)) –
- **batch_idx** (*int*) –
- **batch** (*Any*) –
- **complete_fn** (*Callable*[*[int, Any]*, *None*]) –

Return type

None

train_validation_begin(*trainer*, *evaluator*)

A method called when starting a validation.

Parameters

- **trainer** ([Trainer](#)) –
- **evaluator** ([Evaluator](#)) –

Return type

None

train_validation_end(*trainer*, *evaluator*)

A method called after validation.

Parameters

- **trainer** ([Trainer](#)) – The trainer that calls this method.
- **evaluator** ([Evaluator](#)) – The evaluator used for validation.

Return type

None

[pytorch_pfn_extras.handler.BaseLogic](#)

class [pytorch_pfn_extras.handler.BaseLogic](#)(*options=None*)

Bases: [object](#)

Methods

`__init__([options])`

<code>consume_options(options)</code>	A method to update options of Logic.
<code>eval_step(models, batch_idx, batch)</code>	A method for an evaluation step.
<code>train_epoch_begin(models, epoch, loader)</code>	A method called when starting a new epoch of training.
<code>train_epoch_end(models, epoch)</code>	A method called when completing an epoch of training.
<code>train_step(models, optimizers, batch_idx, batch)</code>	A method invokes the models forward and backward passes.
<code>train_step_optimizers(models, optimizers, ...)</code>	A method in charge of stepping the provided optimizers.
<code>train_validation_begin(models)</code>	A method called when starting a validation.
<code>train_validation_end(models)</code>	A method called when the validation completes.

Parameters

`options (Optional[Dict[str, Any]]) –`

`__init__(options=None)`

Parameters

`options (Optional[Dict[str, Any]]) –`

`consume_options(options)`

A method to update options of Logic.

Note that the given dict will be modified.

Parameters

`options (dict) – Option key-values to be set.`

Return type

`None`

`eval_step(models, batch_idx, batch)`

A method for an evaluation step.

Parameters

- `models (dict of torch.nn.Module)` – The models.
- `batch_idx (int)` – Number of steps already finished.
- `batch (torch.Tensor, list of torch.Tensor, dict of torch.Tensor)` – Input tensors feeded to the model of the current step.

Return type

`Any`

`train_epoch_begin(models, epoch, loader)`

A method called when starting a new epoch of training.

Parameters

- `epoch (int)` – Number of epochs already finished.
- `models (dict of torch.nn.Module)` – The models.

- **loader** (`torch.utils.data.DataLoader`) – The data loader.

Return type

None

train_epoch_end(*models*, *epoch*)

A method called when completing an epoch of training.

Parameters

- **epoch** (`int`) – Number of epochs already finished.
- **models** (`dict of torch.nn.Module`) – The models.

Return type

None

train_step(*models*, *optimizers*, *batch_idx*, *batch*)

A method invokes the models forward and backward passes.

Optimizing is left to *train_step_optimizers* since maybe the user would like to aggregate the gradients of several iterations.

Parameters

- **models** (`dict of torch.nn.Module`) – The models.
- **optimizers** (`dict of torch.optim.Optimizer`) – The optimizers.
- **batch_idx** (`int`) – Number of training steps already finished.
- **batch** (`torch.Tensor, list of torch.Tensor, dict of torch.Tensor`) – Input tensors feeded to the model of the current step.

Return type

Any

train_step_optimizers(*models*, *optimizers*, *batch_idx*)

A method in charge of stepping the provided optimizers.

Parameters

- **optimizers** (`dict of torch.optim.Optimizer`) – The optimizers.
- **batch_idx** (`int`) – Number of steps already finished.
- **models** (`Mapping[str, Module]`) –

Return type

None

train_validation_begin(*models*)

A method called when starting a validation.

Parameters

models (`dict of torch.nn.Module`) – The models.

Return type

None

train_validation_end(*models*)

A method called when the validation completes.

Parameters

models (`dict of torch.nn.Module`) – The models.

Return type

None

pytorch_pfn_extras.handler.ClosureLogic

```
class pytorch_pfn_extras.handler.ClosureLogic(model_name='main', options=None)
```

Bases: *Logic*

A set of methods that defines the training logic.

Parameters

- **model_name** (*str*) – Name of the model. Default is 'main'.
- **options** (*dict, optional*) – The configuration options.
 - **'backward_outputs'** (*list of str*):
A list of names of outputs that require computation of the gradient.
 - **'autocast'** (*bool or dict*):
If True, `torch.autocast` is enabled, using `{"enabled": True, "device_type": "cuda"}` as autocast options. The default is False which corresponds to the following options `{"enabled": False, "device_type": "cuda"}`. If dict, options are passed to `torch.autocast`.
 - **'grad_scaler'** (`torch.cuda.amp.GradScaler`):
A gradient scaler that outputs are applied to.

Methods

<code>__init__([model_name, options])</code>	A set of methods that defines the training logic.
<code>consume_options(options)</code>	A method to update options of Logic.
<code>eval_step(models, batch_idx, batch)</code>	A method for an evaluation step.
<code>train_epoch_begin(models, epoch, loader)</code>	A method called when starting a new epoch of training.
<code>train_epoch_end(models, epoch)</code>	A method called when completing an epoch of training.
<code>train_step(models, optimizers, batch_idx, batch)</code>	A method invokes the model forward and backward passes and performs an optimization step.
<code>train_step_optimizers(models, optimizers, ...)</code>	In closure mode, the stepping of the optimizer cannot be changed.
<code>train_validation_begin(models)</code>	A method called when starting a validation.
<code>train_validation_end(models)</code>	A method called when the validation completes.

consume_options(*options*)

A method to update options of Logic.

Note that the given dict will be modified.

Parameters**options** (*dict*) – Option key-values to be set.**Return type**

None

train_step(*models*, *optimizers*, *batch_idx*, *batch*)

A method invokes the model forward and backward passes and performs an optimization step.

Parameters

- **models** (*dict of torch.nn.Module*) – The models.
- **optimizers** (*dict of torch.optim.Optimizer*) – The optimizers.
- **batch_idx** (*int*) – Number of training steps already finished.
- **batch** (*torch.Tensor*, *list of torch.Tensor*, *dict of torch.Tensor*) – Input tensors feeded to the model of the current step.

Return type

Any

train_step_optimizers(*models*, *optimizers*, *batch_idx*)

In closure mode, the stepping of the optimizer cannot be changed.

If you want to change the stepping of the optimizer, please use the normal Logic class.

Parameters

- **optimizers** (*dict of torch.optim.Optimizer*) – The optimizers.
- **batch_idx** (*int*) – Number of steps already finished.
- **models** (*Mapping[str, Module]*) –

Return type

None

pytorch_pfn_extras.handler.CodeBlock

class `pytorch_pfn_extras.handler.CodeBlock(func, optimizers, backprop, backprop_from, backprop_to, state, runtime)`

Bases: `object`

Class that is used to specify and apply actions to a callable.

CodeBlocks are used in Logic classes to write device agnostic codes, as the device runtime is in charge of doing the execution of the module with the actions requested from the codeblock

Parameters

- **func** (*Callable*) – The function to be operated according to the specified options.
- **optimizer** – The Optimizer that will be used for parameter update.
- **backprop** (*bool*) – Flag to specify if gradients are to be calculated.
- **backprop_from** (*Optional[str]*) – Select a single output from the block execution to perform the gradient calculation.
- **backprop_to** (*Optional[Set[str]]*) – Name of the values where backpropagation will be stopped.
- **state** (*Dict[str, Any]*) – Data that can be used during the CodeBlock execution.
- **optimizers** (*List[Optimizer]*) –
- **runtime** (*Any*) –

Methods

`__init__(func, optimizers, backprop, ...)`

`load_state_dict(state)`

`state_dict()`

Attributes

`func`

`optimizers`

`backprop`

`backprop_from`

`backprop_to`

`state`

`runtime`

`__call__(inputs)`

Call self as a function.

Parameters

`inputs (Any) –`

Return type

`Any`

`__init__(func, optimizers, backprop, backprop_from, backprop_to, state, runtime)`

Parameters

- `func (Callable) –`
- `optimizers (List[Optimizer]) –`
- `backprop (bool) –`
- `backprop_from (Optional[str]) –`
- `backprop_to (Optional[Set[str]]) –`
- `state (Dict[str, Any]) –`
- `runtime (Any) –`

Return type

`None`

```
backprop: bool
backprop_from: Optional[str]
backprop_to: Optional[Set[str]]
func: Callable
load_state_dict(state)

    Parameters
        state (Dict[str, Any]) –

    Return type
        None

optimizers: List[Optimizer]
runtime: Any
state: Dict[str, Any]
state_dict()

    Return type
        Dict[str, Any]
```

[pytorch_pfn_extras.handler.CodeBlockLogic](#)

```
class pytorch_pfn_extras.handler.CodeBlockLogic(model_name='main', options=None)
Bases: BaseLogic
```

A set of methods that defines the training logic.

Parameters

- **model_name** (str) – Name of the model. Default is 'main'.
- **options** (dict, optional) – The configuration options.
 - **'backward_outputs'** (list of str):
A list of names of outputs that require computation of the gradient.

Methods

<code>__init__([model_name, options])</code>	A set of methods that defines the training logic.
<code>consume_options(options)</code>	A method to update options of Logic.
<code>eval_step(models, batch_idx, batch)</code>	A method for an evaluation step.
<code>train_epoch_begin(models, epoch, loader)</code>	A method called when starting a new epoch of training.
<code>train_epoch_end(models, epoch)</code>	A method called when completing an epoch of training.
<code>train_step(models, optimizers, batch_idx, batch)</code>	A method invokes the model forward and backward passes.
<code>train_step_optimizers(models, optimizers, ...)</code>	A method in charge of stepping the provided optimizers.
<code>train_validation_begin(models)</code>	A method called when starting a validation.
<code>train_validation_end(models)</code>	A method called when the validation completes.

`__init__(model_name='main', options=None)`

A set of methods that defines the training logic.

Parameters

- **model_name** (*str*) – Name of the model. Default is 'main'.
- **options** (*dict, optional*) – The configuration options.
 - **'backward_outputs'** (*list of str*):
A list of names of outputs that require computation of the gradient.

Return type

None

`consume_options(options)`

A method to update options of Logic.

Note that the given dict will be modified.

Parameters

- **options** (*dict*) – Option key-values to be set.

Return type

None

`eval_step(models, batch_idx, batch)`

A method for an evaluation step.

Parameters

- **models** (*dict of torch.nn.Module*) – The models.
- **batch_idx** (*int*) – Number of steps already finished.
- **batch** (*torch.Tensor, list of torch.Tensor, dict of torch.Tensor*) – Input tensors feeded to the model of the current step.

Return type

Any

`train_epoch_begin(models, epoch, loader)`

A method called when starting a new epoch of training.

Parameters

- **epoch** (*int*) – Number of epochs already finished.
- **models** (*dict of torch.nn.Module*) – The models.
- **loader** (*torch.utils.data.DataLoader*) – The data loader.

Return type

None

`train_epoch_end(models, epoch)`

A method called when completing an epoch of training.

Parameters

- **epoch** (*int*) – Number of epochs already finished.
- **models** (*dict of torch.nn.Module*) – The models.

Return type

None

train_step(*models*, *optimizers*, *batch_idx*, *batch*)

A method invokes the model forward and backward passes.

Optimizing is left to *train_step_optimizers* since maybe the user would like to aggregate the gradients of several iterations.

Parameters

- **models** (*dict of torch.nn.Module*) – The models.
- **optimizers** (*dict of torch.optim.Optimizer*) – The optimizers.
- **batch_idx** (*int*) – Number of training steps already finished.
- **batch** (*torch.Tensor*, *list of torch.Tensor*, *dict of torch.Tensor*) – Input tensors feeded to the model of the current step.

Return type

Any

train_validation_begin(*models*)

A method called when starting a validation.

Parameters

- **models** (*dict of torch.nn.Module*) – The models.

Return type

None

train_validation_end(*models*)

A method called when the validation completes.

Parameters

- **models** (*dict of torch.nn.Module*) – The models.

Return type

None

pytorch_pfn_extras.handler.Handler

class `pytorch_pfn_extras.handler.Handler`(*logic*, *entry_runtime*, *options*)

Bases: *BaseHandler*

A set of callback functions to perform device-specific operations.

Parameters

- **logic** ([Logic](#)) – A logic.
- **entry_runtime** ([BaseRuntime](#)) – A runtime object.
- **options** (*dict*) – The configuration options.
 - **'eval_report_keys'** (*list of str*):
A list of names of outputs that are given as inputs of `reporting.report` after each evaluation step. Default is an empty list.
 - **'train_report_keys'** (*list of str*):
A list of names of outputs that are given as inputs of `reporting.report` after each training step. Default is an empty list.

Methods

<code>__init__(logic, entry_runtime, options)</code>	A set of callback functions to perform device-specific operations.
<code>consume_options(options)</code>	A method to update options of Handler.
<code>eval_loop_begin(evaluator)</code>	A method called before each evaluation step.
<code>eval_loop_end(evaluator)</code>	A method called after running all steps of the evaluation.
<code>eval_post_step(evaluator, batch_idx, batch, ...)</code>	A method called after each evaluation step.
<code>eval_setup(evaluator, loader)</code>	Called only once when starting a training run.
<code>eval_step(evaluator, batch_idx, batch, ...)</code>	Evaluation iteration.
<code>train_cleanup(trainer)</code>	A method called only once when completing a training run.
<code>train_epoch_begin(trainer, loader)</code>	A method called when starting a new epoch.
<code>train_epoch_end(trainer)</code>	A method called when finishing an epoch.
<code>train_post_step(trainer, batch_idx, batch, ...)</code>	A method called after each training step.
<code>train_setup(trainer, loader)</code>	A method called only once when starting a training run.
<code>train_step(trainer, batch_idx, batch, ...)</code>	A training step.
<code>train_validation_begin(trainer, evaluator)</code>	A method called when starting a validation.
<code>train_validation_end(trainer, evaluator)</code>	A method called after validation.

`__init__(logic, entry_runtime, options)`

A set of callback functions to perform device-specific operations.

Parameters

- `logic (Logic)` – A logic.
- `entry_runtime (BaseRuntime)` – A runtime object.
- `options (dict)` – The configuration options.
 - `'eval_report_keys' (list of str)`:
A list of names of outputs that are given as inputs of `reporting.report` after each evaluation step. Default is an empty list.
 - `'train_report_keys' (list of str)`:
A list of names of outputs that are given as inputs of `reporting.report` after each training step. Default is an empty list.

Return type

None

`consume_options(options)`

A method to update options of Handler.

Note that the given dict will be modified.

Parameters

`options (dict)` – Option key-values to be set.

Return type

None

`eval_loop_end(evaluator)`

A method called after running all steps of the evaluation.

Parameters

• **evaluator** ([Evaluator](#)) – The evaluator.

Return type

None

eval_post_step(*evaluator*, *batch_idx*, *batch*, *outputs*)

A method called after each evaluation step.

Parameters

- **evaluator** ([Evaluator](#)) – The evaluator.
- **batch_idx** (*int*) – Number of iterations already finished.
- **batch** (*dict of torch.Tensor*) – Input tensors of this batch.
- **complete_fn** (*callable*) – A callback function called after training step.
- **outputs** (*Any*) –

Return type

None

eval_setup(*evaluator*, *loader*)

Called only once when starting a training run. When evaluator is not given, this method is not called.

Parameters

- **evaluator** ([Evaluator](#)) – The evaluator.
- **loader** (*torch.utils.data.DataLoader*) – The data loader.

Return type

None

eval_step(*evaluator*, *batch_idx*, *batch*, *complete_fn*)

Evaluation iteration.

Parameters

- **evaluator** ([Evaluator](#)) – The evaluator.
- **batch_idx** (*int*) – Number of iterations already finished.
- **batch** (*dict of torch.Tensor*) – Input tensors of this batch.
- **complete_fn** (*callable*) – A callback function called after training step.

Return type

None

train_cleanup(*trainer*)

A method called only once when completing a training run.

Parameters

- **trainer** ([Trainer](#)) – The trainer that calls this method.
- **loader** (*torch.utils.data.DataLoader*) – The data loader.

Return type

None

train_epoch_begin(*trainer, loader*)

A method called when starting a new epoch.

Parameters

- **trainer** ([Trainer](#)) – The trainer that calls this method.
- **loader** ([torch.utils.data.DataLoader](#)) – The data loader.

Return type

None

train_epoch_end(*trainer*)

A method called when finishing an epoch.

Parameters

- **trainer** ([Trainer](#)) – The trainer that calls this method.

Return type

None

train_post_step(*trainer, batch_idx, batch, outputs*)

A method called after each training step.

Parameters

- **trainer** ([Trainer](#)) – The trainer that calls this method.
- **batch_idx** ([int](#)) – Number of iterations
- **batch** ([dict of torch.Tensor](#)) – Input tensors of this batch.
- **outputs** ([dict of torch.Tensor](#)) – Output tensors of this batch.

Return type

None

train_setup(*trainer, loader*)

A method called only once when starting a training run.

Parameters

- **trainer** ([Trainer](#)) – The trainer that calls this method.
- **loader** ([torch.utils.data.DataLoader](#)) – The data loader.

Return type

None

train_step(*trainer, batch_idx, batch, complete_fn*)

A training step.

Parameters

- **trainer** ([Trainer](#)) – A trainer.
- **batch_idx** ([int](#)) – Number of iterations already finished.
- **batch** ([dict of torch.Tensor](#)) – Input tensors of this batch.
- **complete_fn** ([callable](#)) – A callback function called after training step.

Return type

None

train_validation_begin(*trainer, evaluator*)

A method called when starting a validation.

Parameters

- **evaluator** ([Evaluator](#)) – An evaluator.
- **trainer** ([Trainer](#)) –

Return type

None

train_validation_end(*trainer, evaluator*)

A method called after validation.

Parameters

- **trainer** ([Trainer](#)) – The trainer that calls this method.
- **evaluator** ([Evaluator](#)) – The evaluator used for validation.

Return type

None

pytorch_pfn_extras.handler.Logic

class `pytorch_pfn_extras.handler.Logic(model_name='main', options=None)`

Bases: [BaseLogic](#)

A set of methods that defines the training logic.

Parameters

- **model_name** (`str`) – Name of the model. Default is 'main'.
- **options** (`dict, optional`) – The configuration options.
 - **'backward_outputs'** (`list of str`):
A list of names of outputs that require computation of the gradient.
 - **'autocast'** (`bool or dict`):
If True, `torch.autocast` is enabled, using `{"enabled": True, "device_type": "cuda"}` as autocast options. The default is False which corresponds to the following options `{"enabled": False, "device_type": "cuda"}`. If dict, options are passed to `torch.autocast`.
 - **'grad_scaler'** (`torch.cuda.amp.GradScaler`):
A gradient scaler that outputs are applied to.

Methods

<code>__init__([model_name, options])</code>	A set of methods that defines the training logic.
<code>consume_options(options)</code>	A method to update options of Logic.
<code>eval_step(models, batch_idx, batch)</code>	A method for an evaluation step.
<code>train_epoch_begin(models, epoch, loader)</code>	A method called when starting a new epoch of training.
<code>train_epoch_end(models, epoch)</code>	A method called when completing an epoch of training.
<code>train_step(models, optimizers, batch_idx, batch)</code>	A method invokes the model forward and backward passes.
<code>train_step_optimizers(models, optimizers, ...)</code>	A method in charge of stepping the provided optimizers.
<code>train_validation_begin(models)</code>	A method called when starting a validation.
<code>train_validation_end(models)</code>	A method called when the validation completes.

`__init__(model_name='main', options=None)`

A set of methods that defines the training logic.

Parameters

- **model_name** (`str`) – Name of the model. Default is '`main`'.
- **options** (`dict, optional`) – The configuration options.
 - **'backward_outputs'** (`list of str`):
A list of names of outputs that require computation of the gradient.
 - **'autocast'** (`bool or dict`):
If `True`, `torch.autocast` is enabled, using `{"enabled": True, "device_type": "cuda"}` as autocast options. The default is `False` which corresponds to the following options `{"enabled": False, "device_type": "cuda"}`. If `dict`, options are passed to `torch.autocast`.
 - **'grad_scaler'** (`torch.cuda.amp.GradScaler`):
A gradient scaler that outputs are applied to.

Return type

`None`

`consume_options(options)`

A method to update options of Logic.

Note that the given dict will be modified.

Parameters

`options` (`dict`) – Option key-values to be set.

Return type

`None`

`eval_step(models, batch_idx, batch)`

A method for an evaluation step.

Parameters

- **models** (`dict of torch.nn.Module`) – The models.
- **batch_idx** (`int`) – Number of steps already finished.

- **batch**(*torch.Tensor, list of torch.Tensor, dict of torch.Tensor*) – Input tensors feeded to the model of the current step.

Return type

Any

train_epoch_begin(*models, epoch, loader*)

A method called when starting a new epoch of training.

Parameters

- **epoch** (*int*) – Number of epochs already finished.
- **models** (*dict of torch.nn.Module*) – The models.
- **loader** (*torch.utils.data.DataLoader*) – The data loder.

Return type

None

train_epoch_end(*models, epoch*)

A method called when completing an epoch of training.

Parameters

- **epoch** (*int*) – Number of epochs already finished.
- **models** (*dict of torch.nn.Module*) – The models.

Return type

None

train_step(*models, optimizers, batch_idx, batch*)

A method invokes the model forward and backward passes.

Optimizing is left to *train_step_optimizers* since maybe the user would like to aggregate the gradients of several iterations.

Parameters

- **models** (*dict of torch.nn.Module*) – The models.
- **optimizers** (*dict of torch.optim.Optimizer*) – The optimizers.
- **batch_idx** (*int*) – Number of training steps already finished.
- **batch**(*torch.Tensor, list of torch.Tensor, dict of torch.Tensor*) – Input tensors feeded to the model of the current step.

Return type

Any

train_step_optimizers(*models, optimizers, batch_idx*)

A method in charge of stepping the provided optimizers.

Also a grad scaler will be used if defined.

Parameters

- **optimizers** (*dict of torch.optim.Optimizer*) – The optimizers.
- **batch_idx** (*int*) – Number of steps already finished.
- **models** (*Mapping[str, Module]*) –

Return type

None

train_validation_begin(*models*)

A method called when starting a validation.

Parameters

models (*dict of torch.nn.Module*) – The models.

Return type

None

train_validation_end(*models*)

A method called when the validation completes.

Parameters

models (*dict of torch.nn.Module*) – The models.

Return type

None

pytorch_pfn_extras.logging**Functions**

**pytorch_pfn_extras.logging.
get_logger(*name*)**

Returns a child logger to be used by applications.

pytorch_pfn_extras.logging.get_logger**pytorch_pfn_extras.logging.get_logger(*name*)**

Returns a child logger to be used by applications.

Parameters

name (*str*) – Name used to register and retrieve the logger object.

Returns

A logging.Logger object used to log in the application code.

Return type

Logger

pytorch_pfn_extras.nn**Functions**

pytorch_pfn_extras.nn.ensure(tensor[, ...])

Checks the shape and type of a tensor.

[pytorch_pfn_extras.nn.ensure](#)

`pytorch_pfn_extras.nn.ensure(tensor, shape=None, dtype=None, broadcastable=False, can_cast=False)`

Checks the shape and type of a tensor.

Parameters

- **shape** (*Optional[Tuple[Optional[int], ...]]*) – Tuple with the desired shape. If the input tensor shape is not compatible, `ValueError` will be raised. If `None` is set as a dimension value, that dimension will be ignored.
- **dtype** (*Optional[dtype]*) – Checks if the `dtype` of the input tensor matches the provided one.
- **broadcastable** (`bool`) – Check if the shapes are compatible using broadcasting rules.
- **can_cast** (`bool`) – Check if the input tensor can be casted to the provided type.
- **tensor** (`Tensor`) –

Return type

`None`

Classes

<code>pytorch_pfn_extras.nn.Ensure(*[, shape, ...])</code>	Module to check the shape of a tensor.
<code>pytorch_pfn_extras.nn.ExtendedSequential()</code>	Sequential module with extended features from chainer.
<code>pytorch_pfn_extras.nn.LazyBatchNorm1d(...)</code>	BatchNorm1d module with lazy weight initialization.
<code>pytorch_pfn_extras.nn.LazyBatchNorm2d(...)</code>	BatchNorm2d module with lazy weight initialization.
<code>pytorch_pfn_extras.nn.LazyBatchNorm3d(...)</code>	BatchNorm3d module with lazy weight initialization.
<code>pytorch_pfn_extras.nn.LazyConv1d(...)</code>	Conv1d module with lazy weight initialization.
<code>pytorch_pfn_extras.nn.LazyConv2d(...)</code>	Conv2d module with lazy weight initialization.
<code>pytorch_pfn_extras.nn.LazyConv3d(...)</code>	Conv3d module with lazy weight initialization.
<code>pytorch_pfn_extras.nn.LazyLinear(...)</code>	Linear module with lazy weight initialization.

[pytorch_pfn_extras.nn.Ensure](#)

`class pytorch_pfn_extras.nn.Ensure(*, shape=None, dtype=None, broadcastable=False, can_cast=False)`

Bases: `Module`

Module to check the shape of a tensor.

Parameters

- **shape** (*Optional[Tuple[Optional[int], ...]]*) – Tuple with the desired shape. If the input tensor shape is not compatible, `ValueError` will be raised. If `None` is set as a dimension value, that dimension will be ignored.
- **dtype** (*Optional[dtype]*) – Checks if the `dtype` of the input tensor matches the provided one.
- **broadcastable** (`bool`) – Check if the shapes are compatible using broadcasting rules.
- **can_cast** (`bool`) – Check if the input tensor can be casted to the provided type.

Initializes internal Module state, shared by both `nn.Module` and `ScriptModule`.

Methods

<code>__init__(*[shape, dtype, broadcastable, ...])</code>	Initializes internal Module state, shared by both nn.Module and ScriptModule.
<code>add_module(name, module)</code>	Adds a child module to the current module.
<code>apply(fn)</code>	Applies <code>fn</code> recursively to every submodule (as returned by <code>.children()</code>) as well as self.
<code>bfloat16()</code>	Casts all floating point parameters and buffers to bfloat16 datatype.
<code>buffers([recurse])</code>	Returns an iterator over module buffers.
<code>children()</code>	Returns an iterator over immediate children modules.
<code>cpu()</code>	Moves all model parameters and buffers to the CPU.
<code>cuda([device])</code>	Moves all model parameters and buffers to the GPU.
<code>double()</code>	Casts all floating point parameters and buffers to double datatype.
<code>eval()</code>	Sets the module in evaluation mode.
<code>extra_repr()</code>	Set the extra representation of the module
<code>float()</code>	Casts all floating point parameters and buffers to float datatype.
<code>forward(input)</code>	Defines the computation performed at every call.
<code>get_buffer(target)</code>	Returns the buffer given by <code>target</code> if it exists, otherwise throws an error.
<code>get_extra_state()</code>	Returns any extra state to include in the module's state_dict.
<code>get_parameter(target)</code>	Returns the parameter given by <code>target</code> if it exists, otherwise throws an error.
<code>get_submodule(target)</code>	Returns the submodule given by <code>target</code> if it exists, otherwise throws an error.
<code>half()</code>	Casts all floating point parameters and buffers to half datatype.
<code>ipu([device])</code>	Moves all model parameters and buffers to the IPU.
<code>load_state_dict(state_dict[, strict])</code>	Copies parameters and buffers from <code>state_dict</code> into this module and its descendants.
<code>modules()</code>	Returns an iterator over all modules in the network.
<code>named_buffers([prefix, recurse, ...])</code>	Returns an iterator over module buffers, yielding both the name of the buffer as well as the buffer itself.
<code>named_children()</code>	Returns an iterator over immediate children modules, yielding both the name of the module as well as the module itself.
<code>named_modules([memo, prefix, remove_duplicate])</code>	Returns an iterator over all modules in the network, yielding both the name of the module as well as the module itself.
<code>named_parameters([prefix, recurse, ...])</code>	Returns an iterator over module parameters, yielding both the name of the parameter as well as the parameter itself.
<code>parameters([recurse])</code>	Returns an iterator over module parameters.
<code>register_backward_hook(hook)</code>	Registers a backward hook on the module.
<code>register_buffer(name, tensor[, persistent])</code>	Adds a buffer to the module.
<code>register_forward_hook(hook, *[, prepend, ...])</code>	Registers a forward hook on the module.
<code>register_forward_pre_hook(hook, *[, ...])</code>	Registers a forward pre-hook on the module.

continues on next page

Table 1 – continued from previous page

<code>register_full_backward_hook(hook[, prepend])</code>	Registers a backward hook on the module.
<code>register_full_backward_pre_hook(hook[, prepend])</code>	Registers a backward pre-hook on the module.
<code>register_load_state_dict_post_hook(hook)</code>	Registers a post hook to be run after module's <code>load_state_dict</code> is called.
<code>register_module(name, module)</code>	Alias for <code>add_module()</code> .
<code>register_parameter(name, param)</code>	Adds a parameter to the module.
<code>register_state_dict_pre_hook(hook)</code>	These hooks will be called with arguments: <code>self</code> , <code>prefix</code> , and <code>keep_vars</code> before calling <code>state_dict</code> on <code>self</code> .
<code>requires_grad_([requires_grad])</code>	Change if autograd should record operations on parameters in this module.
<code>set_extra_state(state)</code>	This function is called from <code>load_state_dict()</code> to handle any extra state found within the <code>state_dict</code> .
<code>share_memory()</code>	See <code>torch.Tensor.share_memory_()</code>
<code>state_dict(*args[, destination, prefix, ...])</code>	Returns a dictionary containing references to the whole state of the module.
<code>to(*args, **kwargs)</code>	Moves and/or casts the parameters and buffers.
<code>to_empty(*, device)</code>	Moves the parameters and buffers to the specified device without copying storage.
<code>train([mode])</code>	Sets the module in training mode.
<code>type(dst_type)</code>	Casts all parameters and buffers to <code>dst_type</code> .
<code>xpu([device])</code>	Moves all model parameters and buffers to the XPU.
<code>zero_grad([set_to_none])</code>	Sets gradients of all model parameters to zero.

Attributes

<code>T_destination</code>	alias of <code>TypeVar('T_destination', bound=Dict[str, Any])</code>
<code>call_super_init</code>	
<code>dump_patches</code>	

`__init__(*, shape=None, dtype=None, broadcastable=False, can_cast=False)`

Initializes internal Module state, shared by both nn.Module and ScriptModule.

Parameters

- `shape` (`Optional[Tuple[Optional[int], ...]]`) –
- `dtype` (`Optional[dtype]`) –
- `broadcastable` (`bool`) –
- `can_cast` (`bool`) –

`forward(input)`

Defines the computation performed at every call.

Should be overridden by all subclasses.

Note: Although the recipe for forward pass needs to be defined within this function, one should call the `Module` instance afterwards instead of this since the former takes care of running the registered hooks while the latter silently ignores them.

Parameters**input** (*Tensor*) –**Return type***Tensor***training:** `bool`**pytorch_pfn_extras.nn.ExtendedSequential**

```
class pytorch_pfn_extras.nn.ExtendedSequential(*args: Module)
class pytorch_pfn_extras.nn.ExtendedSequential(arg: OrderedDict[str, Module])
```

Bases: `Sequential`

Sequential module with extended features from chainer.

Initializes internal `Module` state, shared by both `nn.Module` and `ScriptModule`.**Methods**

<code>__init__(*)args</code>	Initializes internal <code>Module</code> state, shared by both <code>nn.Module</code> and <code>ScriptModule</code> .
<code>add_module(name, module)</code>	Adds a child module to the current module.
<code>append(module)</code>	Appends a given module to the end.
<code>apply(fn)</code>	Applies <code>fn</code> recursively to every submodule (as returned by <code>.children()</code>) as well as self.
<code>bfloat16()</code>	Casts all floating point parameters and buffers to <code>bfloat16</code> datatype.
<code>buffers([recurse])</code>	Returns an iterator over module buffers.
<code>children()</code>	Returns an iterator over immediate children modules.
<code>cpu()</code>	Moves all model parameters and buffers to the CPU.
<code>cuda([device])</code>	Moves all model parameters and buffers to the GPU.
<code>double()</code>	Casts all floating point parameters and buffers to <code>double</code> datatype.
<code>eval()</code>	Sets the module in evaluation mode.
<code>extend(sequential)</code>	
<code>extra_repr()</code>	Set the extra representation of the module
<code>float()</code>	Casts all floating point parameters and buffers to <code>float</code> datatype.
<code>forward(input)</code>	Defines the computation performed at every call.
<code>get_buffer(target)</code>	Returns the buffer given by <code>target</code> if it exists, otherwise throws an error.
<code>get_extra_state()</code>	Returns any extra state to include in the module's <code>state_dict</code> .

continues on next page

Table 2 – continued from previous page

<code>get_parameter(target)</code>	Returns the parameter given by <code>target</code> if it exists, otherwise throws an error.
<code>get_submodule(target)</code>	Returns the submodule given by <code>target</code> if it exists, otherwise throws an error.
<code>half()</code>	Casts all floating point parameters and buffers to <code>half</code> datatype.
<code>insert(index, module)</code>	
<code>ipu([device])</code>	Moves all model parameters and buffers to the IPU.
<code>load_state_dict(state_dict[, strict])</code>	Copies parameters and buffers from <code>state_dict</code> into this module and its descendants.
<code>modules()</code>	Returns an iterator over all modules in the network.
<code>named_buffers([prefix, recurse, ...])</code>	Returns an iterator over module buffers, yielding both the name of the buffer as well as the buffer itself.
<code>named_children()</code>	Returns an iterator over immediate children modules, yielding both the name of the module as well as the module itself.
<code>named_modules([memo, prefix, remove_duplicate])</code>	Returns an iterator over all modules in the network, yielding both the name of the module as well as the module itself.
<code>named_parameters([prefix, recurse, ...])</code>	Returns an iterator over module parameters, yielding both the name of the parameter as well as the parameter itself.
<code>parameters([recurse])</code>	Returns an iterator over module parameters.
<code>pop(key)</code>	
<code>register_backward_hook(hook)</code>	Registers a backward hook on the module.
<code>register_buffer(name, tensor[, persistent])</code>	Adds a buffer to the module.
<code>register_forward_hook(hook, *[, prepend, ...])</code>	Registers a forward hook on the module.
<code>register_forward_pre_hook(hook, *[, ...])</code>	Registers a forward pre-hook on the module.
<code>register_full_backward_hook(hook[, prepend])</code>	Registers a backward hook on the module.
<code>register_full_backward_pre_hook(hook[, prepend])</code>	Registers a backward pre-hook on the module.
<code>register_load_state_dict_post_hook(hook)</code>	Registers a post hook to be run after module's <code>load_state_dict</code> is called.
<code>register_module(name, module)</code>	Alias for <code>add_module()</code> .
<code>register_parameter(name, param)</code>	Adds a parameter to the module.
<code>register_state_dict_pre_hook(hook)</code>	These hooks will be called with arguments: <code>self</code> , <code>prefix</code> , and <code>keep_vars</code> before calling <code>state_dict</code> on <code>self</code> .
<code>repeat(n_repeat[, mode])</code>	Repeats this Sequential multiple times.
<code>requires_grad_([requires_grad])</code>	Change if autograd should record operations on parameters in this module.
<code>set_extra_state(state)</code>	This function is called from <code>load_state_dict()</code> to handle any extra state found within the <code>state_dict</code> .
<code>share_memory()</code>	See <code>torch.Tensor.share_memory_()</code>
<code>state_dict(*args[, destination, prefix, ...])</code>	Returns a dictionary containing references to the whole state of the module.
<code>to(*args, **kwargs)</code>	Moves and/or casts the parameters and buffers.

continues on next page

Table 2 – continued from previous page

<code>to_empty(*, device)</code>	Moves the parameters and buffers to the specified device without copying storage.
<code>train([mode])</code>	Sets the module in training mode.
<code>type(dst_type)</code>	Casts all parameters and buffers to <code>dst_type</code> .
<code>xpu([device])</code>	Moves all model parameters and buffers to the XPU.
<code>zero_grad([set_to_none])</code>	Sets gradients of all model parameters to zero.

Attributes

<code>T_destination</code>	alias of <code>TypeVar('T_destination', bound=Dict[str, Any])</code>
<code>call_super_init</code>	
<code>dump_patches</code>	

`repeat(n_repeat, mode='init')`

Repeats this Sequential multiple times.

This method returns a `Sequential` object which has original `Sequential` multiple times repeatedly. The `mode` argument means how to copy this sequential to repeat.

The functions is supposed to behave the same way as `repeat` in `chainer`.

When the mode is set to `init`, the default value, modules will be copied and reinitialized by calling `reset_parameters` (or `_reset_parameters`) method.

To repeat user-defined modules, which have parameters or buffers, with mode=``init`` in this `Sequential`, you need to implement the `reset_parameters` or `_reset_parameters` method to the module to reinitialize parameters and (if necessary) buffers; otherwise the initialization cannot be performed and a warning message will be shown.

Parameters

- **`n_repeat` (int)** – Number of times to repeat.
- **`mode` (str)** – It should be either `init`, `copy`, or `share`. `init` means parameters of each repeated element in the returned `Sequential` will be re-initialized, so that all elements have different initial parameters. `copy` means that the parameters will not be re-initialized but object itself will be deep-copied, so that all elements have same initial parameters but can be changed independently. `share` means all the elements which consist the resulting `Sequential` object are same object because they are shallow-copied, so that all parameters of elements are shared with each other.

Return type

`ExtendedSequential`

[pytorch_pfn_extras.nn.LazyBatchNorm1d](#)

```
class pytorch_pfn_extras.nn.LazyBatchNorm1d(num_features, *args, **kwargs)
```

Bases: `_LazyBatchNorm`, `BatchNorm1d`

BatchNorm1d module with lazy weight initialization.

When `num_features` is `None`, it is determined at the first time of the forward step.

Initializes internal Module state, shared by both `nn.Module` and `ScriptModule`.

Methods

<code>__init__(num_features, *args, **kwargs)</code>	Initializes internal Module state, shared by both <code>nn.Module</code> and <code>ScriptModule</code> .
<code>add_module(name, module)</code>	Adds a child module to the current module.
<code>apply(fn)</code>	Applies <code>fn</code> recursively to every submodule (as returned by <code>.children()</code>) as well as self.
<code>bfloat16()</code>	Casts all floating point parameters and buffers to <code>bfloat16</code> datatype.
<code>buffers([recurse])</code>	Returns an iterator over module buffers.
<code>children()</code>	Returns an iterator over immediate children modules.
<code>cpu()</code>	Moves all model parameters and buffers to the CPU.
<code>cuda([device])</code>	Moves all model parameters and buffers to the GPU.
<code>double()</code>	Casts all floating point parameters and buffers to <code>double</code> datatype.
<code>eval()</code>	Sets the module in evaluation mode.
<code>extra_repr()</code>	Set the extra representation of the module
<code>float()</code>	Casts all floating point parameters and buffers to <code>float</code> datatype.
<code>forward(input)</code>	Defines the computation performed at every call.
<code>get_buffer(target)</code>	Returns the buffer given by <code>target</code> if it exists, otherwise throws an error.
<code>get_extra_state()</code>	Returns any extra state to include in the module's <code>state_dict</code> .
<code>get_parameter(target)</code>	Returns the parameter given by <code>target</code> if it exists, otherwise throws an error.
<code>get_submodule(target)</code>	Returns the submodule given by <code>target</code> if it exists, otherwise throws an error.
<code>half()</code>	Casts all floating point parameters and buffers to <code>half</code> datatype.
<code>ipu([device])</code>	Moves all model parameters and buffers to the IPU.
<code>load_state_dict(state_dict[, strict])</code>	Copies parameters and buffers from <code>state_dict</code> into this module and its descendants.
<code>modules()</code>	Returns an iterator over all modules in the network.
<code>named_buffers([prefix, recurse, ...])</code>	Returns an iterator over module buffers, yielding both the name of the buffer as well as the buffer itself.
<code>named_children()</code>	Returns an iterator over immediate children modules, yielding both the name of the module as well as the module itself.

continues on next page

Table 3 – continued from previous page

<code>named_modules([memo, prefix, remove_duplicate])</code>	Returns an iterator over all modules in the network, yielding both the name of the module as well as the module itself.
<code>named_parameters([prefix, recurse, ...])</code>	Returns an iterator over module parameters, yielding both the name of the parameter as well as the parameter itself.
<code>parameters([recurse])</code>	Returns an iterator over module parameters.
<code>register_backward_hook(hook)</code>	Registers a backward hook on the module.
<code>register_buffer(name, tensor[, persistent])</code>	Adds a buffer to the module.
<code>register_forward_hook(hook, *[, prepend, ...])</code>	Registers a forward hook on the module.
<code>register_forward_pre_hook(hook, *[, ...])</code>	Registers a forward pre-hook on the module.
<code>register_full_backward_hook(hook[, prepend])</code>	Registers a backward hook on the module.
<code>register_full_backward_pre_hook(hook[, prepend])</code>	Registers a backward pre-hook on the module.
<code>register_load_state_dict_post_hook(hook)</code>	Registers a post hook to be run after module's <code>load_state_dict</code> is called.
<code>register_module(name, module)</code>	Alias for <code>add_module()</code> .
<code>register_parameter(name, param)</code>	Adds a parameter to the module.
<code>register_state_dict_pre_hook(hook)</code>	These hooks will be called with arguments: <code>self</code> , <code>prefix</code> , and <code>keep_vars</code> before calling <code>state_dict</code> on <code>self</code> .
<code>requires_grad_([requires_grad])</code>	Change if autograd should record operations on parameters in this module.
<code>reset_parameters()</code>	
<code>reset_running_stats()</code>	
<code>set_extra_state(state)</code>	This function is called from <code>load_state_dict()</code> to handle any extra state found within the <code>state_dict</code> .
<code>share_memory()</code>	See <code>torch.Tensor.share_memory_()</code>
<code>state_dict(*args, **kwargs)</code>	Returns a dictionary containing a whole state of the module.
<code>to(*args, **kwargs)</code>	Moves and/or casts the parameters and buffers.
<code>to_empty(*, device)</code>	Moves the parameters and buffers to the specified device without copying storage.
<code>train([mode])</code>	Sets the module in training mode.
<code>type(dst_type)</code>	Casts all parameters and buffers to <code>dst_type</code> .
<code>xpu([device])</code>	Moves all model parameters and buffers to the XPU.
<code>zero_grad([set_to_none])</code>	Sets gradients of all model parameters to zero.

Attributes

T_destination	alias of TypeVar('T_destination', bound=Dict[str, Any])
call_super_init	
dump_patches	
lazy_buffer_names	
lazy_parameter_names	
lazy_parameters_determined	Returns if all lazy parameters are determined.

Parameters

- **num_features** (*int*) –
- **args** (*Any*) –
- **kwargs** (*Any*) –

running_mean: *Any*

running_var: *Any*

pytorch_pfn_extras.nn.LazyBatchNorm2d

class pytorch_pfn_extras.nn.LazyBatchNorm2d(*num_features*, **args*, ***kwargs*)

Bases: _LazyBatchNorm, BatchNorm2d

BatchNorm2d module with lazy weight initialization.

When *num_features* is None, it is determined at the first time of the forward step.

Initializes internal Module state, shared by both nn.Module and ScriptModule.

Methods

__init__(<i>num_features</i> , * <i>args</i> , ** <i>kwargs</i>)	Initializes internal Module state, shared by both nn.Module and ScriptModule.
add_module(<i>name</i> , <i>module</i>)	Adds a child module to the current module.
apply(<i>fn</i>)	Applies <i>fn</i> recursively to every submodule (as returned by .children()) as well as self.
bfloat16()	Casts all floating point parameters and buffers to bfloat16 datatype.
buffers([reuse])	Returns an iterator over module buffers.
children()	Returns an iterator over immediate children modules.
cpu()	Moves all model parameters and buffers to the CPU.
cuda([device])	Moves all model parameters and buffers to the GPU.
double()	Casts all floating point parameters and buffers to double datatype.

continues on next page

Table 4 – continued from previous page

<code>eval()</code>	Sets the module in evaluation mode.
<code>extra_repr()</code>	Set the extra representation of the module
<code>float()</code>	Casts all floating point parameters and buffers to <code>float</code> datatype.
<code>forward(input)</code>	Defines the computation performed at every call.
<code>get_buffer(target)</code>	Returns the buffer given by <code>target</code> if it exists, otherwise throws an error.
<code>get_extra_state()</code>	Returns any extra state to include in the module's <code>state_dict</code> .
<code>get_parameter(target)</code>	Returns the parameter given by <code>target</code> if it exists, otherwise throws an error.
<code>get_submodule(target)</code>	Returns the submodule given by <code>target</code> if it exists, otherwise throws an error.
<code>half()</code>	Casts all floating point parameters and buffers to <code>half</code> datatype.
<code>ipu([device])</code>	Moves all model parameters and buffers to the IPU.
<code>load_state_dict(state_dict[, strict])</code>	Copies parameters and buffers from <code>state_dict</code> into this module and its descendants.
<code>modules()</code>	Returns an iterator over all modules in the network.
<code>named_buffers([prefix, recurse, ...])</code>	Returns an iterator over module buffers, yielding both the name of the buffer as well as the buffer itself.
<code>named_children()</code>	Returns an iterator over immediate children modules, yielding both the name of the module as well as the module itself.
<code>named_modules([memo, prefix, remove_duplicate])</code>	Returns an iterator over all modules in the network, yielding both the name of the module as well as the module itself.
<code>named_parameters([prefix, recurse, ...])</code>	Returns an iterator over module parameters, yielding both the name of the parameter as well as the parameter itself.
<code>parameters([recurse])</code>	Returns an iterator over module parameters.
<code>register_backward_hook(hook)</code>	Registers a backward hook on the module.
<code>register_buffer(name, tensor[, persistent])</code>	Adds a buffer to the module.
<code>register_forward_hook(hook, *[, prepend, ...])</code>	Registers a forward hook on the module.
<code>register_forward_pre_hook(hook, *[, ...])</code>	Registers a forward pre-hook on the module.
<code>register_full_backward_hook(hook[, prepend])</code>	Registers a backward hook on the module.
<code>register_full_backward_pre_hook(hook[, prepend])</code>	Registers a backward pre-hook on the module.
<code>register_load_state_dict_post_hook(hook)</code>	Registers a post hook to be run after module's <code>load_state_dict</code> is called.
<code>register_module(name, module)</code>	Alias for <code>add_module()</code> .
<code>register_parameter(name, param)</code>	Adds a parameter to the module.
<code>register_state_dict_pre_hook(hook)</code>	These hooks will be called with arguments: <code>self</code> , <code>prefix</code> , and <code>keep_vars</code> before calling <code>state_dict</code> on <code>self</code> .
<code>requires_grad_(requires_grad)</code>	Change if autograd should record operations on parameters in this module.
<code>reset_parameters()</code>	

continues on next page

Table 4 – continued from previous page

<code>reset_running_stats()</code>	
<code>set_extra_state(state)</code>	This function is called from <code>load_state_dict()</code> to handle any extra state found within the <code>state_dict</code> .
<code>share_memory()</code>	See <code>torch.Tensor.share_memory_()</code>
<code>state_dict(*args, **kwargs)</code>	Returns a dictionary containing a whole state of the module.
<code>to(*args, **kwargs)</code>	Moves and/or casts the parameters and buffers.
<code>to_empty(*, device)</code>	Moves the parameters and buffers to the specified device without copying storage.
<code>train([mode])</code>	Sets the module in training mode.
<code>type(dst_type)</code>	Casts all parameters and buffers to <code>dst_type</code> .
<code>xpu([device])</code>	Moves all model parameters and buffers to the XPU.
<code>zero_grad([set_to_none])</code>	Sets gradients of all model parameters to zero.

Attributes

<code>T_destination</code>	alias of <code>TypeVar('T_destination', bound=Dict[str, Any])</code>
<code>call_super_init</code>	
<code>dump_patches</code>	
<code>lazy_buffer_names</code>	
<code>lazy_parameter_names</code>	
<code>lazy_parameters_determined</code>	Returns if all lazy parameters are determined.

Parameters

- `num_features (int)` –
- `args (Any)` –
- `kwargs (Any)` –

`running_mean: Any`

`running_var: Any`

pytorch_pfn_extras.nn.LazyBatchNorm3d

`class pytorch_pfn_extras.nn.LazyBatchNorm3d(num_features, *args, **kwargs)`

Bases: `_LazyBatchNorm, BatchNorm3d`

BatchNorm3d module with lazy weight initialization.

When `num_features` is `None`, it is determined at the first time of the forward step.

Initializes internal Module state, shared by both `nn.Module` and `ScriptModule`.

Methods

<code>__init__(num_features, *args, **kwargs)</code>	Initializes internal Module state, shared by both nn.Module and ScriptModule.
<code>add_module(name, module)</code>	Adds a child module to the current module.
<code>apply(fn)</code>	Applies <code>fn</code> recursively to every submodule (as returned by <code>.children()</code>) as well as self.
<code>bfloat16()</code>	Casts all floating point parameters and buffers to bfloat16 datatype.
<code>buffers([recurse])</code>	Returns an iterator over module buffers.
<code>children()</code>	Returns an iterator over immediate children modules.
<code>cpu()</code>	Moves all model parameters and buffers to the CPU.
<code>cuda([device])</code>	Moves all model parameters and buffers to the GPU.
<code>double()</code>	Casts all floating point parameters and buffers to <code>double</code> datatype.
<code>eval()</code>	Sets the module in evaluation mode.
<code>extra_repr()</code>	Set the extra representation of the module
<code>float()</code>	Casts all floating point parameters and buffers to <code>float</code> datatype.
<code>forward(input)</code>	Defines the computation performed at every call.
<code>get_buffer(target)</code>	Returns the buffer given by <code>target</code> if it exists, otherwise throws an error.
<code>get_extra_state()</code>	Returns any extra state to include in the module's state_dict.
<code>get_parameter(target)</code>	Returns the parameter given by <code>target</code> if it exists, otherwise throws an error.
<code>get_submodule(target)</code>	Returns the submodule given by <code>target</code> if it exists, otherwise throws an error.
<code>half()</code>	Casts all floating point parameters and buffers to <code>half</code> datatype.
<code>ipu([device])</code>	Moves all model parameters and buffers to the IPU.
<code>load_state_dict(state_dict[, strict])</code>	Copies parameters and buffers from <code>state_dict</code> into this module and its descendants.
<code>modules()</code>	Returns an iterator over all modules in the network.
<code>named_buffers([prefix, recurse, ...])</code>	Returns an iterator over module buffers, yielding both the name of the buffer as well as the buffer itself.
<code>named_children()</code>	Returns an iterator over immediate children modules, yielding both the name of the module as well as the module itself.
<code>named_modules([memo, prefix, remove_duplicate])</code>	Returns an iterator over all modules in the network, yielding both the name of the module as well as the module itself.
<code>named_parameters([prefix, recurse, ...])</code>	Returns an iterator over module parameters, yielding both the name of the parameter as well as the parameter itself.
<code>parameters([recurse])</code>	Returns an iterator over module parameters.
<code>register_backward_hook(hook)</code>	Registers a backward hook on the module.
<code>register_buffer(name, tensor[, persistent])</code>	Adds a buffer to the module.
<code>register_forward_hook(hook, *[, prepend, ...])</code>	Registers a forward hook on the module.
<code>register_forward_pre_hook(hook, *[, ...])</code>	Registers a forward pre-hook on the module.

continues on next page

Table 5 – continued from previous page

<code>register_full_backward_hook(hook[, prepend])</code>	Registers a backward hook on the module.
<code>register_full_backward_pre_hook(hook[, prepend])</code>	Registers a backward pre-hook on the module.
<code>register_load_state_dict_post_hook(hook)</code>	Registers a post hook to be run after module's <code>load_state_dict</code> is called.
<code>register_module(name, module)</code>	Alias for <code>add_module()</code> .
<code>register_parameter(name, param)</code>	Adds a parameter to the module.
<code>register_state_dict_pre_hook(hook)</code>	These hooks will be called with arguments: <code>self</code> , <code>prefix</code> , and <code>keep_vars</code> before calling <code>state_dict</code> on <code>self</code> .
<code>requires_grad_([requires_grad])</code>	Change if autograd should record operations on parameters in this module.
<code>reset_parameters()</code>	
<code>reset_running_stats()</code>	
<code>set_extra_state(state)</code>	This function is called from <code>load_state_dict()</code> to handle any extra state found within the <code>state_dict</code> .
<code>share_memory()</code>	See <code>torch.Tensor.share_memory_()</code>
<code>state_dict(*args, **kwargs)</code>	Returns a dictionary containing a whole state of the module.
<code>to(*args, **kwargs)</code>	Moves and/or casts the parameters and buffers.
<code>to_empty(*, device)</code>	Moves the parameters and buffers to the specified device without copying storage.
<code>train([mode])</code>	Sets the module in training mode.
<code>type(dst_type)</code>	Casts all parameters and buffers to <code>dst_type</code> .
<code>xpu([device])</code>	Moves all model parameters and buffers to the XPU.
<code>zero_grad([set_to_none])</code>	Sets gradients of all model parameters to zero.

Attributes

<code>T_destination</code>	alias of <code>TypeVar('T_destination', bound=Dict[str, Any])</code>
<code>call_super_init</code>	
<code>dump_patches</code>	
<code>lazy_buffer_names</code>	
<code>lazy_parameter_names</code>	
<code>lazy_parameters_determined</code>	Returns if all lazy parameters are determined.

Parameters

- **num_features** (`int`) –
- **args** (`Any`) –
- **kwargs** (`Any`) –

`running_mean: Any`
`running_var: Any`

pytorch_pfn_extras.nn.LazyConv1d

`class pytorch_pfn_extras.nn.LazyConv1d(in_channels, *args, **kwargs)`

Bases: `_LazyConvNd, Conv1d`

Conv1d module with lazy weight initialization.

When `in_channels` is `None`, it is determined at the first time of the forward step.

Initializes internal Module state, shared by both `nn.Module` and `ScriptModule`.

Methods

<code>__init__(in_channels, *args, **kwargs)</code>	Initializes internal Module state, shared by both <code>nn.Module</code> and <code>ScriptModule</code> .
<code>add_module(name, module)</code>	Adds a child module to the current module.
<code>apply(fn)</code>	Applies <code>fn</code> recursively to every submodule (as returned by <code>.children()</code>) as well as self.
<code>bfloat16()</code>	Casts all floating point parameters and buffers to <code>bfloat16</code> datatype.
<code>buffers([recurse])</code>	Returns an iterator over module buffers.
<code>children()</code>	Returns an iterator over immediate children modules.
<code>cpu()</code>	Moves all model parameters and buffers to the CPU.
<code>cuda([device])</code>	Moves all model parameters and buffers to the GPU.
<code>double()</code>	Casts all floating point parameters and buffers to <code>double</code> datatype.
<code>eval()</code>	Sets the module in evaluation mode.
<code>extra_repr()</code>	Set the extra representation of the module
<code>float()</code>	Casts all floating point parameters and buffers to <code>float</code> datatype.
<code>forward(input)</code>	Defines the computation performed at every call.
<code>get_buffer(target)</code>	Returns the buffer given by <code>target</code> if it exists, otherwise throws an error.
<code>get_extra_state()</code>	Returns any extra state to include in the module's <code>state_dict</code> .
<code>get_parameter(target)</code>	Returns the parameter given by <code>target</code> if it exists, otherwise throws an error.
<code>get_submodule(target)</code>	Returns the submodule given by <code>target</code> if it exists, otherwise throws an error.
<code>half()</code>	Casts all floating point parameters and buffers to <code>half</code> datatype.
<code>ipu([device])</code>	Moves all model parameters and buffers to the IPU.
<code>load_state_dict(state_dict[, strict])</code>	Copies parameters and buffers from <code>state_dict</code> into this module and its descendants.
<code>modules()</code>	Returns an iterator over all modules in the network.
<code>named_buffers([prefix, recurse, ...])</code>	Returns an iterator over module buffers, yielding both the name of the buffer as well as the buffer itself.

continues on next page

Table 6 – continued from previous page

<code>named_children()</code>	Returns an iterator over immediate children modules, yielding both the name of the module as well as the module itself.
<code>named_modules([memo, prefix, remove_duplicate])</code>	Returns an iterator over all modules in the network, yielding both the name of the module as well as the module itself.
<code>named_parameters([prefix, recurse, ...])</code>	Returns an iterator over module parameters, yielding both the name of the parameter as well as the parameter itself.
<code>parameters([recurse])</code>	Returns an iterator over module parameters.
<code>register_backward_hook(hook)</code>	Registers a backward hook on the module.
<code>register_buffer(name, tensor[, persistent])</code>	Adds a buffer to the module.
<code>register_forward_hook(hook, *[, prepend, ...])</code>	Registers a forward hook on the module.
<code>register_forward_pre_hook(hook, *[, ...])</code>	Registers a forward pre-hook on the module.
<code>register_full_backward_hook(hook[, prepend])</code>	Registers a backward hook on the module.
<code>register_full_backward_pre_hook(hook[, prepend])</code>	Registers a backward pre-hook on the module.
<code>register_load_state_dict_post_hook(hook)</code>	Registers a post hook to be run after module's <code>load_state_dict</code> is called.
<code>register_module(name, module)</code>	Alias for <code>add_module()</code> .
<code>register_parameter(name, param)</code>	Adds a parameter to the module.
<code>register_state_dict_pre_hook(hook)</code>	These hooks will be called with arguments: <code>self</code> , <code>prefix</code> , and <code>keep_vars</code> before calling <code>state_dict</code> on <code>self</code> .
<code>requires_grad_([requires_grad])</code>	Change if autograd should record operations on parameters in this module.
<code>reset_parameters()</code>	
<code>set_extra_state(state)</code>	This function is called from <code>load_state_dict()</code> to handle any extra state found within the <code>state_dict</code> .
<code>share_memory()</code>	See <code>torch.Tensor.share_memory_()</code>
<code>state_dict(*args, **kwargs)</code>	Returns a dictionary containing a whole state of the module.
<code>to(*args, **kwargs)</code>	Moves and/or casts the parameters and buffers.
<code>to_empty(*, device)</code>	Moves the parameters and buffers to the specified device without copying storage.
<code>train([mode])</code>	Sets the module in training mode.
<code>type(dst_type)</code>	Casts all parameters and buffers to <code>dst_type</code> .
<code>xpu([device])</code>	Moves all model parameters and buffers to the XPU.
<code>zero_grad([set_to_none])</code>	Sets gradients of all model parameters to zero.

Attributes

T_destination	alias of TypeVar('T_destination', bound=Dict[str, Any])
call_super_init	
dump_patches	
lazy_buffer_names	
lazy_parameter_names	
lazy_parameters_determined	Returns if all lazy parameters are determined.

Parameters

- **in_channels** (*int*) –
- **args** (*Any*) –
- **kwargs** (*Any*) –

pytorch_pfn_extras.nn.LazyConv2d

```
class pytorch_pfn_extras.nn.LazyConv2d(in_channels, *args, **kwargs)
```

Bases: _LazyConvNd, Conv2d

Conv2d module with lazy weight initialization.

When `in_channels` is `None`, it is determined at the first time of the forward step.

Initializes internal Module state, shared by both `nn.Module` and `ScriptModule`.

Methods

<code>__init__(in_channels, *args, **kwargs)</code>	Initializes internal Module state, shared by both <code>nn.Module</code> and <code>ScriptModule</code> .
<code>add_module(name, module)</code>	Adds a child module to the current module.
<code>apply(fn)</code>	Applies <code>fn</code> recursively to every submodule (as returned by <code>.children()</code>) as well as self.
<code>bfloat16()</code>	Casts all floating point parameters and buffers to <code>bfloat16</code> datatype.
<code>buffers([recurse])</code>	Returns an iterator over module buffers.
<code>children()</code>	Returns an iterator over immediate children modules.
<code>cpu()</code>	Moves all model parameters and buffers to the CPU.
<code>cuda([device])</code>	Moves all model parameters and buffers to the GPU.
<code>double()</code>	Casts all floating point parameters and buffers to <code>double</code> datatype.
<code>eval()</code>	Sets the module in evaluation mode.
<code>extra_repr()</code>	Set the extra representation of the module
<code>float()</code>	Casts all floating point parameters and buffers to <code>float</code> datatype.

continues on next page

Table 7 – continued from previous page

<code>forward(input)</code>	Defines the computation performed at every call.
<code>get_buffer(target)</code>	Returns the buffer given by <code>target</code> if it exists, otherwise throws an error.
<code>get_extra_state()</code>	Returns any extra state to include in the module's <code>state_dict</code> .
<code>get_parameter(target)</code>	Returns the parameter given by <code>target</code> if it exists, otherwise throws an error.
<code>get_submodule(target)</code>	Returns the submodule given by <code>target</code> if it exists, otherwise throws an error.
<code>half()</code>	Casts all floating point parameters and buffers to <code>half</code> datatype.
<code>ipu([device])</code>	Moves all model parameters and buffers to the IPU.
<code>load_state_dict(state_dict[, strict])</code>	Copies parameters and buffers from <code>state_dict</code> into this module and its descendants.
<code>modules()</code>	Returns an iterator over all modules in the network.
<code>named_buffers([prefix, recurse, ...])</code>	Returns an iterator over module buffers, yielding both the name of the buffer as well as the buffer itself.
<code>named_children()</code>	Returns an iterator over immediate children modules, yielding both the name of the module as well as the module itself.
<code>named_modules([memo, prefix, remove_duplicate])</code>	Returns an iterator over all modules in the network, yielding both the name of the module as well as the module itself.
<code>named_parameters([prefix, recurse, ...])</code>	Returns an iterator over module parameters, yielding both the name of the parameter as well as the parameter itself.
<code>parameters([recurse])</code>	Returns an iterator over module parameters.
<code>register_backward_hook(hook)</code>	Registers a backward hook on the module.
<code>register_buffer(name, tensor[, persistent])</code>	Adds a buffer to the module.
<code>register_forward_hook(hook, *[, prepend, ...])</code>	Registers a forward hook on the module.
<code>register_forward_pre_hook(hook, *[, ...])</code>	Registers a forward pre-hook on the module.
<code>register_full_backward_hook(hook[, prepend])</code>	Registers a backward hook on the module.
<code>register_full_backward_pre_hook(hook[, prepend])</code>	Registers a backward pre-hook on the module.
<code>register_load_state_dict_post_hook(hook)</code>	Registers a post hook to be run after module's <code>load_state_dict</code> is called.
<code>register_module(name, module)</code>	Alias for <code>add_module()</code> .
<code>register_parameter(name, param)</code>	Adds a parameter to the module.
<code>register_state_dict_pre_hook(hook)</code>	These hooks will be called with arguments: <code>self</code> , <code>prefix</code> , and <code>keep_vars</code> before calling <code>state_dict</code> on <code>self</code> .
<code>requires_grad_([requires_grad])</code>	Change if autograd should record operations on parameters in this module.
<code>reset_parameters()</code>	
<code>set_extra_state(state)</code>	This function is called from <code>load_state_dict()</code> to handle any extra state found within the <code>state_dict</code> .
<code>share_memory()</code>	See <code>torch.Tensor.share_memory_()</code>
<code>state_dict(*args, **kwargs)</code>	Returns a dictionary containing a whole state of the module.

continues on next page

Table 7 – continued from previous page

<code>to(*args, **kwargs)</code>	Moves and/or casts the parameters and buffers.
<code>to_empty(*, device)</code>	Moves the parameters and buffers to the specified device without copying storage.
<code>train([mode])</code>	Sets the module in training mode.
<code>type(dst_type)</code>	Casts all parameters and buffers to <code>dst_type</code> .
<code>xpu([device])</code>	Moves all model parameters and buffers to the XPU.
<code>zero_grad([set_to_none])</code>	Sets gradients of all model parameters to zero.

Attributes

<code>T_destination</code>	alias of <code>TypeVar('T_destination', bound=Dict[str, Any])</code>
<code>call_super_init</code>	
<code>dump_patches</code>	
<code>lazy_buffer_names</code>	
<code>lazy_parameter_names</code>	
<code>lazy_parameters_determined</code>	Returns if all lazy parameters are determined.

Parameters

- `in_channels (int)` –
- `args (Any)` –
- `kwargs (Any)` –

`pytorch_pfn_extras.nn.LazyConv3d`

```
class pytorch_pfn_extras.nn.LazyConv3d(in_channels, *args, **kwargs)
```

Bases: `_LazyConvNd, Conv3d`

Conv3d module with lazy weight initialization.

When `in_channels` is `None`, it is determined at the first time of the forward step.

Initializes internal Module state, shared by both `nn.Module` and `ScriptModule`.

Methods

<code>__init__(in_channels, *args, **kwargs)</code>	Initializes internal Module state, shared by both <code>nn.Module</code> and <code>ScriptModule</code> .
<code>add_module(name, module)</code>	Adds a child module to the current module.
<code>apply(fn)</code>	Applies <code>fn</code> recursively to every submodule (as returned by <code>.children()</code>) as well as self.
<code>bfloat16()</code>	Casts all floating point parameters and buffers to <code>bfloat16</code> datatype.

continues on next page

Table 8 – continued from previous page

<code>buffers([recurse])</code>	Returns an iterator over module buffers.
<code>children()</code>	Returns an iterator over immediate children modules.
<code>cpu()</code>	Moves all model parameters and buffers to the CPU.
<code>cuda([device])</code>	Moves all model parameters and buffers to the GPU.
<code>double()</code>	Casts all floating point parameters and buffers to <code>double</code> datatype.
<code>eval()</code>	Sets the module in evaluation mode.
<code>extra_repr()</code>	Set the extra representation of the module
<code>float()</code>	Casts all floating point parameters and buffers to <code>float</code> datatype.
<code>forward(input)</code>	Defines the computation performed at every call.
<code>get_buffer(target)</code>	Returns the buffer given by <code>target</code> if it exists, otherwise throws an error.
<code>get_extra_state()</code>	Returns any extra state to include in the module's <code>state_dict</code> .
<code>get_parameter(target)</code>	Returns the parameter given by <code>target</code> if it exists, otherwise throws an error.
<code>get_submodule(target)</code>	Returns the submodule given by <code>target</code> if it exists, otherwise throws an error.
<code>half()</code>	Casts all floating point parameters and buffers to <code>half</code> datatype.
<code>ipu([device])</code>	Moves all model parameters and buffers to the IPU.
<code>load_state_dict(state_dict[, strict])</code>	Copies parameters and buffers from <code>state_dict</code> into this module and its descendants.
<code>modules()</code>	Returns an iterator over all modules in the network.
<code>named_buffers([prefix, recurse, ...])</code>	Returns an iterator over module buffers, yielding both the name of the buffer as well as the buffer itself.
<code>named_children()</code>	Returns an iterator over immediate children modules, yielding both the name of the module as well as the module itself.
<code>named_modules([memo, prefix, remove_duplicate])</code>	Returns an iterator over all modules in the network, yielding both the name of the module as well as the module itself.
<code>named_parameters([prefix, recurse, ...])</code>	Returns an iterator over module parameters, yielding both the name of the parameter as well as the parameter itself.
<code>parameters([recurse])</code>	Returns an iterator over module parameters.
<code>register_backward_hook(hook)</code>	Registers a backward hook on the module.
<code>register_buffer(name, tensor[, persistent])</code>	Adds a buffer to the module.
<code>register_forward_hook(hook, *[, prepend, ...])</code>	Registers a forward hook on the module.
<code>register_forward_pre_hook(hook, *[, ...])</code>	Registers a forward pre-hook on the module.
<code>register_full_backward_hook(hook[, prepend])</code>	Registers a backward hook on the module.
<code>register_full_backward_pre_hook(hook[, prepend])</code>	Registers a backward pre-hook on the module.
<code>register_load_state_dict_post_hook(hook)</code>	Registers a post hook to be run after module's <code>load_state_dict</code> is called.
<code>register_module(name, module)</code>	Alias for <code>add_module()</code> .
<code>register_parameter(name, param)</code>	Adds a parameter to the module.

continues on next page

Table 8 – continued from previous page

<code>register_state_dict_pre_hook(hook)</code>	These hooks will be called with arguments: <code>self</code> , <code>prefix</code> , and <code>keep_vars</code> before calling <code>state_dict</code> on <code>self</code> .
<code>requires_grad_(requires_grad)</code>	Change if autograd should record operations on parameters in this module.
<code>reset_parameters()</code>	
<code>set_extra_state(state)</code>	This function is called from <code>load_state_dict()</code> to handle any extra state found within the <code>state_dict</code> .
<code>share_memory()</code>	See <code>torch.Tensor.share_memory_()</code>
<code>state_dict(*args, **kwargs)</code>	Returns a dictionary containing a whole state of the module.
<code>to(*args, **kwargs)</code>	Moves and/or casts the parameters and buffers.
<code>to_empty(*, device)</code>	Moves the parameters and buffers to the specified device without copying storage.
<code>train([mode])</code>	Sets the module in training mode.
<code>type(dst_type)</code>	Casts all parameters and buffers to <code>dst_type</code> .
<code>xpu([device])</code>	Moves all model parameters and buffers to the XPU.
<code>zero_grad([set_to_none])</code>	Sets gradients of all model parameters to zero.

Attributes

<code>T_destination</code>	alias of <code>TypeVar('T_destination', bound=Dict[str, Any])</code>
<code>call_super_init</code>	
<code>dump_patches</code>	
<code>lazy_buffer_names</code>	
<code>lazy_parameter_names</code>	
<code>lazy_parameters_determined</code>	Returns if all lazy parameters are determined.

Parameters

- `in_channels (int) –`
- `args (Any) –`
- `kwargs (Any) –`

[pytorch_pfn_extras.nn.LazyLinear](#)

```
class pytorch_pfn_extras.nn.LazyLinear(in_features, *args, **kwargs)
```

Bases: [LazyInitializationMixin](#), [Linear](#)

Linear module with lazy weight initialization.

When `in_features` is `None`, it is determined at the first time of the forward step.

Initializes internal Module state, shared by both `nn.Module` and `ScriptModule`.

Methods

<code>__init__(in_features, *args, **kwargs)</code>	Initializes internal Module state, shared by both <code>nn.Module</code> and <code>ScriptModule</code> .
<code>add_module(name, module)</code>	Adds a child module to the current module.
<code>apply(fn)</code>	Applies <code>fn</code> recursively to every submodule (as returned by <code>.children()</code>) as well as self.
<code>bfloat16()</code>	Casts all floating point parameters and buffers to <code>bfloat16</code> datatype.
<code>buffers([recurse])</code>	Returns an iterator over module buffers.
<code>children()</code>	Returns an iterator over immediate children modules.
<code>cpu()</code>	Moves all model parameters and buffers to the CPU.
<code>cuda([device])</code>	Moves all model parameters and buffers to the GPU.
<code>double()</code>	Casts all floating point parameters and buffers to <code>double</code> datatype.
<code>eval()</code>	Sets the module in evaluation mode.
<code>extra_repr()</code>	Set the extra representation of the module
<code>float()</code>	Casts all floating point parameters and buffers to <code>float</code> datatype.
<code>forward(input)</code>	Defines the computation performed at every call.
<code>get_buffer(target)</code>	Returns the buffer given by <code>target</code> if it exists, otherwise throws an error.
<code>get_extra_state()</code>	Returns any extra state to include in the module's <code>state_dict</code> .
<code>get_parameter(target)</code>	Returns the parameter given by <code>target</code> if it exists, otherwise throws an error.
<code>get_submodule(target)</code>	Returns the submodule given by <code>target</code> if it exists, otherwise throws an error.
<code>half()</code>	Casts all floating point parameters and buffers to <code>half</code> datatype.
<code>ipu([device])</code>	Moves all model parameters and buffers to the IPU.
<code>load_state_dict(state_dict[, strict])</code>	Copies parameters and buffers from <code>state_dict</code> into this module and its descendants.
<code>modules()</code>	Returns an iterator over all modules in the network.
<code>named_buffers([prefix, recurse, ...])</code>	Returns an iterator over module buffers, yielding both the name of the buffer as well as the buffer itself.
<code>named_children()</code>	Returns an iterator over immediate children modules, yielding both the name of the module as well as the module itself.

continues on next page

Table 9 – continued from previous page

<code>named_modules([memo, prefix, remove_duplicate])</code>	Returns an iterator over all modules in the network, yielding both the name of the module as well as the module itself.
<code>named_parameters([prefix, recurse, ...])</code>	Returns an iterator over module parameters, yielding both the name of the parameter as well as the parameter itself.
<code>parameters([recurse])</code>	Returns an iterator over module parameters.
<code>register_backward_hook(hook)</code>	Registers a backward hook on the module.
<code>register_buffer(name, tensor[, persistent])</code>	Adds a buffer to the module.
<code>register_forward_hook(hook, *[, prepend, ...])</code>	Registers a forward hook on the module.
<code>register_forward_pre_hook(hook, *[, ...])</code>	Registers a forward pre-hook on the module.
<code>register_full_backward_hook(hook[, prepend])</code>	Registers a backward hook on the module.
<code>register_full_backward_pre_hook(hook[, prepend])</code>	Registers a backward pre-hook on the module.
<code>register_load_state_dict_post_hook(hook)</code>	Registers a post hook to be run after module's <code>load_state_dict</code> is called.
<code>register_module(name, module)</code>	Alias for <code>add_module()</code> .
<code>register_parameter(name, param)</code>	Adds a parameter to the module.
<code>register_state_dict_pre_hook(hook)</code>	These hooks will be called with arguments: <code>self</code> , <code>prefix</code> , and <code>keep_vars</code> before calling <code>state_dict</code> on <code>self</code> .
<code>requires_grad_([requires_grad])</code>	Change if autograd should record operations on parameters in this module.
<code>reset_parameters()</code>	
<code>set_extra_state(state)</code>	This function is called from <code>load_state_dict()</code> to handle any extra state found within the <code>state_dict</code> . See <code>torch.Tensor.share_memory_()</code>
<code>share_memory()</code>	
<code>state_dict(*args, **kwargs)</code>	Returns a dictionary containing a whole state of the module.
<code>to(*args, **kwargs)</code>	Moves and/or casts the parameters and buffers.
<code>to_empty(*, device)</code>	Moves the parameters and buffers to the specified device without copying storage.
<code>train([mode])</code>	Sets the module in training mode.
<code>type(dst_type)</code>	Casts all parameters and buffers to <code>dst_type</code> .
<code>xpu([device])</code>	Moves all model parameters and buffers to the XPU.
<code>zero_grad([set_to_none])</code>	Sets gradients of all model parameters to zero.

Attributes

T_destination	alias of TypeVar('T_destination', bound=Dict[str, Any])
call_super_init	
dump_patches	
lazy_buffer_names	
lazy_parameter_names	
lazy_parameters_determined	Returns if all lazy parameters are determined.

Parameters

- **in_features** (*int*) –
- **args** (*Any*) –
- **kwargs** (*Any*) –

`__init__(in_features, *args, **kwargs)`

Initializes internal Module state, shared by both nn.Module and ScriptModule.

Parameters

- **in_features** (*Optional[int]*) –
- **args** (*Any*) –
- **kwargs** (*Any*) –

Return type

None

`forward(input)`

Defines the computation performed at every call.

Should be overridden by all subclasses.

Note: Although the recipe for forward pass needs to be defined within this function, one should call the Module instance afterwards instead of this since the former takes care of running the registered hooks while the latter silently ignores them.

Parameters

input (*Tensor*) –

Return type

Tensor

lazy_parameter_names: `Tuple[str, ...] = ('weight',)`

reset_parameters()

Return type

None

Modules

`pytorch_pfn_extras.nn.modules`

`pytorch_pfn_extras.nn.parallel`

pytorch_pfn_extras.nn.modules

Modules

`pytorch_pfn_extras.nn.modules.ensure_shape`

`pytorch_pfn_extras.nn.modules.
extended_sequential`

`pytorch_pfn_extras.nn.modules.lazy`

`pytorch_pfn_extras.nn.modules.
lazy_batchnorm`

`pytorch_pfn_extras.nn.modules.lazy_conv`

`pytorch_pfn_extras.nn.modules.lazy_linear`

pytorch_pfn_extras.nn.modules.ensure_shape

Functions

<code>pytorch_pfn_extras.nn.modules. ensure_shape.ensure(tensor)</code>	Checks the shape and type of a tensor.
---	--

pytorch_pfn_extras.nn.modules.ensure_shape.ensure

`pytorch_pfn_extras.nn.modules.ensure_shape.ensure(tensor, shape=None, dtype=None,
broadcastable=False, can_cast=False)`

Checks the shape and type of a tensor.

Parameters

- **shape** (*Optional[Tuple[Optional[int], ...]]*) – Tuple with the desired shape. If the input tensor shape is not compatible, *ValueError* will be raised. If *None* is set as a dimension value, that dimension will be ignored.
- **dtype** (*Optional[dtype]*) – Checks if the *dtype* of the input tensor matches the provided one.
- **broadcastable** (*bool*) – Check if the shapes are compatible using broadcasting rules.
- **can_cast** (*bool*) – Check if the input tensor can be casted to the provided type.

- **tensor** (*Tensor*) –

Return type

None

Classes

<code>pytorch_pfn_extras.nn.modules.ensure_shape.Ensure(*)</code>	Module to check the shape of a tensor.
---	--

`pytorch_pfn_extras.nn.modules.ensure_shape.Ensure`

```
class pytorch_pfn_extras.nn.modules.ensure_shape.Ensure(*, shape=None, dtype=None,
                                                       broadcastable=False, can_cast=False)
```

Bases: `Module`

Module to check the shape of a tensor.

Parameters

- **shape** (*Optional[Tuple[Optional[int], ...]]*) – Tuple with the desired shape. If the input tensor shape is not compatible, `ValueError` will be raised. If `None` is set as a dimension value, that dimension will be ignored.
- **dtype** (*Optional[dtype]*) – Checks if the `dtype` of the input thensor matches the provided one.
- **broadcastable** (`bool`) – Check if the shapes are compatible using broadcasting rules.
- **can_cast** (`bool`) – Check if the input tensor can be casted to the provided type.

Initializes internal Module state, shared by both `nn.Module` and `ScriptModule`.

Methods

<code>__init__(*, shape, dtype, broadcastable, ...)</code>	Initializes internal Module state, shared by both <code>nn.Module</code> and <code>ScriptModule</code> .
<code>add_module(name, module)</code>	Adds a child module to the current module.
<code>apply(fn)</code>	Applies <code>fn</code> recursively to every submodule (as returned by <code>.children()</code>) as well as self.
<code>bfloat16()</code>	Casts all floating point parameters and buffers to <code>bfloat16</code> datatype.
<code>buffers([reuse])</code>	Returns an iterator over module buffers.
<code>children()</code>	Returns an iterator over immediate children modules.
<code>cpu()</code>	Moves all model parameters and buffers to the CPU.
<code>cuda([device])</code>	Moves all model parameters and buffers to the GPU.
<code>double()</code>	Casts all floating point parameters and buffers to <code>double</code> datatype.
<code>eval()</code>	Sets the module in evaluation mode.
<code>extra_repr()</code>	Set the extra representation of the module
<code>float()</code>	Casts all floating point parameters and buffers to <code>float</code> datatype.

continues on next page

Table 10 – continued from previous page

<code>forward(input)</code>	Defines the computation performed at every call.
<code>get_buffer(target)</code>	Returns the buffer given by <code>target</code> if it exists, otherwise throws an error.
<code>get_extra_state()</code>	Returns any extra state to include in the module's <code>state_dict</code> .
<code>get_parameter(target)</code>	Returns the parameter given by <code>target</code> if it exists, otherwise throws an error.
<code>get_submodule(target)</code>	Returns the submodule given by <code>target</code> if it exists, otherwise throws an error.
<code>half()</code>	Casts all floating point parameters and buffers to <code>half</code> datatype.
<code>ipu([device])</code>	Moves all model parameters and buffers to the IPU.
<code>load_state_dict(state_dict[, strict])</code>	Copies parameters and buffers from <code>state_dict</code> into this module and its descendants.
<code>modules()</code>	Returns an iterator over all modules in the network.
<code>named_buffers([prefix, recurse, ...])</code>	Returns an iterator over module buffers, yielding both the name of the buffer as well as the buffer itself.
<code>named_children()</code>	Returns an iterator over immediate children modules, yielding both the name of the module as well as the module itself.
<code>named_modules([memo, prefix, remove_duplicate])</code>	Returns an iterator over all modules in the network, yielding both the name of the module as well as the module itself.
<code>named_parameters([prefix, recurse, ...])</code>	Returns an iterator over module parameters, yielding both the name of the parameter as well as the parameter itself.
<code>parameters([recurse])</code>	Returns an iterator over module parameters.
<code>register_backward_hook(hook)</code>	Registers a backward hook on the module.
<code>register_buffer(name, tensor[, persistent])</code>	Adds a buffer to the module.
<code>register_forward_hook(hook, *[, prepend, ...])</code>	Registers a forward hook on the module.
<code>register_forward_pre_hook(hook, *[, ...])</code>	Registers a forward pre-hook on the module.
<code>register_full_backward_hook(hook[, prepend])</code>	Registers a backward hook on the module.
<code>register_full_backward_pre_hook(hook[, prepend])</code>	Registers a backward pre-hook on the module.
<code>register_load_state_dict_post_hook(hook)</code>	Registers a post hook to be run after module's <code>load_state_dict</code> is called.
<code>register_module(name, module)</code>	Alias for <code>add_module()</code> .
<code>register_parameter(name, param)</code>	Adds a parameter to the module.
<code>register_state_dict_pre_hook(hook)</code>	These hooks will be called with arguments: <code>self</code> , <code>prefix</code> , and <code>keep_vars</code> before calling <code>state_dict</code> on <code>self</code> .
<code>requires_grad_([requires_grad])</code>	Change if autograd should record operations on parameters in this module.
<code>set_extra_state(state)</code>	This function is called from <code>load_state_dict()</code> to handle any extra state found within the <code>state_dict</code> .
<code>share_memory()</code>	See <code>torch.Tensor.share_memory_()</code>
<code>state_dict(*args[, destination, prefix, ...])</code>	Returns a dictionary containing references to the whole state of the module.
<code>to(*args, **kwargs)</code>	Moves and/or casts the parameters and buffers.

continues on next page

Table 10 – continued from previous page

<code>to_empty(*, device)</code>	Moves the parameters and buffers to the specified device without copying storage.
<code>train([mode])</code>	Sets the module in training mode.
<code>type(dst_type)</code>	Casts all parameters and buffers to <code>dst_type</code> .
<code>xpu([device])</code>	Moves all model parameters and buffers to the XPU.
<code>zero_grad([set_to_none])</code>	Sets gradients of all model parameters to zero.

Attributes

<code>T_destination</code>	alias of <code>TypeVar('T_destination', bound=Dict[str, Any])</code>
<code>call_super_init</code>	
<code>dump_patches</code>	

`__init__(*, shape=None, dtype=None, broadcastable=False, can_cast=False)`

Initializes internal Module state, shared by both `nn.Module` and `ScriptModule`.

Parameters

- `shape` (*Optional[Tuple[Optional[int], ...]]*) –
- `dtype` (*Optional[dtype]*) –
- `broadcastable` (`bool`) –
- `can_cast` (`bool`) –

`forward(input)`

Defines the computation performed at every call.

Should be overridden by all subclasses.

Note: Although the recipe for forward pass needs to be defined within this function, one should call the `Module` instance afterwards instead of this since the former takes care of running the registered hooks while the latter silently ignores them.

Parameters

`input` (`Tensor`) –

Return type

`Tensor`

`training: bool`

pytorch_pfn_extras.nn.modules.extended_sequential**Classes**

<code>pytorch_pfn_extras.nn.modules. extended_sequential.ExtendedSequential()</code>	Sequential module with extended features from chainer.
<code>pytorch_pfn_extras.nn.modules. extended_sequential.TypeVar(...)</code>	Type variable.

pytorch_pfn_extras.nn.modules.extended_sequential.ExtendedSequential

```
class pytorch_pfn_extras.nn.modules.extended_sequential.ExtendedSequential(*args: Module)
class pytorch_pfn_extras.nn.modules.extended_sequential.ExtendedSequential(arg:
                                                               OrderedDict[str,
                                                               Module])
```

Bases: Sequential

Sequential module with extended features from chainer.

Initializes internal Module state, shared by both nn.Module and ScriptModule.

Methods

<code>__init__(*)args</code>	Initializes internal Module state, shared by both nn.Module and ScriptModule.
<code>add_module(name, module)</code>	Adds a child module to the current module.
<code>append(module)</code>	Appends a given module to the end.
<code>apply(fn)</code>	Applies fn recursively to every submodule (as returned by .children()) as well as self.
<code>bfloat16()</code>	Casts all floating point parameters and buffers to bfloat16 datatype.
<code>buffers([recurse])</code>	Returns an iterator over module buffers.
<code>children()</code>	Returns an iterator over immediate children modules.
<code>cpu()</code>	Moves all model parameters and buffers to the CPU.
<code>cuda([device])</code>	Moves all model parameters and buffers to the GPU.
<code>double()</code>	Casts all floating point parameters and buffers to double datatype.
<code>eval()</code>	Sets the module in evaluation mode.
<code>extend(sequential)</code>	
<code>extra_repr()</code>	Set the extra representation of the module
<code>float()</code>	Casts all floating point parameters and buffers to float datatype.
<code>forward(input)</code>	Defines the computation performed at every call.
<code>get_buffer(target)</code>	Returns the buffer given by target if it exists, otherwise throws an error.
<code>get_extra_state()</code>	Returns any extra state to include in the module's state_dict.

continues on next page

Table 11 – continued from previous page

<code>get_parameter(target)</code>	Returns the parameter given by <code>target</code> if it exists, otherwise throws an error.
<code>get_submodule(target)</code>	Returns the submodule given by <code>target</code> if it exists, otherwise throws an error.
<code>half()</code>	Casts all floating point parameters and buffers to <code>half</code> datatype.
<code>insert(index, module)</code>	
<code>ipu([device])</code>	Moves all model parameters and buffers to the IPU.
<code>load_state_dict(state_dict[, strict])</code>	Copies parameters and buffers from <code>state_dict</code> into this module and its descendants.
<code>modules()</code>	Returns an iterator over all modules in the network.
<code>named_buffers([prefix, recurse, ...])</code>	Returns an iterator over module buffers, yielding both the name of the buffer as well as the buffer itself.
<code>named_children()</code>	Returns an iterator over immediate children modules, yielding both the name of the module as well as the module itself.
<code>named_modules([memo, prefix, remove_duplicate])</code>	Returns an iterator over all modules in the network, yielding both the name of the module as well as the module itself.
<code>named_parameters([prefix, recurse, ...])</code>	Returns an iterator over module parameters, yielding both the name of the parameter as well as the parameter itself.
<code>parameters([recurse])</code>	Returns an iterator over module parameters.
<code>pop(key)</code>	
<code>register_backward_hook(hook)</code>	Registers a backward hook on the module.
<code>register_buffer(name, tensor[, persistent])</code>	Adds a buffer to the module.
<code>register_forward_hook(hook, *[, prepend, ...])</code>	Registers a forward hook on the module.
<code>register_forward_pre_hook(hook, *[, ...])</code>	Registers a forward pre-hook on the module.
<code>register_full_backward_hook(hook[, prepend])</code>	Registers a backward hook on the module.
<code>register_full_backward_pre_hook(hook[, prepend])</code>	Registers a backward pre-hook on the module.
<code>register_load_state_dict_post_hook(hook)</code>	Registers a post hook to be run after module's <code>load_state_dict</code> is called.
<code>register_module(name, module)</code>	Alias for <code>add_module()</code> .
<code>register_parameter(name, param)</code>	Adds a parameter to the module.
<code>register_state_dict_pre_hook(hook)</code>	These hooks will be called with arguments: <code>self</code> , <code>prefix</code> , and <code>keep_vars</code> before calling <code>state_dict</code> on <code>self</code> .
<code>repeat(n_repeat[, mode])</code>	Repeats this Sequential multiple times.
<code>requires_grad_([requires_grad])</code>	Change if autograd should record operations on parameters in this module.
<code>set_extra_state(state)</code>	This function is called from <code>load_state_dict()</code> to handle any extra state found within the <code>state_dict</code> .
<code>share_memory()</code>	See <code>torch.Tensor.share_memory_()</code>
<code>state_dict(*args[, destination, prefix, ...])</code>	Returns a dictionary containing references to the whole state of the module.
<code>to(*args, **kwargs)</code>	Moves and/or casts the parameters and buffers.

continues on next page

Table 11 – continued from previous page

<code>to_empty(*, device)</code>	Moves the parameters and buffers to the specified device without copying storage.
<code>train([mode])</code>	Sets the module in training mode.
<code>type(dst_type)</code>	Casts all parameters and buffers to <code>dst_type</code> .
<code>xpu([device])</code>	Moves all model parameters and buffers to the XPU.
<code>zero_grad([set_to_none])</code>	Sets gradients of all model parameters to zero.

Attributes

<code>T_destination</code>	alias of <code>TypeVar('T_destination', bound=Dict[str, Any])</code>
<code>call_super_init</code>	
<code>dump_patches</code>	

`repeat(n_repeat, mode='init')`

Repeats this Sequential multiple times.

This method returns a `Sequential` object which has original `Sequential` multiple times repeatedly. The `mode` argument means how to copy this sequential to repeat.

The functions is supposed to behave the same way as `repeat` in `chainer`.

When the mode is set to `init`, the default value, modules will be copied and reinitialized by calling `reset_parameters` (or `_reset_parameters`) method.

To repeat user-defined modules, which have parameters or buffers, with mode=``init`` in this `Sequential`, you need to implement the `reset_parameters` or `_reset_parameters` method to the module to reinitialize parameters and (if necessary) buffers; otherwise the initialization cannot be performed and a warning message will be shown.

Parameters

- `n_repeat (int)` – Number of times to repeat.
- `mode (str)` – It should be either `init`, `copy`, or `share`. `init` means parameters of each repeated element in the returned `Sequential` will be re-initialized, so that all elements have different initial parameters. `copy` means that the parameters will not be re-initialized but object itself will be deep-copied, so that all elements have same initial parameters but can be changed independently. `share` means all the elements which consist the resulting `Sequential` object are same object because they are shallow-copied, so that all parameters of elements are shared with each other.

Return type

`ExtendedSequential`

`training: bool`

[pytorch_pfn_extras.nn.modules.extended_sequential.TypeVar](#)

```
class pytorch_pfn_extras.nn.modules.extended_sequential.TypeVar(name, *constraints,
                                                               bound=None, covariant=False,
                                                               contravariant=False)
```

Bases: `_Final`, `_Immutable`

Type variable.

Usage:

```
T = TypeVar('T') # Can be anything
A = TypeVar('A', str, bytes) # Must be str or bytes
```

Type variables exist primarily for the benefit of static type checkers. They serve as the parameters for generic types as well as for generic function definitions. See class `Generic` for more information on generic types. Generic functions work as follows:

```
def repeat(x: T, n: int) -> List[T]:
    """Return a list containing n references to x."""
    return [x]*n

def longest(x: A, y: A) -> A:
    """Return the longest of two strings."""
    return x if len(x) >= len(y) else y
```

The latter example's signature is essentially the overloading of `(str, str) -> str` and `(bytes, bytes) -> bytes`. Also note that if the arguments are instances of some subclass of `str`, the return type is still plain `str`.

At runtime, `isinstance(x, T)` and `issubclass(C, T)` will raise `TypeError`.

Type variables defined with `covariant=True` or `contravariant=True` can be used to declare covariant or contravariant generic types. See PEP 484 for more details. By default generic types are invariant in all type variables.

Type variables can be introspected. e.g.:

```
T.__name__ == 'T' T.__constraints__ == () T.__covariant__ == False T.__contravariant__ = False
A.__constraints__ == (str, bytes)
```

Note that only type variables defined in global scope can be pickled.

Methods

```
__init__(name, *constraints[, bound, ...])
```

```
__init__(name, *constraints, bound=None, covariant=False, contravariant=False)
```

[pytorch_pfn_extras.nn.modules.lazy](#)

Classes

<code>pytorch_pfn_extras.nn.modules.lazy.</code>	A mixin for modules that lazily initialize buffers and pa-
<code>LazyInitializationMixin(...)</code>	rameters.
<code>pytorch_pfn_extras.nn.modules.lazy.</code>	
<code>UninitializedParameter([...])</code>	

pytorch_pfn_extras.nn.modules.lazy.LazyInitializationMixin

```
class pytorch_pfn_extras.nn.modules.lazy.LazyInitializationMixin(*args, **kwargs)
```

Bases: object

A mixin for modules that lazily initialize buffers and parameters.

Unlike regular modules, subclasses of this module can initialize buffers and parameters outside of the constructor (`__init__`). This allows you to, for example, initialize parameters in `forward` method to determine the shape of the weight based on the initial input.

Be sure to run “dummy” forward once to initialize all parameters that should be trained, before passing `module.parameters()` to an optimizer; otherwise weights initialized after `module.parameters()` (e.g., in `forward` function) will never be trained.

Note that lazy modules cannot validate if the shape is correct during deserialization. Also note that the initial weights may become different from the original (non-lazy) module even if the random seed is manually configured, as the order of initialization is different from the original one; especially, `module.cuda()` may cause the initialization to run on a GPU.

The default value of lazy buffers and parameters are `torch.Tensor([])` and `UninitializedParameter()`, respectively.

Methods

```
__init__(*args, **kwargs)
```

```
state_dict(*args, **kwargs)
```

Returns a dictionary containing a whole state of the module.

Attributes

```
lazy_buffer_names
```

```
lazy_parameter_names
```

```
lazy_parameters_determined
```

Returns if all lazy parameters are determined.

Parameters

- **args** (Any) –
- **kwargs** (Any) –

```
__init__(*args, **kwargs)
```

Parameters

- **self** (Any) –
- **args** (Any) –
- **kwargs** (Any) –

Return type

None

```
lazy_buffer_names: Tuple[str, ...] = ()  
lazy_parameter_names: Tuple[str, ...] = ()  
property lazy_parameters_determined: bool  
    Returns if all lazy parameters are determined.
```

Subclasses can perform parameters initialization after all lazy parameters are determined. Note that this may be called during `__init__`.

`state_dict(*args, **kwargs)`

Returns a dictionary containing a whole state of the module.

This function overrides the default behavior to exclude uninitialized parameter from serialization. This is needed because we need to discriminate lazy parameters (`UninitializedParameter()`) and initialized empty parameters (`torch.nn.Parameter(torch.Tensor())`) during deserialization.

See comments of `_lazy_load_hook` for details.

Parameters

- `self (Any)` –
- `args (Any)` –
- `kwargs (Any)` –

Return type

`Dict[str, Any]`

pytorch_pfn_extras.nn.modules.lazy.UninitializedParameter

```
class pytorch_pfn_extras.nn.modules.lazy.UninitializedParameter(data=None,  
                                                               requires_grad=True)
```

Bases: `Parameter`

Methods

`__init__()`

<code>abs()</code>	See <code>torch.abs()</code>
<code>abs_()</code>	In-place version of <code>abs()</code>
<code>absolute()</code>	Alias for <code>abs()</code>
<code>absolute_()</code>	In-place version of <code>absolute()</code> Alias for <code>abs_()</code>
<code>acos()</code>	See <code>torch.acos()</code>
<code>acos_()</code>	In-place version of <code>acos()</code>
<code>acosh()</code>	See <code>torch.acosh()</code>
<code>acosh_()</code>	In-place version of <code>acosh()</code>
<code>add(other, *, alpha)</code>	Add a scalar or tensor to <code>self</code> tensor.
<code>add_(other, *, alpha)</code>	In-place version of <code>add()</code>
<code>addbmm(batch1, batch2, *, [beta, alpha])</code>	See <code>torch.addbmm()</code>
<code>addbmm_(batch1, batch2, *, [beta, alpha])</code>	In-place version of <code>addbmm()</code>
<code>addcdiv(tensor1, tensor2, *, [value])</code>	See <code>torch.addcdiv()</code>

continues on next page

Table 12 – continued from previous page

addcddiv_(tensor1, tensor2, *[, value])	In-place version of <code>addcddiv()</code>
addcmul_(tensor1, tensor2, *[, value])	See <code>torch.addcmul()</code>
addcmul_(tensor1, tensor2, *[, value])	In-place version of <code>addcmul()</code>
addmm_(mat1, mat2, *[, beta, alpha])	See <code>torch.addmm()</code>
addmm_(mat1, mat2, *[, beta, alpha])	In-place version of <code>addmm()</code>
addmv_(mat, vec, *[, beta, alpha])	See <code>torch.addmv()</code>
addmv_(mat, vec, *[, beta, alpha])	In-place version of <code>addmv()</code>
addr_(vec1, vec2, *[, beta, alpha])	See <code>torch.addr()</code>
addr_(vec1, vec2, *[, beta, alpha])	In-place version of <code>addr()</code>
adjoint()	Alias for <code>adjoint()</code>
align_as(other)	Permutes the dimensions of the <code>self</code> tensor to match the dimension order in the <code>other</code> tensor, adding size-one dims for any new names.
align_to(*names)	Permutes the dimensions of the <code>self</code> tensor to match the order specified in <code>names</code> , adding size-one dims for any new names.
all([dim, keepdim])	See <code>torch.all()</code>
allclose(other[, rtol, atol, equal_nan])	See <code>torch.allclose()</code>
amax([dim, keepdim])	See <code>torch.amax()</code>
amin([dim, keepdim])	See <code>torch.amin()</code>
aminmax(*[, dim, keepdim])	See <code>torch.aminmax()</code>
angle()	See <code>torch.angle()</code>
any([dim, keepdim])	See <code>torch.any()</code>
apply_(callable)	Applies the function <code>callable</code> to each element in the tensor, replacing each element with the value returned by <code>callable</code> .
arccos()	See <code>torch.arccos()</code>
arccos_()	In-place version of <code>arccos()</code>
arccosh	<code>acosh()</code> -> Tensor
arccosh_	<code>acosh_()</code> -> Tensor
arcsin()	See <code>torch.arcsin()</code>
arcsin_()	In-place version of <code>arcsin()</code>
arcsinh()	See <code>torch.arcsinh()</code>
arcsinh_()	In-place version of <code>arcsinh()</code>
arctan()	See <code>torch.arctan()</code>
arctan2(other)	See <code>torch.arctan2()</code>
arctan2_	<code>atan2_(other)</code> -> Tensor
arctan_()	In-place version of <code>arctan()</code>
arctanh()	See <code>torch.arctanh()</code>
arctanh_(other)	In-place version of <code>arctanh()</code>
argmax([dim, keepdim])	See <code>torch.argmax()</code>
argmin([dim, keepdim])	See <code>torch.argmin()</code>
argsort([dim, descending])	See <code>torch.argsort()</code>
argwhere()	See <code>torch.argwhere()</code>
as_strided(size, stride[, storage_offset])	See <code>torch.as_strided()</code>
as_strided_	
as_strided_scatter(src, size, stride[, ...])	See <code>torch.as_strided_scatter()</code>
as_subclass(cls)	Makes a <code>cls</code> instance with the same data pointer as <code>self</code> .
asin()	See <code>torch.asin()</code>

continues on next page

Table 12 – continued from previous page

<code>asin_()</code>	In-place version of <code>asin()</code>
<code>asinh()</code>	See <code>torch.asinh()</code>
<code>asinh_()</code>	In-place version of <code>asinh()</code>
<code>atan()</code>	See <code>torch.atan()</code>
<code>atan2(other)</code>	See <code>torch.atan2()</code>
<code>atan2_(other)</code>	In-place version of <code>atan2()</code>
<code>atan_()</code>	In-place version of <code>atan()</code>
<code>atanh()</code>	See <code>torch.atanh()</code>
<code>atanh_(other)</code>	In-place version of <code>atanh()</code>
<code>backward([gradient, retain_graph, ...])</code>	Computes the gradient of current tensor w.r.t.
<code>baddbmm(batch1, batch2, *[beta, alpha])</code>	See <code>torch.baddbmm()</code>
<code>baddbmm_(batch1, batch2, *[beta, alpha])</code>	In-place version of <code>baddbmm()</code>
<code>bernoulli(*[generator])</code>	Returns a result tensor where each <code>result[i]</code> is independently sampled from <code>Bernoulli(self[i])</code> .
<code>bernoulli_([p, generator])</code>	Fills each location of <code>self</code> with an independent sample from <code>Bernoulli(p)</code> .
<code>bfloat16([memory_format])</code>	<code>self.bfloat16()</code> is equivalent to <code>self.to(torch.bfloat16)</code> .
<code>bincount([weights, minlength])</code>	See <code>torch.bincount()</code>
<code>bitwise_and()</code>	See <code>torch.bitwise_and()</code>
<code>bitwise_and_()</code>	In-place version of <code>bitwise_and()</code>
<code>bitwise_left_shift(other)</code>	See <code>torch.bitwise_left_shift()</code>
<code>bitwise_left_shift_(other)</code>	In-place version of <code>bitwise_left_shift()</code>
<code>bitwise_not()</code>	See <code>torch.bitwise_not()</code>
<code>bitwise_not_()</code>	In-place version of <code>bitwise_not()</code>
<code>bitwise_or()</code>	See <code>torch.bitwise_or()</code>
<code>bitwise_or_()</code>	In-place version of <code>bitwise_or()</code>
<code>bitwise_right_shift(other)</code>	See <code>torch.bitwise_right_shift()</code>
<code>bitwise_right_shift_(other)</code>	In-place version of <code>bitwise_right_shift()</code>
<code>bitwise_xor()</code>	See <code>torch.bitwise_xor()</code>
<code>bitwise_xor_()</code>	In-place version of <code>bitwise_xor()</code>
<code>bmm(batch2)</code>	See <code>torch.bmm()</code>
<code>bool([memory_format])</code>	<code>self.bool()</code> is equivalent to <code>self.to(torch.bool)</code> .
<code>broadcast_to(shape)</code>	See <code>torch.broadcast_to()</code> .
<code>byte([memory_format])</code>	<code>self.byte()</code> is equivalent to <code>self.to(torch.uint8)</code> .
<code>cauchy_([median, sigma, generator])</code>	Fills the tensor with numbers drawn from the Cauchy distribution:
<code>ccol_indices</code>	
<code>cdouble([memory_format])</code>	<code>self.cdouble()</code> is equivalent to <code>self.to(torch.complex128)</code> .
<code>ceil()</code>	See <code>torch.ceil()</code>
<code>ceil_()</code>	In-place version of <code>ceil()</code>
<code>cfloat([memory_format])</code>	<code>self.cfloat()</code> is equivalent to <code>self.to(torch.complex64)</code> .
<code>chalf([memory_format])</code>	<code>self.chalf()</code> is equivalent to <code>self.to(torch.complex32)</code> .
<code>char([memory_format])</code>	<code>self.char()</code> is equivalent to <code>self.to(torch.int8)</code> .

continues on next page

Table 12 – continued from previous page

cholesky([upper])	See <code>torch.cholesky()</code>
cholesky_inverse([upper])	See <code>torch.cholesky_inverse()</code>
cholesky_solve(input2[, upper])	See <code>torch.cholesky_solve()</code>
chunk(chunks[, dim])	See <code>torch.chunk()</code>
clamp([min, max])	See <code>torch.clamp()</code>
clamp_([min, max])	In-place version of <code>clamp()</code>
clamp_max	
clamp_max_	
clamp_min	
clamp_min_	
clip([min, max])	Alias for <code>clamp()</code> .
clip_([min, max])	Alias for <code>clamp_()</code> .
clone(*[, memory_format])	See <code>torch.clone()</code>
coalesce()	Returns a coalesced copy of <code>self</code> if <code>self</code> is an uncoalesced tensor.
col_indices()	Returns the tensor containing the column indices of the <code>self</code> tensor when <code>self</code> is a sparse CSR tensor of layout <code>sparse_csr</code> .
conj()	See <code>torch.conj()</code>
conj_physical()	See <code>torch.conj_physical()</code>
conj_physical_()	In-place version of <code>conj_physical()</code>
contiguous([memory_format])	Returns a contiguous in memory tensor containing the same data as <code>self</code> tensor.
copy_(src[, non_blocking])	Copies the elements from <code>src</code> into <code>self</code> tensor and returns <code>self</code> .
copysign(other)	See <code>torch.copysign()</code>
copysign_(other)	In-place version of <code>copysign()</code>
corrcoef()	See <code>torch.corrcoef()</code>
cos()	See <code>torch.cos()</code>
cos_()	In-place version of <code>cos()</code>
cosh()	See <code>torch.cosh()</code>
cosh_()	In-place version of <code>cosh()</code>
count_nonzero([dim])	See <code>torch.count_nonzero()</code>
cov(*[, correction, fweights, aweights])	See <code>torch.cov()</code>
cpu([memory_format])	Returns a copy of this object in CPU memory.
cross(other[, dim])	See <code>torch.cross()</code>
crow_indices()	Returns the tensor containing the compressed row indices of the <code>self</code> tensor when <code>self</code> is a sparse CSR tensor of layout <code>sparse_csr</code> .
cuda([device, non_blocking, memory_format])	Returns a copy of this object in CUDA memory.
cummax(dim)	See <code>torch.cummax()</code>
cummin(dim)	See <code>torch.cummin()</code>
cumprod(dim[, dtype])	See <code>torch.cumprod()</code>
cumprod_(dim[, dtype])	In-place version of <code>cumprod()</code>
cumsum(dim[, dtype])	See <code>torch.cumsum()</code>
cumsum_(dim[, dtype])	In-place version of <code>cumsum()</code>

continues on next page

Table 12 – continued from previous page

<code>data_ptr()</code>	Returns the address of the first element of <code>self</code> tensor.
<code>deg2rad()</code>	See <code>torch.deg2rad()</code>
<code>deg2rad_()</code>	In-place version of <code>deg2rad()</code>
<code>dense_dim()</code>	Return the number of dense dimensions in a sparse tensor <code>self</code> .
<code>dequantize()</code>	Given a quantized Tensor, dequantize it and return the dequantized float Tensor.
<code>det()</code>	See <code>torch.det()</code>
<code>detach</code>	Returns a new Tensor, detached from the current graph.
<code>detach_</code>	Detaches the Tensor from the graph that created it, making it a leaf.
<code>diag([diagonal])</code>	See <code>torch.diag()</code>
<code>diag_embed([offset, dim1, dim2])</code>	See <code>torch.diag_embed()</code>
<code>diagflat([offset])</code>	See <code>torch.diagflat()</code>
<code>diagonal([offset, dim1, dim2])</code>	See <code>torch.diagonal()</code>
<code>diagonal_scatter(src[, offset, dim1, dim2])</code>	See <code>torch.diagonal_scatter()</code>
<code>diff([n, dim, prepend, append])</code>	See <code>torch.diff()</code>
<code>digamma()</code>	See <code>torch.digamma()</code>
<code>digamma_()</code>	In-place version of <code>digamma()</code>
<code>dim()</code>	Returns the number of dimensions of <code>self</code> tensor.
<code>dist(other[, p])</code>	See <code>torch.dist()</code>
<code>div(value, *[, rounding_mode])</code>	See <code>torch.div()</code>
<code>div_(value, *[, rounding_mode])</code>	In-place version of <code>div()</code>
<code>divide(value, *[, rounding_mode])</code>	See <code>torch.divide()</code>
<code>divide_(value, *[, rounding_mode])</code>	In-place version of <code>divide()</code>
<code>dot(other)</code>	See <code>torch.dot()</code>
<code>double([memory_format])</code>	<code>self.double()</code> is equivalent to <code>self.to(torch.float64)</code> .
<code>dsplit(split_size_or_sections)</code>	See <code>torch.dsplit()</code>
<code>eig([eigenvectors])</code>	
<code>element_size()</code>	Returns the size in bytes of an individual element.
<code>eq(other)</code>	See <code>torch.eq()</code>
<code>eq_(other)</code>	In-place version of <code>eq()</code>
<code>equal(other)</code>	See <code>torch.equal()</code>
<code>erf()</code>	See <code>torch.erf()</code>
<code>erf_()</code>	In-place version of <code>erf()</code>
<code>erfc()</code>	See <code>torch.erfc()</code>
<code>erfc_()</code>	In-place version of <code>erfc()</code>
<code>erfinv()</code>	See <code>torch.erfinv()</code>
<code>erfinv_()</code>	In-place version of <code>erfinv()</code>
<code>exp()</code>	See <code>torch.exp()</code>
<code>exp2()</code>	See <code>torch.exp2()</code>
<code>exp2_()</code>	In-place version of <code>exp2()</code>
<code>exp_()</code>	In-place version of <code>exp()</code>
<code>expand(*sizes)</code>	Returns a new view of the <code>self</code> tensor with singleton dimensions expanded to a larger size.
<code>expand_as(other)</code>	Expand this tensor to the same size as <code>other</code> .
<code>expm1()</code>	See <code>torch.expm1()</code>

continues on next page

Table 12 – continued from previous page

<code>expm1_()</code>	In-place version of <code>expm1()</code>
<code>exponential_([lambd, generator])</code>	Fills <code>self</code> tensor with elements drawn from the exponential distribution:
<code>fill_(value)</code>	Fills <code>self</code> tensor with the specified value.
<code>fill_diagonal_(fill_value[, wrap])</code>	Fill the main diagonal of a tensor that has at least 2-dimensions.
<code>fix()</code>	See <code>torch.fix()</code> .
<code>fix_()</code>	In-place version of <code>fix()</code>
<code>flatten([start_dim, end_dim])</code>	See <code>torch.flatten()</code>
<code>flip(dims)</code>	See <code>torch.flip()</code>
<code>fliplr()</code>	See <code>torch.fliplr()</code>
<code>flipud()</code>	See <code>torch.flipud()</code>
<code>float([memory_format])</code>	<code>self.float()</code> is equivalent to <code>self.to(torch.float32)</code> .
<code>float_power(exponent)</code>	See <code>torch.float_power()</code>
<code>float_power_(exponent)</code>	In-place version of <code>float_power()</code>
<code>floor()</code>	See <code>torch.floor()</code>
<code>floor_()</code>	In-place version of <code>floor()</code>
<code>floor_divide(value)</code>	See <code>torch.floor_divide()</code>
<code>floor_divide_(value)</code>	In-place version of <code>floor_divide()</code>
<code>fmax(other)</code>	See <code>torch.fmax()</code>
<code>fmin(other)</code>	See <code>torch.fmin()</code>
<code>fmod(divisor)</code>	See <code>torch.fmod()</code>
<code>fmod_(divisor)</code>	In-place version of <code>fmod()</code>
<code>frac()</code>	See <code>torch.frac()</code>
<code>frac_()</code>	In-place version of <code>frac()</code>
<code>frexp(input)</code>	See <code>torch.frexp()</code>
<code>gather(dim, index)</code>	See <code>torch.gather()</code>
<code>gcd(other)</code>	See <code>torch.gcd()</code>
<code>gcd_(other)</code>	In-place version of <code>gcd()</code>
<code>ge(other)</code>	See <code>torch.ge()</code> .
<code>ge_(other)</code>	In-place version of <code>ge()</code> .
<code>geometric_(p, *[, generator])</code>	Fills <code>self</code> tensor with elements drawn from the geometric distribution:
<code>geqrft()</code>	See <code>torch.geqrft()</code>
<code>ger(vec2)</code>	See <code>torch.ger()</code>
<code>get_device()</code>	For CUDA tensors, this function returns the device ordinal of the GPU on which the tensor resides.
<code>greater(other)</code>	See <code>torch.greater()</code> .
<code>greater_(other)</code>	In-place version of <code>greater()</code> .
<code>greater_equal(other)</code>	See <code>torch.greater_equal()</code> .
<code>greater_equal_(other)</code>	In-place version of <code>greater_equal()</code> .
<code>gt(other)</code>	See <code>torch.gt()</code> .
<code>gt_(other)</code>	In-place version of <code>gt()</code> .
<code>half([memory_format])</code>	<code>self.half()</code> is equivalent to <code>self.to(torch.float16)</code> .
<code>hardshrink([lambd])</code>	See <code>torch.nn.functional.hardshrink()</code>
<code>has_names</code>	Is True if any of this tensor's dimensions are named.
<code>heaviside(values)</code>	See <code>torch.heaviside()</code>
<code>heaviside_(values)</code>	In-place version of <code>heaviside()</code>

continues on next page

Table 12 – continued from previous page

<code>histc([bins, min, max])</code>	See <code>torch.histc()</code>
<code>histogram(input, bins, *[range, weight, ...])</code>	See <code>torch.histogram()</code>
<code>hsplit(split_size_or_sections)</code>	See <code>torch.hsplit()</code>
<code>hypot(other)</code>	See <code>torch.hypot()</code>
<code>hypot_(other)</code>	In-place version of <code>hypot()</code>
<code>i0()</code>	See <code>torch.i0()</code>
<code>i0_()</code>	In-place version of <code>i0()</code>
<code>igamma(other)</code>	See <code>torch.igamma()</code>
<code>igamma_(other)</code>	In-place version of <code>igamma()</code>
<code>igammac(other)</code>	See <code>torch.igammac()</code>
<code>igammac_(other)</code>	In-place version of <code>igammac()</code>
<code>index_add(dim, index, source, *[alpha])</code>	Out-of-place version of <code>torch.Tensor.index_add_()</code> .
<code>index_add_(dim, index, source, *[alpha])</code>	Accumulate the elements of <code>alpha</code> times <code>source</code> into the <code>self</code> tensor by adding to the indices in the order given in <code>index</code> .
<code>index_copy(dim, index, tensor2)</code>	Out-of-place version of <code>torch.Tensor.index_copy_()</code> .
<code>index_copy_(dim, index, tensor)</code>	Copies the elements of <code>tensor</code> into the <code>self</code> tensor by selecting the indices in the order given in <code>index</code> .
<code>index_fill(dim, index, value)</code>	Out-of-place version of <code>torch.Tensor.index_fill_()</code> .
<code>index_fill_(dim, index, value)</code>	Fills the elements of the <code>self</code> tensor with value <code>value</code> by selecting the indices in the order given in <code>index</code> .
<code>index_put(indices, values[, accumulate])</code>	Out-place version of <code>index_put_()</code> .
<code>index_put_(indices, values[, accumulate])</code>	Puts values from the tensor <code>values</code> into the tensor <code>self</code> using the indices specified in <code>indices</code> (which is a tuple of Tensors).
<code>index_reduce</code>	
<code>index_reduce_(dim, index, source, reduce, *)</code>	Accumulate the elements of <code>source</code> into the <code>self</code> tensor by accumulating to the indices in the order given in <code>index</code> using the reduction given by the <code>reduce</code> argument.
<code>index_select(dim, index)</code>	See <code>torch.index_select()</code>
<code>indices()</code>	Return the indices tensor of a sparse COO tensor.
<code>inner(other)</code>	See <code>torch.inner()</code> .
<code>int([memory_format])</code>	<code>self.int()</code> is equivalent to <code>self.to(torch.int32)</code> .
<code>int_repr()</code>	Given a quantized Tensor, <code>self.int_repr()</code> returns a CPU Tensor with <code>uint8_t</code> as data type that stores the underlying <code>uint8_t</code> values of the given Tensor.
<code>inverse()</code>	See <code>torch.inverse()</code>
<code>ipu([device, non_blocking, memory_format])</code>	Returns a copy of this object in IPU memory.
<code>is_coalesced()</code>	Returns True if <code>self</code> is a sparse COO tensor that is coalesced, False otherwise.
<code>is_complex()</code>	Returns True if the data type of <code>self</code> is a complex data type.
<code>is_conj()</code>	Returns True if the conjugate bit of <code>self</code> is set to true.

continues on next page

Table 12 – continued from previous page

<code>is_contiguous([memory_format])</code>	Returns True if <code>self</code> tensor is contiguous in memory in the order specified by memory format.
<code>is_distributed</code>	
<code>is_floating_point()</code>	Returns True if the data type of <code>self</code> is a floating point data type.
<code>is_inference()</code>	See <code>torch.is_inference()</code>
<code>is_neg()</code>	Returns True if the negative bit of <code>self</code> is set to true.
<code>is_nonzero</code>	
<code>is_pinned</code>	Returns true if this tensor resides in pinned memory.
<code>is_same_size</code>	
<code>is_set_to(tensor)</code>	Returns True if both tensors are pointing to the exact same memory (same storage, offset, size and stride).
<code>is_shared()</code>	Checks if tensor is in shared memory.
<code>is_signed()</code>	Returns True if the data type of <code>self</code> is a signed data type.
<code>isclose(other[, rtol, atol, equal_nan])</code>	See <code>torch.isclose()</code>
<code>isfinite()</code>	See <code>torch.isfinite()</code>
<code>isinf()</code>	See <code>torch.isinf()</code>
<code>isnan()</code>	See <code>torch.isnan()</code>
<code>isneginf()</code>	See <code>torch.isneginf()</code>
<code>isposinf()</code>	See <code>torch.isposinf()</code>
<code>isreal()</code>	See <code>torch.isreal()</code>
<code>istft(n_fft[, hop_length, win_length, ...])</code>	See <code>torch.istft()</code>
<code>item()</code>	Returns the value of this tensor as a standard Python number.
<code>kron(other)</code>	See <code>torch.kron()</code>
<code>kthvalue(k[, dim, keepdim])</code>	See <code>torch.kthvalue()</code>
<code>lcm(other)</code>	See <code>torch.lcm()</code>
<code>lcm_(other)</code>	In-place version of <code>lcm()</code>
<code>ldexp(other)</code>	See <code>torch.ldexp()</code>
<code>ldexp_(other)</code>	In-place version of <code>ldexp()</code>
<code>le(other)</code>	See <code>torch.le()</code> .
<code>le_(other)</code>	In-place version of <code>le()</code> .
<code>lerp(end, weight)</code>	See <code>torch.lerp()</code>
<code>lerp_(end, weight)</code>	In-place version of <code>lerp()</code>
<code>less</code>	<code>lt(other) -> Tensor</code>
<code>less_(other)</code>	In-place version of <code>less()</code> .
<code>less_equal(other)</code>	See <code>torch.less_equal()</code> .
<code>less_equal_(other)</code>	In-place version of <code>less_equal()</code> .
<code>lgamma()</code>	See <code>torch.lgamma()</code>
<code>lgamma_()</code>	In-place version of <code>lgamma()</code>
<code>log()</code>	See <code>torch.log()</code>
<code>log10()</code>	See <code>torch.log10()</code>
<code>log10_(other)</code>	In-place version of <code>log10()</code>
<code>log1p()</code>	See <code>torch.log1p()</code>
<code>log1p_(other)</code>	In-place version of <code>log1p()</code>
<code>log2()</code>	See <code>torch.log2()</code>
<code>log2_(other)</code>	In-place version of <code>log2()</code>

continues on next page

Table 12 – continued from previous page

<code>log_()</code>	In-place version of <code>log()</code>
<code>log_normal_([mean, std, generator])</code>	Fills <code>self</code> tensor with numbers samples from the log-normal distribution parameterized by the given mean μ and standard deviation σ .
<code>log_softmax</code>	
<code>logaddexp(other)</code>	See <code>torch.logaddexp()</code>
<code>logaddexp2(other)</code>	See <code>torch.logaddexp2()</code>
<code>logcumsumexp(dim)</code>	See <code>torch.logcumsumexp()</code>
<code>logdet()</code>	See <code>torch.logdet()</code>
<code>logical_and()</code>	See <code>torch.logical_and()</code>
<code>logical_and_()</code>	In-place version of <code>logical_and()</code>
<code>logical_not()</code>	See <code>torch.logical_not()</code>
<code>logical_not_()</code>	In-place version of <code>logical_not()</code>
<code>logical_or()</code>	See <code>torch.logical_or()</code>
<code>logical_or_()</code>	In-place version of <code>logical_or()</code>
<code>logical_xor()</code>	See <code>torch.logical_xor()</code>
<code>logical_xor_()</code>	In-place version of <code>logical_xor()</code>
<code>logit()</code>	See <code>torch.logit()</code>
<code>logit_()</code>	In-place version of <code>logit()</code>
<code>logsumexp(dim[, keepdim])</code>	See <code>torch.logsumexp()</code>
<code>long([memory_format])</code>	<code>self.long()</code> is equivalent to <code>self.to(torch.int64)</code> .
<code>lstsq(other)</code>	
<code>lt(other)</code>	See <code>torch.lt()</code> .
<code>lt_(other)</code>	In-place version of <code>lt()</code> .
<code>lu([pivot, get_infos])</code>	See <code>torch.lu()</code>
<code>lu_solve(LU_data, LU_pivots)</code>	See <code>torch.lu_solve()</code>
<code>map2_</code>	
<code>map_(tensor, callable)</code>	Applies <code>callable</code> for each element in <code>self</code> tensor and the given <code>tensor</code> and stores the results in <code>self</code> tensor.
<code>masked_fill(mask, value)</code>	Out-of-place version of <code>torch.Tensor.masked_fill_()</code>
<code>masked_fill_(mask, value)</code>	Fills elements of <code>self</code> tensor with <code>value</code> where <code>mask</code> is True.
<code>masked_scatter(mask, tensor)</code>	Out-of-place version of <code>torch.Tensor.masked_scatter_()</code>
<code>masked_scatter_(mask, source)</code>	Copies elements from <code>source</code> into <code>self</code> tensor at positions where the <code>mask</code> is True.
<code>masked_select(mask)</code>	See <code>torch.masked_select()</code>
<code>materialize(shape[, device, dtype])</code>	Create a Parameter with the same properties of the uninitialized one.
<code>matmul(tensor2)</code>	See <code>torch.matmul()</code>
<code>matrix_exp()</code>	See <code>torch.matrix_exp()</code>

continues on next page

Table 12 – continued from previous page

`matrix_power(n)`

Note: `matrix_power()` is deprecated, use `torch.linalg.matrix_power()` instead.

<code>max([dim, keepdim])</code>	See <code>torch.max()</code>
<code>maximum(other)</code>	See <code>torch.maximum()</code>
<code>mean([dim, keepdim, dtype])</code>	See <code>torch.mean()</code>
<code>median([dim, keepdim])</code>	See <code>torch.median()</code>
<code>min([dim, keepdim])</code>	See <code>torch.min()</code>
<code>minimum(other)</code>	See <code>torch.minimum()</code>
<code>mm(mat2)</code>	See <code>torch.mm()</code>
<code>mode([dim, keepdim])</code>	See <code>torch.mode()</code>
<code>moveaxis(source, destination)</code>	See <code>torch.moveaxis()</code>
<code>movedim(source, destination)</code>	See <code>torch.movedim()</code>
<code>msort()</code>	See <code>torch.msort()</code>
<code>mul(value)</code>	See <code>torch.mul()</code> .
<code>mul_(value)</code>	In-place version of <code>mul()</code> .
<code>multinomial(num_samples[, replacement, ...])</code>	See <code>torch.multinomial()</code>
<code>multiply(value)</code>	See <code>torch.multiply()</code> .
<code>multiply_(value)</code>	In-place version of <code>multiply()</code> .
<code>mv(vec)</code>	See <code>torch.mv()</code>
<code>mvlgamma(p)</code>	See <code>torch.mvlgamma()</code>
<code>mvlgamma_(p)</code>	In-place version of <code>mvlgamma()</code>
<code>nan_to_num([nan, posinf, neginf])</code>	See <code>torch.nan_to_num()</code> .
<code>nan_to_num_([nan, posinf, neginf])</code>	In-place version of <code>nan_to_num()</code> .
<code>nanmean([dim, keepdim, dtype])</code>	See <code>torch.nanmean()</code>
<code>nanmedian([dim, keepdim])</code>	See <code>torch.nanmedian()</code>
<code>nanquantile(q[, dim, keepdim, interpolation])</code>	See <code>torch.nanquantile()</code>
<code>nansum([dim, keepdim, dtype])</code>	See <code>torch.nansum()</code>
<code>narrow(dimension, start, length)</code>	See <code>torch.narrow()</code> .
<code>narrow_copy(dimension, start, length)</code>	See <code>torch.narrow_copy()</code> .
<code>ndimension()</code>	Alias for <code>dim()</code>
<code>ne(other)</code>	See <code>torch.ne()</code> .
<code>ne_(other)</code>	In-place version of <code>ne()</code> .
<code>neg()</code>	See <code>torch.neg()</code>
<code>neg_()</code>	In-place version of <code>neg()</code>
<code>negative()</code>	See <code>torch.negative()</code>
<code>negative_()</code>	In-place version of <code>negative()</code>
<code>nelement()</code>	Alias for <code>numel()</code>
<code>new</code>	
<code>new_empty(size, *[, dtype, device, ...])</code>	Returns a Tensor of size <code>size</code> filled with uninitialized data.
<code>new_empty_strided(size, stride[, dtype, ...])</code>	Returns a Tensor of size <code>size</code> and strides <code>stride</code> filled with uninitialized data.
<code>new_full(size, fill_value, *[, dtype, ...])</code>	Returns a Tensor of size <code>size</code> filled with <code>fill_value</code> .
<code>new_ones(size, *[, dtype, device, ...])</code>	Returns a Tensor of size <code>size</code> filled with 1.
<code>new_tensor(data, *[, dtype, device, ...])</code>	Returns a new Tensor with <code>data</code> as the tensor data.

continues on next page

Table 12 – continued from previous page

<code>new_zeros(size, *[..., dtype, device, ...])</code>	Returns a Tensor of size <code>size</code> filled with <code>0</code> .
<code>nextafter(other)</code>	See <code>torch.nextafter()</code>
<code>nextafter_(other)</code>	In-place version of <code>nextafter()</code>
<code>nonzero()</code>	See <code>torch.nonzero()</code>
<code>norm([p, dim, keepdim, dtype])</code>	See <code>torch.norm()</code>
<code>normal_([mean, std, generator])</code>	Fills <code>self</code> tensor with elements samples from the normal distribution parameterized by <code>mean</code> and <code>std</code> .
<code>not_equal(other)</code>	See <code>torch.not_equal()</code> .
<code>not_equal_(other)</code>	In-place version of <code>not_equal()</code> .
<code>numel()</code>	See <code>torch.numel()</code>
<code>numpy(*[..., force])</code>	Returns the tensor as a NumPy ndarray.
<code>orgqr(input2)</code>	See <code>torch.orgqr()</code>
<code>ormqr(input2, input3[, left, transpose])</code>	See <code>torch.ormqr()</code>
<code>outer(vec2)</code>	See <code>torch.outer()</code> .
<code>permute(*dims)</code>	See <code>torch.permute()</code>
<code>pin_memory()</code>	Copies the tensor to pinned memory, if it's not already pinned.
<code>pinverse()</code>	See <code>torch.pinverse()</code>
<code>polygamma(n)</code>	See <code>torch.polygamma()</code>
<code>polygamma_(n)</code>	In-place version of <code>polygamma()</code>
<code>positive()</code>	See <code>torch.positive()</code>
<code>pow(exponent)</code>	See <code>torch.pow()</code>
<code>pow_(exponent)</code>	In-place version of <code>pow()</code>
<code>prelu</code>	
<code>prod([dim, keepdim, dtype])</code>	See <code>torch.prod()</code>
<code>put(input, index, source[, accumulate])</code>	Out-of-place version of <code>torch.Tensor.put_()</code> .
<code>put_(index, source[, accumulate])</code>	Copies the elements from <code>source</code> into the positions specified by <code>index</code> .
<code>q_per_channel_axis()</code>	Given a Tensor quantized by linear (affine) per-channel quantization, returns the index of dimension on which per-channel quantization is applied.
<code>q_per_channel_scales()</code>	Given a Tensor quantized by linear (affine) per-channel quantization, returns a Tensor of scales of the underlying quantizer.
<code>q_per_channel_zero_points()</code>	Given a Tensor quantized by linear (affine) per-channel quantization, returns a tensor of zero_points of the underlying quantizer.
<code>q_scale()</code>	Given a Tensor quantized by linear(affine) quantization, returns the scale of the underlying quantizer().
<code>q_zero_point()</code>	Given a Tensor quantized by linear(affine) quantization, returns the zero_point of the underlying quantizer().
<code>qr([some])</code>	See <code>torch.qr()</code>
<code>qscheme()</code>	Returns the quantization scheme of a given QTensor.
<code>quantile(q[, dim, keepdim, interpolation])</code>	See <code>torch.quantile()</code>
<code>rad2deg()</code>	See <code>torch.rad2deg()</code>
<code>rad2deg_(*)</code>	In-place version of <code>rad2deg()</code>
<code>random_([from, to, generator])</code>	Fills <code>self</code> tensor with numbers sampled from the discrete uniform distribution over <code>[from, to - 1]</code> .
<code>ravel()</code>	see <code>torch.ravel()</code>

continues on next page

Table 12 – continued from previous page

<code>reciprocal()</code>	See <code>torch.reciprocal()</code>
<code>reciprocal_()</code>	In-place version of <code>reciprocal()</code>
<code>record_stream(stream)</code>	Ensures that the tensor memory is not reused for another tensor until all current work queued on <code>stream</code> are complete.
<code>refine_names(*names)</code>	Refines the dimension names of <code>self</code> according to <code>names</code> .
<code>register_hook(hook)</code>	Registers a backward hook.
<code>reinforce(reward)</code>	
<code>relu</code>	
<code>relu_</code>	
<code>remainder(divisor)</code>	See <code>torch.remainder()</code>
<code>remainder_(divisor)</code>	In-place version of <code>remainder()</code>
<code>rename(*names, **rename_map)</code>	Renames dimension names of <code>self</code> .
<code>rename_(*names, **rename_map)</code>	In-place version of <code>rename()</code> .
<code>renorm(p, dim, maxnorm)</code>	See <code>torch.renorm()</code>
<code>renorm_(p, dim, maxnorm)</code>	In-place version of <code>renorm()</code>
<code>repeat(*sizes)</code>	Repeats this tensor along the specified dimensions.
<code>repeat_interleave(repeats[, dim, output_size])</code>	See <code>torch.repeat_interleave()</code> .
<code>requires_grad_([requires_grad])</code>	Change if autograd should record operations on this tensor: sets this tensor's <code>requires_grad</code> attribute in-place.
<code>reshape(*shape)</code>	Returns a tensor with the same data and number of elements as <code>self</code> but with the specified shape.
<code>reshape_as(other)</code>	Returns this tensor as the same shape as <code>other</code> .
<code>resize(*sizes)</code>	
<code>resize_(*sizes[, memory_format])</code>	Resizes <code>self</code> tensor to the specified size.
<code>resize_as(tensor)</code>	
<code>resize_as_(tensor[, memory_format])</code>	Resizes the <code>self</code> tensor to be the same size as the specified <code>tensor</code> .
<code>resize_as_sparse_</code>	
<code>resolve_conj()</code>	See <code>torch.resolve_conj()</code>
<code>resolve_neg()</code>	See <code>torch.resolve_neg()</code>
<code>retain_grad()</code>	Enables this Tensor to have their grad populated during <code>backward()</code> .
<code>roll(shifts, dims)</code>	See <code>torch.roll()</code>
<code>rot90(k, dims)</code>	See <code>torch.rot90()</code>
<code>round([decimals])</code>	See <code>torch.round()</code>
<code>round_([decimals])</code>	In-place version of <code>round()</code>
<code>row_indices</code>	
<code>rsqrt()</code>	See <code>torch.rsqrt()</code>
<code>rsqrt_()</code>	In-place version of <code>rsqrt()</code>
<code>scatter(dim, index, src)</code>	Out-of-place version of <code>torch.Tensor.scatter_()</code>

continues on next page

Table 12 – continued from previous page

<code>scatter_(dim, index, src[, reduce])</code>	Writes all values from the tensor <code>src</code> into <code>self</code> at the indices specified in the <code>index</code> tensor.
<code>scatter_add(dim, index, src)</code>	Out-of-place version of <code>torch.Tensor.scatter_()</code> .
<code>scatter_add_(dim, index, src)</code>	Adds all values from the tensor <code>src</code> into <code>self</code> at the indices specified in the <code>index</code> tensor in a similar fashion as <code>scatter_()</code> .
<code>scatter_reduce(dim, index, src, reduce, *[...,])</code>	Out-of-place version of <code>torch.Tensor.scatter_reduce_()</code> .
<code>scatter_reduce_(dim, index, src, reduce, *)</code>	Reduces all values from the <code>src</code> tensor to the indices specified in the <code>index</code> tensor in the <code>self</code> tensor using the applied reduction defined via the <code>reduce</code> argument ("sum", "prod", "mean", "amax", "amin").
<code>select(dim, index)</code>	See <code>torch.select()</code>
<code>select_scatter(src, dim, index)</code>	See <code>torch.select_scatter()</code>
<code>set_([source, storage_offset, size, stride])</code>	Sets the underlying storage, size, and strides.
<code>sgn()</code>	See <code>torch.sgn()</code>
<code>sgn_()</code>	In-place version of <code>sgn()</code>
<code>share_memory_()</code>	Moves the underlying storage to shared memory.
<code>short([memory_format])</code>	<code>self.short()</code> is equivalent to <code>self.to(torch.int16)</code> .
<code>sigmoid()</code>	See <code>torch.sigmoid()</code>
<code>sigmoid_()</code>	In-place version of <code>sigmoid()</code>
<code>sign()</code>	See <code>torch.sign()</code>
<code>sign_()</code>	In-place version of <code>sign()</code>
<code>signbit()</code>	See <code>torch.signbit()</code>
<code>sin()</code>	See <code>torch.sin()</code>
<code>sin_()</code>	In-place version of <code>sin()</code>
<code>sinc()</code>	See <code>torch.sinc()</code>
<code>sinc_()</code>	In-place version of <code>sinc()</code>
<code>sinh()</code>	See <code>torch.sinh()</code>
<code>sinh_()</code>	In-place version of <code>sinh()</code>
<code>size([dim])</code>	Returns the size of the <code>self</code> tensor.
<code>slice_scatter(src[, dim, start, end, step])</code>	See <code>torch.slice_scatter()</code>
<code>slogdet()</code>	See <code>torch.slogdet()</code>
<code>smm(mat)</code>	See <code>torch.smm()</code>
<code>softmax(dim)</code>	Alias for <code>torch.nn.functional.softmax()</code> .
<code>solve(other)</code>	
<code>sort([dim, descending])</code>	See <code>torch.sort()</code>
<code>sparse_dim()</code>	Return the number of sparse dimensions in a sparse tensor <code>self</code> .
<code>sparse_mask(mask)</code>	Returns a new sparse tensor with values from a strided tensor <code>self</code> filtered by the indices of the sparse tensor <code>mask</code> .
<code>sparse_resize_(size, sparse_dim, dense_dim)</code>	Resizes <code>self</code> sparse tensor to the desired size and the number of sparse and dense dimensions.
<code>sparse_resize_and_clear_(size, sparse_dim, ...)</code>	Removes all specified elements from a sparse tensor <code>self</code> and resizes <code>self</code> to the desired size and the number of sparse and dense dimensions.
<code>split(split_size[, dim])</code>	See <code>torch.split()</code>

continues on next page

Table 12 – continued from previous page

split_with_sizes

<code>sqrt()</code>	See <code>torch.sqrt()</code>
<code>sqrt_()</code>	In-place version of <code>sqrt()</code>
<code>square()</code>	See <code>torch.square()</code>
<code>square_()</code>	In-place version of <code>square()</code>
<code>squeeze([dim])</code>	See <code>torch.squeeze()</code>
<code>squeeze_([dim])</code>	In-place version of <code>squeeze()</code>
<code>sspaddmm(mat1, mat2, *[beta, alpha])</code>	See <code>torch.sspaddmm()</code>
<code>std([dim, correction, keepdim])</code>	See <code>torch.std()</code>
<code>stft(n_fft[, hop_length, win_length, ...])</code>	See <code>torch.stft()</code>
<code>storage()</code>	Returns the underlying <code>TypedStorage</code> .
<code>storage_offset()</code>	Returns <code>self</code> tensor's offset in the underlying storage in terms of number of storage elements (not bytes).
<code>storage_type()</code>	Returns the type of the underlying storage.
<code>stride(dim)</code>	Returns the stride of <code>self</code> tensor.
<code>sub(other, *[beta, alpha])</code>	See <code>torch.sub()</code> .
<code>sub_(other, *[beta, alpha])</code>	In-place version of <code>sub()</code>
<code>subtract(other, *[beta, alpha])</code>	See <code>torch.subtract()</code> .
<code>subtract_(other, *[beta, alpha])</code>	In-place version of <code>subtract()</code> .
<code>sum([dim, keepdim, dtype])</code>	See <code>torch.sum()</code>
<code>sum_to_size(*size)</code>	Sum this tensor to <code>size</code> .
<code>svd([some, compute_uv])</code>	See <code>torch.svd()</code>
<code>swapaxes(axis0, axis1)</code>	See <code>torch.swapaxes()</code>
<code>swapaxes_(axis0, axis1)</code>	In-place version of <code>swapaxes()</code>
<code>swapdims(dim0, dim1)</code>	See <code>torch.swapdims()</code>
<code>swapdims_(dim0, dim1)</code>	In-place version of <code>swapdims()</code>
<code>symeig([eigenvectors])</code>	
<code>t()</code>	See <code>torch.t()</code>
<code>t_()</code>	In-place version of <code>t()</code>
<code>take(indices)</code>	See <code>torch.take()</code>
<code>take_along_dim(indices, dim)</code>	See <code>torch.take_along_dim()</code>
<code>tan()</code>	See <code>torch.tan()</code>
<code>tan_()</code>	In-place version of <code>tan()</code>
<code>tanh()</code>	See <code>torch.tanh()</code>
<code>tanh_()</code>	In-place version of <code>tanh()</code>
<code>tensor_split(indices_or_sections[, dim])</code>	See <code>torch.tensor_split()</code>
<code>tile(*reps)</code>	See <code>torch.tile()</code>
<code>to(*args, **kwargs)</code>	Performs Tensor dtype and/or device conversion.
<code>to_dense()</code>	Creates a strided copy of <code>self</code> if <code>self</code> is not a strided tensor, otherwise returns <code>self</code> .
<code>to_mkldnn()</code>	Returns a copy of the tensor in <code>torch.mkldnn</code> layout.
<code>to_padded_tensor(padding[, output_size])</code>	See <code>to_padded_tensor()</code>
<code>to_sparse(sparseDims)</code>	Returns a sparse copy of the tensor.
<code>to_sparse_bsc(blocksize, dense_dim)</code>	Convert a tensor to a block sparse column (BSC) storage format of given blocksize.
<code>to_sparse_bsr(blocksize, dense_dim)</code>	Convert a tensor to a block sparse row (BSR) storage format of given blocksize.

continues on next page

Table 12 – continued from previous page

<code>to_sparse_coo()</code>	Convert a tensor to coordinate format.
<code>to_sparse_csc()</code>	Convert a tensor to compressed column storage (CSC) format.
<code>to_sparse_csr([dense_dim])</code>	Convert a tensor to compressed row storage format (CSR).
<code>tolist()</code>	Returns the tensor as a (nested) list.
<code>topk(k[, dim, largest, sorted])</code>	See <code>torch.topk()</code>
<code>trace()</code>	See <code>torch.trace()</code>
<code>transpose(dim0, dim1)</code>	See <code>torch.transpose()</code>
<code>transpose_(dim0, dim1)</code>	In-place version of <code>transpose()</code>
<code>triangular_solve(A[, upper, transpose, ...])</code>	See <code>torch.triangular_solve()</code>
<code>tril([diagonal])</code>	See <code>torch.tril()</code>
<code>tril_([diagonal])</code>	In-place version of <code>tril()</code>
<code>triu([diagonal])</code>	See <code>torch.triu()</code>
<code>triu_([diagonal])</code>	In-place version of <code>triu()</code>
<code>true_divide(value)</code>	See <code>torch.true_divide()</code>
<code>true_divide_(value)</code>	In-place version of <code>true_divide_()</code>
<code>trunc()</code>	See <code>torch.trunc()</code>
<code>trunc_()</code>	In-place version of <code>trunc()</code>
<code>type([dtype, non_blocking])</code>	Returns the type if <code>dtype</code> is not provided, else casts this object to the specified type.
<code>type_as(tensor)</code>	Returns this tensor cast to the type of the given tensor.
<code>unbind([dim])</code>	See <code>torch.unbind()</code>
<code>unflatten(dim, sizes)</code>	See <code>torch.unflatten()</code> .
<code>unfold(dimension, size, step)</code>	Returns a view of the original tensor which contains all slices of size <code>size</code> from <code>self</code> tensor in the dimension <code>dimension</code> .
<code>uniform_([from, to])</code>	Fills <code>self</code> tensor with numbers sampled from the continuous uniform distribution:
<code>unique([sorted, return_inverse, ...])</code>	Returns the unique elements of the input tensor.
<code>unique_consecutive([return_inverse, ...])</code>	Eliminates all but the first element from every consecutive group of equivalent elements.
<code>unsafe_chunk(chunks[, dim])</code>	See <code>torch.unsafe_chunk()</code>
<code>unsafe_split(split_size[, dim])</code>	See <code>torch.unsafe_split()</code>
<code>unsafe_split_with_sizes</code>	
<code>unsqueeze(dim)</code>	See <code>torch.unsqueeze()</code>
<code>unsqueeze_(dim)</code>	In-place version of <code>unsqueeze()</code>
<code>untyped_storage()</code>	Returns the underlying <code>UntypedStorage</code> .
<code>values()</code>	Return the values tensor of a sparse COO tensor.
<code>var([dim, correction, keepdim])</code>	See <code>torch.var()</code>
<code>vdot(other)</code>	See <code>torch.vdot()</code>
<code>view(*shape)</code>	Returns a new tensor with the same data as the <code>self</code> tensor but of a different <code>shape</code> .
<code>view_as(other)</code>	View this tensor as the same size as <code>other</code> .
<code>vsplit(split_size_or_sections)</code>	See <code>torch.vsplit()</code>
<code>where(condition, y)</code>	<code>self.where(condition, y)</code> is equivalent to <code>torch.where(condition, self, y)</code> .
<code>xlogy(other)</code>	See <code>torch.xlogy()</code>
<code>xlogy_(other)</code>	In-place version of <code>xlogy()</code>
<code>xpu([device, non_blocking, memory_format])</code>	Returns a copy of this object in XPU memory.

continues on next page

Table 12 – continued from previous page

<code>zero_()</code>	Fills <code>self</code> tensor with zeros.
----------------------	--

Attributes

<code>H</code>	Returns a view of a matrix (2-D tensor) conjugated and transposed.
<code>T</code>	Returns a view of this tensor with its dimensions reversed.
<code>data</code>	
<code>device</code>	Is the <code>torch.device</code> where this Tensor is.
<code>dtype</code>	
<code>grad</code>	This attribute is <code>None</code> by default and becomes a Tensor the first time a call to <code>backward()</code> computes gradients for <code>self</code> .
<code>grad_fn</code>	
<code>imag</code>	Returns a new tensor containing imaginary values of the <code>self</code> tensor.
<code>is_cpu</code>	Is <code>True</code> if the Tensor is stored on the CPU, <code>False</code> otherwise.
<code>is_cuda</code>	Is <code>True</code> if the Tensor is stored on the GPU, <code>False</code> otherwise.
<code>is_ipu</code>	Is <code>True</code> if the Tensor is stored on the IPU, <code>False</code> otherwise.
<code>is_leaf</code>	All Tensors that have <code>requires_grad</code> which is <code>False</code> will be leaf Tensors by convention.
<code>is_meta</code>	Is <code>True</code> if the Tensor is a meta tensor, <code>False</code> otherwise.
<code>is_mkldnn</code>	
<code>is_mps</code>	Is <code>True</code> if the Tensor is stored on the MPS device, <code>False</code> otherwise.
<code>is_nested</code>	
<code>is_ort</code>	
<code>is_quantized</code>	Is <code>True</code> if the Tensor is quantized, <code>False</code> otherwise.
<code>is_sparse</code>	Is <code>True</code> if the Tensor uses sparse storage layout, <code>False</code> otherwise.
<code>is_sparse_csr</code>	Is <code>True</code> if the Tensor uses sparse CSR storage layout, <code>False</code> otherwise.
<code>is_vulkan</code>	
<code>is_xpu</code>	Is <code>True</code> if the Tensor is stored on the XPU, <code>False</code> otherwise.
<code>layout</code>	

continues on next page

Table 13 – continued from previous page

mH	Accessing this property is equivalent to calling <code>adjoint()</code> .
mT	Returns a view of this tensor with the last two dimensions transposed.
name	
names	Stores names for each of this tensor's dimensions.
ndim	Alias for <code>dim()</code>
output_nr	
real	Returns a new tensor containing real values of the <code>self</code> tensor for a complex-valued input tensor.
requires_grad	Is <code>True</code> if gradients need to be computed for this Tensor, <code>False</code> otherwise.
retains_grad	Is <code>True</code> if this Tensor is non-leaf and its grad is enabled to be populated during <code>backward()</code> , <code>False</code> otherwise.
shape	
volatile	

property `is_leaf: bool`

All Tensors that have `requires_grad` which is `False` will be leaf Tensors by convention.

For Tensors that have `requires_grad` which is `True`, they will be leaf Tensors if they were created by the user. This means that they are not the result of an operation and so `grad_fn` is `None`.

Only leaf Tensors will have their `grad` populated during a call to `backward()`. To get `grad` populated for non-leaf Tensors, you can use `retain_grad()`.

Example:

```
>>> a = torch.rand(10, requires_grad=True)
>>> a.is_leaf
True
>>> b = torch.rand(10, requires_grad=True).cuda()
>>> b.is_leaf
False
# b was created by the operation that cast a cpu Tensor into a cuda Tensor
>>> c = torch.rand(10, requires_grad=True) + 2
>>> c.is_leaf
False
# c was created by the addition operation
>>> d = torch.rand(10).cuda()
>>> d.is_leaf
True
# d does not require gradients and so has no operation creating it (that is_
# tracked by the autograd engine)
>>> e = torch.rand(10).cuda().requires_grad_()
>>> e.is_leaf
True
# e requires gradients and has no operations creating it
```

(continues on next page)

(continued from previous page)

```
>>> f = torch.rand(10, requires_grad=True, device="cuda")
>>> f.is_leaf
True
# f requires grad, has no operation creating it
```

`materialize(shape, device=None, dtype=None)`

Create a Parameter with the same properties of the uninitialized one. Given a shape, it materializes a parameter in the same device and with the same *dtype* as the current one or the specified ones in the arguments.

Parameters

- **shape** (`Tuple[int, ...]`) – (tuple): the shape for the materialized tensor.
- **device** (`torch.device`) – the desired device of the parameters and buffers in this module. Optional.
- **dtype** (`torch.dtype`) – the desired floating point type of the floating point parameters and buffers in this module. Optional.

Return type

None

`share_memory_()`

Moves the underlying storage to shared memory.

This is a no-op if the underlying storage is already in shared memory and for CUDA tensors. Tensors in shared memory cannot be resized.

Return type`UninitializedParameter`**`pytorch_pfn_extras.nn.modules.lazy_batchnorm`****Classes**

<code>pytorch_pfn_extras.nn.modules.lazy_batchnorm.LazyBatchNorm1d(...)</code>	BatchNorm1d module with lazy weight initialization.
<code>pytorch_pfn_extras.nn.modules.lazy_batchnorm.LazyBatchNorm2d(...)</code>	BatchNorm2d module with lazy weight initialization.
<code>pytorch_pfn_extras.nn.modules.lazy_batchnorm.LazyBatchNorm3d(...)</code>	BatchNorm3d module with lazy weight initialization.
<code>pytorch_pfn_extras.nn.modules.lazy_batchnorm.LazyInitializationMixin(...)</code>	A mixin for modules that lazily initialize buffers and parameters.
<code>pytorch_pfn_extras.nn.modules.lazy_batchnorm.UninitializedParameter(...)</code>	

[pytorch_pfn_extras.nn.modules.lazy_batchnorm.LazyBatchNorm1d](#)

```
class pytorch_pfn_extras.nn.modules.lazy_batchnorm.LazyBatchNorm1d(num_features, *args,  
**kwargs)
```

Bases: `_LazyBatchNorm`, `BatchNorm1d`

BatchNorm1d module with lazy weight initialization.

When `num_features` is `None`, it is determined at the first time of the forward step.

Initializes internal Module state, shared by both `nn.Module` and `ScriptModule`.

Methods

<code>__init__(num_features, *args, **kwargs)</code>	Initializes internal Module state, shared by both <code>nn.Module</code> and <code>ScriptModule</code> .
<code>add_module(name, module)</code>	Adds a child module to the current module.
<code>apply(fn)</code>	Applies <code>fn</code> recursively to every submodule (as returned by <code>.children()</code>) as well as self.
<code>bfloat16()</code>	Casts all floating point parameters and buffers to <code>bfloat16</code> datatype.
<code>buffers([recurse])</code>	Returns an iterator over module buffers.
<code>children()</code>	Returns an iterator over immediate children modules.
<code>cpu()</code>	Moves all model parameters and buffers to the CPU.
<code>cuda([device])</code>	Moves all model parameters and buffers to the GPU.
<code>double()</code>	Casts all floating point parameters and buffers to <code>double</code> datatype.
<code>eval()</code>	Sets the module in evaluation mode.
<code>extra_repr()</code>	Set the extra representation of the module
<code>float()</code>	Casts all floating point parameters and buffers to <code>float</code> datatype.
<code>forward(input)</code>	Defines the computation performed at every call.
<code>get_buffer(target)</code>	Returns the buffer given by <code>target</code> if it exists, otherwise throws an error.
<code>get_extra_state()</code>	Returns any extra state to include in the module's <code>state_dict</code> .
<code>get_parameter(target)</code>	Returns the parameter given by <code>target</code> if it exists, otherwise throws an error.
<code>get_submodule(target)</code>	Returns the submodule given by <code>target</code> if it exists, otherwise throws an error.
<code>half()</code>	Casts all floating point parameters and buffers to <code>half</code> datatype.
<code>ipu([device])</code>	Moves all model parameters and buffers to the IPU.
<code>load_state_dict(state_dict[, strict])</code>	Copies parameters and buffers from <code>state_dict</code> into this module and its descendants.
<code>modules()</code>	Returns an iterator over all modules in the network.
<code>named_buffers([prefix, recurse, ...])</code>	Returns an iterator over module buffers, yielding both the name of the buffer as well as the buffer itself.
<code>named_children()</code>	Returns an iterator over immediate children modules, yielding both the name of the module as well as the module itself.

continues on next page

Table 14 – continued from previous page

<code>named_modules([memo, prefix, remove_duplicate])</code>	Returns an iterator over all modules in the network, yielding both the name of the module as well as the module itself.
<code>named_parameters([prefix, recurse, ...])</code>	Returns an iterator over module parameters, yielding both the name of the parameter as well as the parameter itself.
<code>parameters([recurse])</code>	Returns an iterator over module parameters.
<code>register_backward_hook(hook)</code>	Registers a backward hook on the module.
<code>register_buffer(name, tensor[, persistent])</code>	Adds a buffer to the module.
<code>register_forward_hook(hook, *[, prepend, ...])</code>	Registers a forward hook on the module.
<code>register_forward_pre_hook(hook, *[, ...])</code>	Registers a forward pre-hook on the module.
<code>register_full_backward_hook(hook[, prepend])</code>	Registers a backward hook on the module.
<code>register_full_backward_pre_hook(hook[, prepend])</code>	Registers a backward pre-hook on the module.
<code>register_load_state_dict_post_hook(hook)</code>	Registers a post hook to be run after module's <code>load_state_dict</code> is called.
<code>register_module(name, module)</code>	Alias for <code>add_module()</code> .
<code>register_parameter(name, param)</code>	Adds a parameter to the module.
<code>register_state_dict_pre_hook(hook)</code>	These hooks will be called with arguments: <code>self</code> , <code>prefix</code> , and <code>keep_vars</code> before calling <code>state_dict</code> on <code>self</code> .
<code>requires_grad_([requires_grad])</code>	Change if autograd should record operations on parameters in this module.
<code>reset_parameters()</code>	
<code>reset_running_stats()</code>	
<code>set_extra_state(state)</code>	This function is called from <code>load_state_dict()</code> to handle any extra state found within the <code>state_dict</code> .
<code>share_memory()</code>	See <code>torch.Tensor.share_memory_()</code>
<code>state_dict(*args, **kwargs)</code>	Returns a dictionary containing a whole state of the module.
<code>to(*args, **kwargs)</code>	Moves and/or casts the parameters and buffers.
<code>to_empty(*, device)</code>	Moves the parameters and buffers to the specified device without copying storage.
<code>train([mode])</code>	Sets the module in training mode.
<code>type(dst_type)</code>	Casts all parameters and buffers to <code>dst_type</code> .
<code>xpu([device])</code>	Moves all model parameters and buffers to the XPU.
<code>zero_grad([set_to_none])</code>	Sets gradients of all model parameters to zero.

Attributes

T_destination	alias of TypeVar('T_destination', bound=Dict[str, Any])
call_super_init	
dump_patches	
lazy_buffer_names	
lazy_parameter_names	
lazy_parameters_determined	Returns if all lazy parameters are determined.

Parameters

- **num_features** (*Optional[int]*) –
- **args** (*Any*) –
- **kwargs** (*Any*) –

affine: bool

eps: float

momentum: float

num_batches_tracked: Optional[Tensor]

num_features: Optional[int]

running_mean: Any

running_var: Any

track_running_stats: bool

training: bool

pytorch_pfn_extras.nn.modules.lazy_batchnorm.LazyBatchNorm2d

```
class pytorch_pfn_extras.nn.modules.lazy_batchnorm.LazyBatchNorm2d(num_features, *args,  
**kwargs)
```

Bases: `_LazyBatchNorm`, `BatchNorm2d`

BatchNorm2d module with lazy weight initialization.

When `num_features` is None, it is determined at the first time of the forward step.

Initializes internal Module state, shared by both nn.Module and ScriptModule.

Methods

<code>__init__(num_features, *args, **kwargs)</code>	Initializes internal Module state, shared by both nn.Module and ScriptModule.
<code>add_module(name, module)</code>	Adds a child module to the current module.
<code>apply(fn)</code>	Applies <code>fn</code> recursively to every submodule (as returned by <code>.children()</code>) as well as self.
<code>bfloat16()</code>	Casts all floating point parameters and buffers to bfloat16 datatype.
<code>buffers([recurse])</code>	Returns an iterator over module buffers.
<code>children()</code>	Returns an iterator over immediate children modules.
<code>cpu()</code>	Moves all model parameters and buffers to the CPU.
<code>cuda([device])</code>	Moves all model parameters and buffers to the GPU.
<code>double()</code>	Casts all floating point parameters and buffers to <code>double</code> datatype.
<code>eval()</code>	Sets the module in evaluation mode.
<code>extra_repr()</code>	Set the extra representation of the module
<code>float()</code>	Casts all floating point parameters and buffers to <code>float</code> datatype.
<code>forward(input)</code>	Defines the computation performed at every call.
<code>get_buffer(target)</code>	Returns the buffer given by <code>target</code> if it exists, otherwise throws an error.
<code>get_extra_state()</code>	Returns any extra state to include in the module's state_dict.
<code>get_parameter(target)</code>	Returns the parameter given by <code>target</code> if it exists, otherwise throws an error.
<code>get_submodule(target)</code>	Returns the submodule given by <code>target</code> if it exists, otherwise throws an error.
<code>half()</code>	Casts all floating point parameters and buffers to <code>half</code> datatype.
<code>ipu([device])</code>	Moves all model parameters and buffers to the IPU.
<code>load_state_dict(state_dict[, strict])</code>	Copies parameters and buffers from <code>state_dict</code> into this module and its descendants.
<code>modules()</code>	Returns an iterator over all modules in the network.
<code>named_buffers([prefix, recurse, ...])</code>	Returns an iterator over module buffers, yielding both the name of the buffer as well as the buffer itself.
<code>named_children()</code>	Returns an iterator over immediate children modules, yielding both the name of the module as well as the module itself.
<code>named_modules([memo, prefix, remove_duplicate])</code>	Returns an iterator over all modules in the network, yielding both the name of the module as well as the module itself.
<code>named_parameters([prefix, recurse, ...])</code>	Returns an iterator over module parameters, yielding both the name of the parameter as well as the parameter itself.
<code>parameters([recurse])</code>	Returns an iterator over module parameters.
<code>register_backward_hook(hook)</code>	Registers a backward hook on the module.
<code>register_buffer(name, tensor[, persistent])</code>	Adds a buffer to the module.
<code>register_forward_hook(hook, *[, prepend, ...])</code>	Registers a forward hook on the module.
<code>register_forward_pre_hook(hook, *[, ...])</code>	Registers a forward pre-hook on the module.

continues on next page

Table 15 – continued from previous page

<code>register_full_backward_hook(hook[, prepend])</code>	Registers a backward hook on the module.
<code>register_full_backward_pre_hook(hook[, prepend])</code>	Registers a backward pre-hook on the module.
<code>register_load_state_dict_post_hook(hook)</code>	Registers a post hook to be run after module's <code>load_state_dict</code> is called.
<code>register_module(name, module)</code>	Alias for <code>add_module()</code> .
<code>register_parameter(name, param)</code>	Adds a parameter to the module.
<code>register_state_dict_pre_hook(hook)</code>	These hooks will be called with arguments: <code>self</code> , <code>prefix</code> , and <code>keep_vars</code> before calling <code>state_dict</code> on <code>self</code> .
<code>requires_grad_([requires_grad])</code>	Change if autograd should record operations on parameters in this module.
<code>reset_parameters()</code>	
<code>reset_running_stats()</code>	
<code>set_extra_state(state)</code>	This function is called from <code>load_state_dict()</code> to handle any extra state found within the <code>state_dict</code> .
<code>share_memory()</code>	See <code>torch.Tensor.share_memory_()</code>
<code>state_dict(*args, **kwargs)</code>	Returns a dictionary containing a whole state of the module.
<code>to(*args, **kwargs)</code>	Moves and/or casts the parameters and buffers.
<code>to_empty(*, device)</code>	Moves the parameters and buffers to the specified device without copying storage.
<code>train([mode])</code>	Sets the module in training mode.
<code>type(dst_type)</code>	Casts all parameters and buffers to <code>dst_type</code> .
<code>xpu([device])</code>	Moves all model parameters and buffers to the XPU.
<code>zero_grad([set_to_none])</code>	Sets gradients of all model parameters to zero.

Attributes

<code>T_destination</code>	alias of <code>TypeVar('T_destination', bound=Dict[str, Any])</code>
<code>call_super_init</code>	
<code>dump_patches</code>	
<code>lazy_buffer_names</code>	
<code>lazy_parameter_names</code>	
<code>lazy_parameters_determined</code>	Returns if all lazy parameters are determined.

Parameters

- `num_features` (*Optional[int]*) –
- `args` (*Any*) –
- `kwargs` (*Any*) –

```
affine: bool
eps: float
momentum: float
num_batches_tracked: Optional[Tensor]
num_features: Optional[int]
running_mean: Any
running_var: Any
track_running_stats: bool
training: bool
```

pytorch_pfn_extras.nn.modules.lazy_batchnorm.LazyBatchNorm3d

```
class pytorch_pfn_extras.nn.modules.lazy_batchnorm.LazyBatchNorm3d(num_features, *args, **kwargs)
```

Bases: `_LazyBatchNorm`, `BatchNorm3d`

BatchNorm3d module with lazy weight initialization.

When `num_features` is `None`, it is determined at the first time of the forward step.

Initializes internal Module state, shared by both `nn.Module` and `ScriptModule`.

Methods

<code>__init__(num_features, *args, **kwargs)</code>	Initializes internal Module state, shared by both <code>nn.Module</code> and <code>ScriptModule</code> .
<code>add_module(name, module)</code>	Adds a child module to the current module.
<code>apply(fn)</code>	Applies <code>fn</code> recursively to every submodule (as returned by <code>.children()</code>) as well as self.
<code>bfloat16()</code>	Casts all floating point parameters and buffers to <code>bfloat16</code> datatype.
<code>buffers([reuse])</code>	Returns an iterator over module buffers.
<code>children()</code>	Returns an iterator over immediate children modules.
<code>cpu()</code>	Moves all model parameters and buffers to the CPU.
<code>cuda([device])</code>	Moves all model parameters and buffers to the GPU.
<code>double()</code>	Casts all floating point parameters and buffers to <code>double</code> datatype.
<code>eval()</code>	Sets the module in evaluation mode.
<code>extra_repr()</code>	Set the extra representation of the module
<code>float()</code>	Casts all floating point parameters and buffers to <code>float</code> datatype.
<code>forward(input)</code>	Defines the computation performed at every call.
<code>get_buffer(target)</code>	Returns the buffer given by <code>target</code> if it exists, otherwise throws an error.

continues on next page

Table 16 – continued from previous page

<code>get_extra_state()</code>	Returns any extra state to include in the module's <code>state_dict</code> .
<code>get_parameter(target)</code>	Returns the parameter given by <code>target</code> if it exists, otherwise throws an error.
<code>get_submodule(target)</code>	Returns the submodule given by <code>target</code> if it exists, otherwise throws an error.
<code>half()</code>	Casts all floating point parameters and buffers to <code>half</code> datatype.
<code>ipu([device])</code>	Moves all model parameters and buffers to the IPU.
<code>load_state_dict(state_dict[, strict])</code>	Copies parameters and buffers from <code>state_dict</code> into this module and its descendants.
<code>modules()</code>	Returns an iterator over all modules in the network.
<code>named_buffers([prefix, recurse, ...])</code>	Returns an iterator over module buffers, yielding both the name of the buffer as well as the buffer itself.
<code>named_children()</code>	Returns an iterator over immediate children modules, yielding both the name of the module as well as the module itself.
<code>named_modules([memo, prefix, remove_duplicate])</code>	Returns an iterator over all modules in the network, yielding both the name of the module as well as the module itself.
<code>named_parameters([prefix, recurse, ...])</code>	Returns an iterator over module parameters, yielding both the name of the parameter as well as the parameter itself.
<code>parameters([recurse])</code>	Returns an iterator over module parameters.
<code>register_backward_hook(hook)</code>	Registers a backward hook on the module.
<code>register_buffer(name, tensor[, persistent])</code>	Adds a buffer to the module.
<code>register_forward_hook(hook, *[, prepend, ...])</code>	Registers a forward hook on the module.
<code>register_forward_pre_hook(hook, *[, ...])</code>	Registers a forward pre-hook on the module.
<code>register_full_backward_hook(hook[, prepend])</code>	Registers a backward hook on the module.
<code>register_full_backward_pre_hook(hook[, prepend])</code>	Registers a backward pre-hook on the module.
<code>register_load_state_dict_post_hook(hook)</code>	Registers a post hook to be run after module's <code>load_state_dict</code> is called.
<code>register_module(name, module)</code>	Alias for <code>add_module()</code> .
<code>register_parameter(name, param)</code>	Adds a parameter to the module.
<code>register_state_dict_pre_hook(hook)</code>	These hooks will be called with arguments: <code>self</code> , <code>prefix</code> , and <code>keep_vars</code> before calling <code>state_dict</code> on <code>self</code> .
<code>requires_grad_(requires_grad)</code>	Change if autograd should record operations on parameters in this module.
<code>reset_parameters()</code>	
<code>reset_running_stats()</code>	
<code>set_extra_state(state)</code>	This function is called from <code>load_state_dict()</code> to handle any extra state found within the <code>state_dict</code> .
<code>share_memory()</code>	See <code>torch.Tensor.share_memory_()</code>
<code>state_dict(*args, **kwargs)</code>	Returns a dictionary containing a whole state of the module.
<code>to(*args, **kwargs)</code>	Moves and/or casts the parameters and buffers.

continues on next page

Table 16 – continued from previous page

<code>to_empty(*, device)</code>	Moves the parameters and buffers to the specified device without copying storage.
<code>train([mode])</code>	Sets the module in training mode.
<code>type(dst_type)</code>	Casts all parameters and buffers to <code>dst_type</code> .
<code>xpu([device])</code>	Moves all model parameters and buffers to the XPU.
<code>zero_grad([set_to_none])</code>	Sets gradients of all model parameters to zero.

Attributes

<code>T_destination</code>	alias of <code>TypeVar('T_destination', bound=Dict[str, Any])</code>
<code>call_super_init</code>	
<code>dump_patches</code>	
<code>lazy_buffer_names</code>	
<code>lazy_parameter_names</code>	
<code>lazy_parameters_determined</code>	Returns if all lazy parameters are determined.

Parameters

- `num_features` (*Optional[int]*) –
- `args` (*Any*) –
- `kwargs` (*Any*) –

`affine: bool`

`eps: float`

`momentum: float`

`num_batches_tracked: Optional[Tensor]`

`num_features: Optional[int]`

`running_mean: Any`

`running_var: Any`

`track_running_stats: bool`

`training: bool`

[pytorch_pfn_extras.nn.modules.lazy_batchnorm.LazyInitializationMixin](#)

```
class pytorch_pfn_extras.nn.modules.lazy_batchnorm.LazyInitializationMixin(*args, **kwargs)
```

Bases: `object`

A mixin for modules that lazily initialize buffers and parameters.

Unlike regular modules, subclasses of this module can initialize buffers and parameters outside of the constructor (`__init__`). This allows you to, for example, initialize parameters in `forward` method to determine the shape of the weight based on the initial input.

Be sure to run “dummy” forward once to initialize all parameters that should be trained, before passing `module.parameters()` to an optimizer; otherwise weights initialized after `module.parameters()` (e.g., in `forward` function) will never be trained.

Note that lazy modules cannot validate if the shape is correct during deserialization. Also note that the initial weights may become different from the original (non-lazy) module even if the random seed is manually configured, as the order of initialization is different from the original one; especially, `module.cuda()` may cause the initialization to run on a GPU.

The default value of lazy buffers and parameters are `torch.Tensor([])` and `UninitializedParameter()`, respectively.

Methods

```
__init__(*args, **kwargs)
```

```
state_dict(*args, **kwargs)
```

Returns a dictionary containing a whole state of the module.

Attributes

```
lazy_buffer_names
```

```
lazy_parameter_names
```

```
lazy_parameters_determined
```

Returns if all lazy parameters are determined.

Parameters

- **args** (*Any*) –
- **kwargs** (*Any*) –

```
__init__(*args, **kwargs)
```

Parameters

- **self** (*Any*) –
- **args** (*Any*) –
- **kwargs** (*Any*) –

Return type

None

```

lazy_buffer_names: Tuple[str, ...] = ()
lazy_parameter_names: Tuple[str, ...] = ()
property lazy_parameters_determined: bool
    Returns if all lazy parameters are determined.
    Subclasses can perform parameters initialization after all lazy parameters are determined. Note that this may be called during __init__.
state_dict(*args, **kwargs)
    Returns a dictionary containing a whole state of the module.
    This function overrides the default behavior to exclude uninitialized parameter from serialization. This is needed because we need to discriminate lazy parameters (UninitializedParameter()) and initialized empty parameters (torch.nn.Parameter(torch.Tensor())) during deserialization.
    See comments of _lazy_load_hook for details.

```

Parameters

- **self** (Any) –
- **args** (Any) –
- **kwargs** (Any) –

Return type*Dict[str, Any]***[pytorch_pfn_extras.nn.modules.lazy_batchnorm.UninitializedParameter](#)**

```

class pytorch_pfn_extras.nn.modules.lazy_batchnorm.UninitializedParameter(data=None, requires_grad=True)

```

Bases: Parameter

Methods

`__init__()`

<code>abs()</code>	See <code>torch.abs()</code>
<code>abs_()</code>	In-place version of <code>abs()</code>
<code>absolute()</code>	Alias for <code>abs()</code>
<code>absolute_()</code>	In-place version of <code>absolute()</code> Alias for <code>abs_()</code>
<code>acos()</code>	See <code>torch.acos()</code>
<code>acos_()</code>	In-place version of <code>acos()</code>
<code>acosh()</code>	See <code>torch.acosh()</code>
<code>acosh_()</code>	In-place version of <code>acosh()</code>
<code>add(other, *[, alpha])</code>	Add a scalar or tensor to <code>self</code> tensor.
<code>add_(other, *[, alpha])</code>	In-place version of <code>add()</code>
<code>addbmm(batch1, batch2, *[, beta, alpha])</code>	See <code>torch.addbmm()</code>
<code>addbmm_(batch1, batch2, *[, beta, alpha])</code>	In-place version of <code>addbmm()</code>
<code>addcdiv(tensor1, tensor2, *[, value])</code>	See <code>torch.addcdiv()</code>

continues on next page

Table 17 – continued from previous page

addcddiv_(tensor1, tensor2, *[, value])	In-place version of <code>addcddiv()</code>
addcmul_(tensor1, tensor2, *[, value])	See <code>torch.addcmul()</code>
addcmul_(tensor1, tensor2, *[, value])	In-place version of <code>addcmul()</code>
addmm_(mat1, mat2, *[, beta, alpha])	See <code>torch.addmm()</code>
addmm_(mat1, mat2, *[, beta, alpha])	In-place version of <code>addmm()</code>
addmv_(mat, vec, *[, beta, alpha])	See <code>torch.addmv()</code>
addmv_(mat, vec, *[, beta, alpha])	In-place version of <code>addmv()</code>
addr_(vec1, vec2, *[, beta, alpha])	See <code>torch.addr()</code>
addr_(vec1, vec2, *[, beta, alpha])	In-place version of <code>addr()</code>
adjoint()	Alias for <code>adjoint()</code>
align_as(other)	Permutates the dimensions of the <code>self</code> tensor to match the dimension order in the <code>other</code> tensor, adding size-one dims for any new names.
align_to(*names)	Permutates the dimensions of the <code>self</code> tensor to match the order specified in <code>names</code> , adding size-one dims for any new names.
all([dim, keepdim])	See <code>torch.all()</code>
allclose(other[, rtol, atol, equal_nan])	See <code>torch.allclose()</code>
amax([dim, keepdim])	See <code>torch.amax()</code>
amin([dim, keepdim])	See <code>torch.amin()</code>
aminmax(*[, dim, keepdim])	See <code>torch.aminmax()</code>
angle()	See <code>torch.angle()</code>
any([dim, keepdim])	See <code>torch.any()</code>
apply_(callable)	Applies the function <code>callable</code> to each element in the tensor, replacing each element with the value returned by <code>callable</code> .
arccos()	See <code>torch.arccos()</code>
arccos_()	In-place version of <code>arccos()</code>
arccosh	<code>acosh()</code> -> Tensor
arccosh_	<code>acosh_()</code> -> Tensor
arcsin()	See <code>torch.arcsin()</code>
arcsin_()	In-place version of <code>arcsin()</code>
arcsinh()	See <code>torch.arcsinh()</code>
arcsinh_()	In-place version of <code>arcsinh()</code>
arctan()	See <code>torch.arctan()</code>
arctan2(other)	See <code>torch.arctan2()</code>
arctan2_	<code>atan2_(other)</code> -> Tensor
arctan_()	In-place version of <code>arctan()</code>
arctanh()	See <code>torch.arctanh()</code>
arctanh_(other)	In-place version of <code>arctanh()</code>
argmax([dim, keepdim])	See <code>torch.argmax()</code>
argmin([dim, keepdim])	See <code>torch.argmin()</code>
argsort([dim, descending])	See <code>torch.argsort()</code>
argwhere()	See <code>torch.argwhere()</code>
as_strided(size, stride[, storage_offset])	See <code>torch.as_strided()</code>
as_strided_	
as_strided_scatter(src, size, stride[, ...])	See <code>torch.as_strided_scatter()</code>
as_subclass(cls)	Makes a <code>cls</code> instance with the same data pointer as <code>self</code> .
asin()	See <code>torch.asin()</code>

continues on next page

Table 17 – continued from previous page

<code>asin_()</code>	In-place version of <code>asin()</code>
<code>asinh()</code>	See <code>torch.asinh()</code>
<code>asinh_()</code>	In-place version of <code>asinh()</code>
<code>atan()</code>	See <code>torch.atan()</code>
<code>atan2(other)</code>	See <code>torch.atan2()</code>
<code>atan2_(other)</code>	In-place version of <code>atan2()</code>
<code>atan_()</code>	In-place version of <code>atan()</code>
<code>atanh()</code>	See <code>torch.atanh()</code>
<code>atanh_(other)</code>	In-place version of <code>atanh()</code>
<code>backward([gradient, retain_graph, ...])</code>	Computes the gradient of current tensor w.r.t.
<code>baddbmm(batch1, batch2, *[beta, alpha])</code>	See <code>torch.baddbmm()</code>
<code>baddbmm_(batch1, batch2, *[beta, alpha])</code>	In-place version of <code>baddbmm()</code>
<code>bernoulli(*[generator])</code>	Returns a result tensor where each <code>result[i]</code> is independently sampled from <code>Bernoulli(self[i])</code> .
<code>bernoulli_([p, generator])</code>	Fills each location of <code>self</code> with an independent sample from <code>Bernoulli(p)</code> .
<code>bfloat16([memory_format])</code>	<code>self.bfloat16()</code> is equivalent to <code>self.to(torch.bfloat16)</code> .
<code>bincount([weights, minlength])</code>	See <code>torch.bincount()</code>
<code>bitwise_and()</code>	See <code>torch.bitwise_and()</code>
<code>bitwise_and_()</code>	In-place version of <code>bitwise_and()</code>
<code>bitwise_left_shift(other)</code>	See <code>torch.bitwise_left_shift()</code>
<code>bitwise_left_shift_(other)</code>	In-place version of <code>bitwise_left_shift()</code>
<code>bitwise_not()</code>	See <code>torch.bitwise_not()</code>
<code>bitwise_not_()</code>	In-place version of <code>bitwise_not()</code>
<code>bitwise_or()</code>	See <code>torch.bitwise_or()</code>
<code>bitwise_or_()</code>	In-place version of <code>bitwise_or()</code>
<code>bitwise_right_shift(other)</code>	See <code>torch.bitwise_right_shift()</code>
<code>bitwise_right_shift_(other)</code>	In-place version of <code>bitwise_right_shift()</code>
<code>bitwise_xor()</code>	See <code>torch.bitwise_xor()</code>
<code>bitwise_xor_()</code>	In-place version of <code>bitwise_xor()</code>
<code>bmm(batch2)</code>	See <code>torch.bmm()</code>
<code>bool([memory_format])</code>	<code>self.bool()</code> is equivalent to <code>self.to(torch.bool)</code> .
<code>broadcast_to(shape)</code>	See <code>torch.broadcast_to()</code> .
<code>byte([memory_format])</code>	<code>self.byte()</code> is equivalent to <code>self.to(torch.uint8)</code> .
<code>cauchy_([median, sigma, generator])</code>	Fills the tensor with numbers drawn from the Cauchy distribution:
<code>ccol_indices</code>	
<code>cdouble([memory_format])</code>	<code>self.cdouble()</code> is equivalent to <code>self.to(torch.complex128)</code> .
<code>ceil()</code>	See <code>torch.ceil()</code>
<code>ceil_()</code>	In-place version of <code>ceil()</code>
<code>cfloat([memory_format])</code>	<code>self.cfloat()</code> is equivalent to <code>self.to(torch.complex64)</code> .
<code>chalf([memory_format])</code>	<code>self.chalf()</code> is equivalent to <code>self.to(torch.complex32)</code> .
<code>char([memory_format])</code>	<code>self.char()</code> is equivalent to <code>self.to(torch.int8)</code> .

continues on next page

Table 17 – continued from previous page

cholesky([upper])	See <code>torch.cholesky()</code>
cholesky_inverse([upper])	See <code>torch.cholesky_inverse()</code>
cholesky_solve(input2[, upper])	See <code>torch.cholesky_solve()</code>
chunk(chunks[, dim])	See <code>torch.chunk()</code>
clamp([min, max])	See <code>torch.clamp()</code>
clamp_([min, max])	In-place version of <code>clamp()</code>
clamp_max	
clamp_max_	
clamp_min	
clamp_min_	
clip([min, max])	Alias for <code>clamp()</code> .
clip_([min, max])	Alias for <code>clamp_()</code> .
clone(*[, memory_format])	See <code>torch.clone()</code>
coalesce()	Returns a coalesced copy of <code>self</code> if <code>self</code> is an uncoalesced tensor.
col_indices()	Returns the tensor containing the column indices of the <code>self</code> tensor when <code>self</code> is a sparse CSR tensor of layout <code>sparse_csr</code> .
conj()	See <code>torch.conj()</code>
conj_physical()	See <code>torch.conj_physical()</code>
conj_physical_()	In-place version of <code>conj_physical()</code>
contiguous([memory_format])	Returns a contiguous in memory tensor containing the same data as <code>self</code> tensor.
copy_(src[, non_blocking])	Copies the elements from <code>src</code> into <code>self</code> tensor and returns <code>self</code> .
copysign(other)	See <code>torch.copysign()</code>
copysign_(other)	In-place version of <code>copysign()</code>
corrcoef()	See <code>torch.corrcoef()</code>
cos()	See <code>torch.cos()</code>
cos_()	In-place version of <code>cos()</code>
cosh()	See <code>torch.cosh()</code>
cosh_()	In-place version of <code>cosh()</code>
count_nonzero([dim])	See <code>torch.count_nonzero()</code>
cov(*[, correction, fweights, aweights])	See <code>torch.cov()</code>
cpu([memory_format])	Returns a copy of this object in CPU memory.
cross(other[, dim])	See <code>torch.cross()</code>
crow_indices()	Returns the tensor containing the compressed row indices of the <code>self</code> tensor when <code>self</code> is a sparse CSR tensor of layout <code>sparse_csr</code> .
cuda([device, non_blocking, memory_format])	Returns a copy of this object in CUDA memory.
cummax(dim)	See <code>torch.cummax()</code>
cummin(dim)	See <code>torch.cummin()</code>
cumprod(dim[, dtype])	See <code>torch.cumprod()</code>
cumprod_(dim[, dtype])	In-place version of <code>cumprod()</code>
cumsum(dim[, dtype])	See <code>torch.cumsum()</code>
cumsum_(dim[, dtype])	In-place version of <code>cumsum()</code>

continues on next page

Table 17 – continued from previous page

<code>data_ptr()</code>	Returns the address of the first element of <code>self</code> tensor.
<code>deg2rad()</code>	See <code>torch.deg2rad()</code>
<code>deg2rad_()</code>	In-place version of <code>deg2rad()</code>
<code>dense_dim()</code>	Return the number of dense dimensions in a sparse tensor <code>self</code> .
<code>dequantize()</code>	Given a quantized Tensor, dequantize it and return the dequantized float Tensor.
<code>det()</code>	See <code>torch.det()</code>
<code>detach</code>	Returns a new Tensor, detached from the current graph.
<code>detach_</code>	Detaches the Tensor from the graph that created it, making it a leaf.
<code>diag([diagonal])</code>	See <code>torch.diag()</code>
<code>diag_embed([offset, dim1, dim2])</code>	See <code>torch.diag_embed()</code>
<code>diagflat([offset])</code>	See <code>torch.diagflat()</code>
<code>diagonal([offset, dim1, dim2])</code>	See <code>torch.diagonal()</code>
<code>diagonal_scatter(src[, offset, dim1, dim2])</code>	See <code>torch.diagonal_scatter()</code>
<code>diff([n, dim, prepend, append])</code>	See <code>torch.diff()</code>
<code>digamma()</code>	See <code>torch.digamma()</code>
<code>digamma_()</code>	In-place version of <code>digamma()</code>
<code>dim()</code>	Returns the number of dimensions of <code>self</code> tensor.
<code>dist(other[, p])</code>	See <code>torch.dist()</code>
<code>div(value, *[, rounding_mode])</code>	See <code>torch.div()</code>
<code>div_(value, *[, rounding_mode])</code>	In-place version of <code>div()</code>
<code>divide(value, *[, rounding_mode])</code>	See <code>torch.divide()</code>
<code>divide_(value, *[, rounding_mode])</code>	In-place version of <code>divide()</code>
<code>dot(other)</code>	See <code>torch.dot()</code>
<code>double([memory_format])</code>	<code>self.double()</code> is equivalent to <code>self.to(torch.float64)</code> .
<code>dsplit(split_size_or_sections)</code>	See <code>torch.dsplit()</code>
<code>eig([eigenvectors])</code>	
<code>element_size()</code>	Returns the size in bytes of an individual element.
<code>eq(other)</code>	See <code>torch.eq()</code>
<code>eq_(other)</code>	In-place version of <code>eq()</code>
<code>equal(other)</code>	See <code>torch.equal()</code>
<code>erf()</code>	See <code>torch.erf()</code>
<code>erf_()</code>	In-place version of <code>erf()</code>
<code>erfc()</code>	See <code>torch.erfc()</code>
<code>erfc_()</code>	In-place version of <code>erfc()</code>
<code>erfinv()</code>	See <code>torch.erfinv()</code>
<code>erfinv_()</code>	In-place version of <code>erfinv()</code>
<code>exp()</code>	See <code>torch.exp()</code>
<code>exp2()</code>	See <code>torch.exp2()</code>
<code>exp2_()</code>	In-place version of <code>exp2()</code>
<code>exp_()</code>	In-place version of <code>exp()</code>
<code>expand(*sizes)</code>	Returns a new view of the <code>self</code> tensor with singleton dimensions expanded to a larger size.
<code>expand_as(other)</code>	Expand this tensor to the same size as <code>other</code> .
<code>expm1()</code>	See <code>torch.expm1()</code>

continues on next page

Table 17 – continued from previous page

<code>expm1_()</code>	In-place version of <code>expm1()</code>
<code>exponential_([lambda, generator])</code>	Fills <code>self</code> tensor with elements drawn from the exponential distribution:
<code>fill_(value)</code>	Fills <code>self</code> tensor with the specified value.
<code>fill_diagonal_(fill_value[, wrap])</code>	Fill the main diagonal of a tensor that has at least 2-dimensions.
<code>fix()</code>	See <code>torch.fix()</code> .
<code>fix_()</code>	In-place version of <code>fix()</code>
<code>flatten([start_dim, end_dim])</code>	See <code>torch.flatten()</code>
<code>flip(dims)</code>	See <code>torch.flip()</code>
<code>fliplr()</code>	See <code>torch.fliplr()</code>
<code>flipud()</code>	See <code>torch.flipud()</code>
<code>float([memory_format])</code>	<code>self.float()</code> is equivalent to <code>self.to(torch.float32)</code> .
<code>float_power(exponent)</code>	See <code>torch.float_power()</code>
<code>float_power_(exponent)</code>	In-place version of <code>float_power()</code>
<code>floor()</code>	See <code>torch.floor()</code>
<code>floor_()</code>	In-place version of <code>floor()</code>
<code>floor_divide(value)</code>	See <code>torch.floor_divide()</code>
<code>floor_divide_(value)</code>	In-place version of <code>floor_divide()</code>
<code>fmax(other)</code>	See <code>torch.fmax()</code>
<code>fmin(other)</code>	See <code>torch.fmin()</code>
<code>fmod(divisor)</code>	See <code>torch.fmod()</code>
<code>fmod_(divisor)</code>	In-place version of <code>fmod()</code>
<code>frac()</code>	See <code>torch.frac()</code>
<code>frac_()</code>	In-place version of <code>frac()</code>
<code>frexp(input)</code>	See <code>torch.frexp()</code>
<code>gather(dim, index)</code>	See <code>torch.gather()</code>
<code>gcd(other)</code>	See <code>torch.gcd()</code>
<code>gcd_(other)</code>	In-place version of <code>gcd()</code>
<code>ge(other)</code>	See <code>torch.ge()</code> .
<code>ge_(other)</code>	In-place version of <code>ge()</code> .
<code>geometric_(p, *[, generator])</code>	Fills <code>self</code> tensor with elements drawn from the geometric distribution:
<code>geqrft()</code>	See <code>torch.geqrft()</code>
<code>ger(vec2)</code>	See <code>torch.ger()</code>
<code>get_device()</code>	For CUDA tensors, this function returns the device ordinal of the GPU on which the tensor resides.
<code>greater(other)</code>	See <code>torch.greater()</code> .
<code>greater_(other)</code>	In-place version of <code>greater()</code> .
<code>greater_equal(other)</code>	See <code>torch.greater_equal()</code> .
<code>greater_equal_(other)</code>	In-place version of <code>greater_equal()</code> .
<code>gt(other)</code>	See <code>torch.gt()</code> .
<code>gt_(other)</code>	In-place version of <code>gt()</code> .
<code>half([memory_format])</code>	<code>self.half()</code> is equivalent to <code>self.to(torch.float16)</code> .
<code>hardshrink([lambda])</code>	See <code>torch.nn.functional.hardshrink()</code>
<code>has_names</code>	Is True if any of this tensor's dimensions are named.
<code>heaviside(values)</code>	See <code>torch.heaviside()</code>
<code>heaviside_(values)</code>	In-place version of <code>heaviside()</code>

continues on next page

Table 17 – continued from previous page

<code>histc([bins, min, max])</code>	See <code>torch.histc()</code>
<code>histogram(input, bins, *[range, weight, ...])</code>	See <code>torch.histogram()</code>
<code>hsplit(split_size_or_sections)</code>	See <code>torch.hsplit()</code>
<code>hypot(other)</code>	See <code>torch.hypot()</code>
<code>hypot_(other)</code>	In-place version of <code>hypot()</code>
<code>i0()</code>	See <code>torch.i0()</code>
<code>i0_()</code>	In-place version of <code>i0()</code>
<code>igamma(other)</code>	See <code>torch.igamma()</code>
<code>igamma_(other)</code>	In-place version of <code>igamma()</code>
<code>igammac(other)</code>	See <code>torch.igammac()</code>
<code>igammac_(other)</code>	In-place version of <code>igammac()</code>
<code>index_add(dim, index, source, *[alpha])</code>	Out-of-place version of <code>torch.Tensor.index_add_()</code> .
<code>index_add_(dim, index, source, *[alpha])</code>	Accumulate the elements of <code>alpha</code> times <code>source</code> into the <code>self</code> tensor by adding to the indices in the order given in <code>index</code> .
<code>index_copy(dim, index, tensor2)</code>	Out-of-place version of <code>torch.Tensor.index_copy_()</code> .
<code>index_copy_(dim, index, tensor)</code>	Copies the elements of <code>tensor</code> into the <code>self</code> tensor by selecting the indices in the order given in <code>index</code> .
<code>index_fill(dim, index, value)</code>	Out-of-place version of <code>torch.Tensor.index_fill_()</code> .
<code>index_fill_(dim, index, value)</code>	Fills the elements of the <code>self</code> tensor with value <code>value</code> by selecting the indices in the order given in <code>index</code> .
<code>index_put(indices, values[, accumulate])</code>	Out-place version of <code>index_put_()</code> .
<code>index_put_(indices, values[, accumulate])</code>	Puts values from the tensor <code>values</code> into the tensor <code>self</code> using the indices specified in <code>indices</code> (which is a tuple of Tensors).
<code>index_reduce</code>	
<code>index_reduce_(dim, index, source, reduce, *)</code>	Accumulate the elements of <code>source</code> into the <code>self</code> tensor by accumulating to the indices in the order given in <code>index</code> using the reduction given by the <code>reduce</code> argument.
<code>index_select(dim, index)</code>	See <code>torch.index_select()</code>
<code>indices()</code>	Return the indices tensor of a sparse COO tensor.
<code>inner(other)</code>	See <code>torch.inner()</code> .
<code>int([memory_format])</code>	<code>self.int()</code> is equivalent to <code>self.to(torch.int32)</code> .
<code>int_repr()</code>	Given a quantized Tensor, <code>self.int_repr()</code> returns a CPU Tensor with <code>uint8_t</code> as data type that stores the underlying <code>uint8_t</code> values of the given Tensor.
<code>inverse()</code>	See <code>torch.inverse()</code>
<code>ipu([device, non_blocking, memory_format])</code>	Returns a copy of this object in IPU memory.
<code>is_coalesced()</code>	Returns True if <code>self</code> is a sparse COO tensor that is coalesced, False otherwise.
<code>is_complex()</code>	Returns True if the data type of <code>self</code> is a complex data type.
<code>is_conj()</code>	Returns True if the conjugate bit of <code>self</code> is set to true.

continues on next page

Table 17 – continued from previous page

<code>is_contiguous([memory_format])</code>	Returns True if <code>self</code> tensor is contiguous in memory in the order specified by memory format.
<code>is_distributed</code>	
<code>is_floating_point()</code>	Returns True if the data type of <code>self</code> is a floating point data type.
<code>is_inference()</code>	See <code>torch.is_inference()</code>
<code>is_neg()</code>	Returns True if the negative bit of <code>self</code> is set to true.
<code>is_nonzero</code>	
<code>is_pinned</code>	Returns true if this tensor resides in pinned memory.
<code>is_same_size</code>	
<code>is_set_to(tensor)</code>	Returns True if both tensors are pointing to the exact same memory (same storage, offset, size and stride).
<code>is_shared()</code>	Checks if tensor is in shared memory.
<code>is_signed()</code>	Returns True if the data type of <code>self</code> is a signed data type.
<code>isclose(other[, rtol, atol, equal_nan])</code>	See <code>torch.isclose()</code>
<code>isfinite()</code>	See <code>torch.isfinite()</code>
<code>isinf()</code>	See <code>torch.isinf()</code>
<code>isnan()</code>	See <code>torch.isnan()</code>
<code>isneginf()</code>	See <code>torch.isneginf()</code>
<code>isposinf()</code>	See <code>torch.isposinf()</code>
<code>isreal()</code>	See <code>torch.isreal()</code>
<code>istft(n_fft[, hop_length, win_length, ...])</code>	See <code>torch.istft()</code>
<code>item()</code>	Returns the value of this tensor as a standard Python number.
<code>kron(other)</code>	See <code>torch.kron()</code>
<code>kthvalue(k[, dim, keepdim])</code>	See <code>torch.kthvalue()</code>
<code>lcm(other)</code>	See <code>torch.lcm()</code>
<code>lcm_(other)</code>	In-place version of <code>lcm()</code>
<code>ldexp(other)</code>	See <code>torch.ldexp()</code>
<code>ldexp_(other)</code>	In-place version of <code>ldexp()</code>
<code>le(other)</code>	See <code>torch.le()</code> .
<code>le_(other)</code>	In-place version of <code>le()</code> .
<code>lerp(end, weight)</code>	See <code>torch.lerp()</code>
<code>lerp_(end, weight)</code>	In-place version of <code>lerp()</code>
<code>less</code>	<code>lt(other) -> Tensor</code>
<code>less_(other)</code>	In-place version of <code>less()</code> .
<code>less_equal(other)</code>	See <code>torch.less_equal()</code> .
<code>less_equal_(other)</code>	In-place version of <code>less_equal()</code> .
<code>lgamma()</code>	See <code>torch.lgamma()</code>
<code>lgamma_()</code>	In-place version of <code>lgamma()</code>
<code>log()</code>	See <code>torch.log()</code>
<code>log10()</code>	See <code>torch.log10()</code>
<code>log10_(other)</code>	In-place version of <code>log10()</code>
<code>log1p()</code>	See <code>torch.log1p()</code>
<code>log1p_(other)</code>	In-place version of <code>log1p()</code>
<code>log2()</code>	See <code>torch.log2()</code>
<code>log2_(other)</code>	In-place version of <code>log2()</code>

continues on next page

Table 17 – continued from previous page

<code>log_()</code>	In-place version of <code>log()</code>
<code>log_normal_([mean, std, generator])</code>	Fills <code>self</code> tensor with numbers samples from the log-normal distribution parameterized by the given mean μ and standard deviation σ .
<code>log_softmax</code>	
<code>logaddexp(other)</code>	See <code>torch.logaddexp()</code>
<code>logaddexp2(other)</code>	See <code>torch.logaddexp2()</code>
<code>logcumsumexp(dim)</code>	See <code>torch.logcumsumexp()</code>
<code>logdet()</code>	See <code>torch.logdet()</code>
<code>logical_and()</code>	See <code>torch.logical_and()</code>
<code>logical_and_()</code>	In-place version of <code>logical_and()</code>
<code>logical_not()</code>	See <code>torch.logical_not()</code>
<code>logical_not_()</code>	In-place version of <code>logical_not()</code>
<code>logical_or()</code>	See <code>torch.logical_or()</code>
<code>logical_or_()</code>	In-place version of <code>logical_or()</code>
<code>logical_xor()</code>	See <code>torch.logical_xor()</code>
<code>logical_xor_()</code>	In-place version of <code>logical_xor()</code>
<code>logit()</code>	See <code>torch.logit()</code>
<code>logit_()</code>	In-place version of <code>logit()</code>
<code>logsumexp(dim[, keepdim])</code>	See <code>torch.logsumexp()</code>
<code>long([memory_format])</code>	<code>self.long()</code> is equivalent to <code>self.to(torch.int64)</code> .
<code>lstsq(other)</code>	
<code>lt(other)</code>	See <code>torch.lt()</code> .
<code>lt_(other)</code>	In-place version of <code>lt()</code> .
<code>lu([pivot, get_infos])</code>	See <code>torch.lu()</code>
<code>lu_solve(LU_data, LU_pivots)</code>	See <code>torch.lu_solve()</code>
<code>map2_</code>	
<code>map_(tensor, callable)</code>	Applies <code>callable</code> for each element in <code>self</code> tensor and the given <code>tensor</code> and stores the results in <code>self</code> tensor.
<code>masked_fill(mask, value)</code>	Out-of-place version of <code>torch.Tensor.masked_fill_()</code>
<code>masked_fill_(mask, value)</code>	Fills elements of <code>self</code> tensor with <code>value</code> where <code>mask</code> is True.
<code>masked_scatter(mask, tensor)</code>	Out-of-place version of <code>torch.Tensor.masked_scatter_()</code>
<code>masked_scatter_(mask, source)</code>	Copies elements from <code>source</code> into <code>self</code> tensor at positions where the <code>mask</code> is True.
<code>masked_select(mask)</code>	See <code>torch.masked_select()</code>
<code>materialize(shape[, device, dtype])</code>	Create a Parameter with the same properties of the uninitialized one.
<code>matmul(tensor2)</code>	See <code>torch.matmul()</code>
<code>matrix_exp()</code>	See <code>torch.matrix_exp()</code>

continues on next page

Table 17 – continued from previous page

`matrix_power(n)`

Note: `matrix_power()` is deprecated, use `torch.linalg.matrix_power()` instead.

<code>max([dim, keepdim])</code>	See <code>torch.max()</code>
<code>maximum(other)</code>	See <code>torch.maximum()</code>
<code>mean([dim, keepdim, dtype])</code>	See <code>torch.mean()</code>
<code>median([dim, keepdim])</code>	See <code>torch.median()</code>
<code>min([dim, keepdim])</code>	See <code>torch.min()</code>
<code>minimum(other)</code>	See <code>torch.minimum()</code>
<code>mm(mat2)</code>	See <code>torch.mm()</code>
<code>mode([dim, keepdim])</code>	See <code>torch.mode()</code>
<code>moveaxis(source, destination)</code>	See <code>torch.moveaxis()</code>
<code>movedim(source, destination)</code>	See <code>torch.movedim()</code>
<code>msort()</code>	See <code>torch.msort()</code>
<code>mul(value)</code>	See <code>torch.mul()</code> .
<code>mul_(value)</code>	In-place version of <code>mul()</code> .
<code>multinomial(num_samples[, replacement, ...])</code>	See <code>torch.multinomial()</code>
<code>multiply(value)</code>	See <code>torch.multiply()</code> .
<code>multiply_(value)</code>	In-place version of <code>multiply()</code> .
<code>mv(vec)</code>	See <code>torch.mv()</code>
<code>mvlgamma(p)</code>	See <code>torch.mvlgamma()</code>
<code>mvlgamma_(p)</code>	In-place version of <code>mvlgamma()</code>
<code>nan_to_num([nan, posinf, neginf])</code>	See <code>torch.nan_to_num()</code> .
<code>nan_to_num_([nan, posinf, neginf])</code>	In-place version of <code>nan_to_num()</code> .
<code>nanmean([dim, keepdim, dtype])</code>	See <code>torch.nanmean()</code>
<code>nanmedian([dim, keepdim])</code>	See <code>torch.nanmedian()</code>
<code>nanquantile(q[, dim, keepdim, interpolation])</code>	See <code>torch.nanquantile()</code>
<code>nansum([dim, keepdim, dtype])</code>	See <code>torch.nansum()</code>
<code>narrow(dimension, start, length)</code>	See <code>torch.narrow()</code> .
<code>narrow_copy(dimension, start, length)</code>	See <code>torch.narrow_copy()</code> .
<code>ndimension()</code>	Alias for <code>dim()</code>
<code>ne(other)</code>	See <code>torch.ne()</code> .
<code>ne_(other)</code>	In-place version of <code>ne()</code> .
<code>neg()</code>	See <code>torch.neg()</code>
<code>neg_()</code>	In-place version of <code>neg()</code>
<code>negative()</code>	See <code>torch.negative()</code>
<code>negative_()</code>	In-place version of <code>negative()</code>
<code>nelement()</code>	Alias for <code>numel()</code>
<code>new</code>	
<code>new_empty(size, *[, dtype, device, ...])</code>	Returns a Tensor of size <code>size</code> filled with uninitialized data.
<code>new_empty_strided(size, stride[, dtype, ...])</code>	Returns a Tensor of size <code>size</code> and strides <code>stride</code> filled with uninitialized data.
<code>new_full(size, fill_value, *[, dtype, ...])</code>	Returns a Tensor of size <code>size</code> filled with <code>fill_value</code> .
<code>new_ones(size, *[, dtype, device, ...])</code>	Returns a Tensor of size <code>size</code> filled with 1.
<code>new_tensor(data, *[, dtype, device, ...])</code>	Returns a new Tensor with <code>data</code> as the tensor data.

continues on next page

Table 17 – continued from previous page

<code>new_zeros(size, *[..., dtype, device, ...])</code>	Returns a Tensor of size <code>size</code> filled with <code>0</code> .
<code>nextafter(other)</code>	See <code>torch.nextafter()</code>
<code>nextafter_(other)</code>	In-place version of <code>nextafter()</code>
<code>nonzero()</code>	See <code>torch.nonzero()</code>
<code>norm([p, dim, keepdim, dtype])</code>	See <code>torch.norm()</code>
<code>normal_([mean, std, generator])</code>	Fills <code>self</code> tensor with elements samples from the normal distribution parameterized by <code>mean</code> and <code>std</code> .
<code>not_equal(other)</code>	See <code>torch.not_equal()</code> .
<code>not_equal_(other)</code>	In-place version of <code>not_equal()</code> .
<code>numel()</code>	See <code>torch.numel()</code>
<code>numpy(*[..., force])</code>	Returns the tensor as a NumPy ndarray.
<code>orgqr(input2)</code>	See <code>torch.orgqr()</code>
<code>ormqr(input2, input3[, left, transpose])</code>	See <code>torch.ormqr()</code>
<code>outer(vec2)</code>	See <code>torch.outer()</code> .
<code>permute(*dims)</code>	See <code>torch.permute()</code>
<code>pin_memory()</code>	Copies the tensor to pinned memory, if it's not already pinned.
<code>pinverse()</code>	See <code>torch.pinverse()</code>
<code>polygamma(n)</code>	See <code>torch.polygamma()</code>
<code>polygamma_(n)</code>	In-place version of <code>polygamma()</code>
<code>positive()</code>	See <code>torch.positive()</code>
<code>pow(exponent)</code>	See <code>torch.pow()</code>
<code>pow_(exponent)</code>	In-place version of <code>pow()</code>
<code>prelu</code>	
<code>prod([dim, keepdim, dtype])</code>	See <code>torch.prod()</code>
<code>put(input, index, source[, accumulate])</code>	Out-of-place version of <code>torch.Tensor.put_()</code> .
<code>put_(index, source[, accumulate])</code>	Copies the elements from <code>source</code> into the positions specified by <code>index</code> .
<code>q_per_channel_axis()</code>	Given a Tensor quantized by linear (affine) per-channel quantization, returns the index of dimension on which per-channel quantization is applied.
<code>q_per_channel_scales()</code>	Given a Tensor quantized by linear (affine) per-channel quantization, returns a Tensor of scales of the underlying quantizer.
<code>q_per_channel_zero_points()</code>	Given a Tensor quantized by linear (affine) per-channel quantization, returns a tensor of zero_points of the underlying quantizer.
<code>q_scale()</code>	Given a Tensor quantized by linear(affine) quantization, returns the scale of the underlying quantizer().
<code>q_zero_point()</code>	Given a Tensor quantized by linear(affine) quantization, returns the zero_point of the underlying quantizer().
<code>qr([some])</code>	See <code>torch.qr()</code>
<code>qscheme()</code>	Returns the quantization scheme of a given QTensor.
<code>quantile(q[, dim, keepdim, interpolation])</code>	See <code>torch.quantile()</code>
<code>rad2deg()</code>	See <code>torch.rad2deg()</code>
<code>rad2deg_(*)</code>	In-place version of <code>rad2deg()</code>
<code>random_([from, to, generator])</code>	Fills <code>self</code> tensor with numbers sampled from the discrete uniform distribution over <code>[from, to - 1]</code> .
<code>ravel()</code>	see <code>torch.ravel()</code>

continues on next page

Table 17 – continued from previous page

<code>reciprocal()</code>	See <code>torch.reciprocal()</code>
<code>reciprocal_()</code>	In-place version of <code>reciprocal()</code>
<code>record_stream(stream)</code>	Ensures that the tensor memory is not reused for another tensor until all current work queued on <code>stream</code> are complete.
<code>refine_names(*names)</code>	Refines the dimension names of <code>self</code> according to <code>names</code> .
<code>register_hook(hook)</code>	Registers a backward hook.
<code>reinforce(reward)</code>	
<code>relu</code>	
<code>relu_</code>	
<code>remainder(divisor)</code>	See <code>torch.remainder()</code>
<code>remainder_(divisor)</code>	In-place version of <code>remainder()</code>
<code>rename(*names, **rename_map)</code>	Renames dimension names of <code>self</code> .
<code>rename_(*names, **rename_map)</code>	In-place version of <code>rename()</code> .
<code>renorm(p, dim, maxnorm)</code>	See <code>torch.renorm()</code>
<code>renorm_(p, dim, maxnorm)</code>	In-place version of <code>renorm()</code>
<code>repeat(*sizes)</code>	Repeats this tensor along the specified dimensions.
<code>repeat_interleave(repeats[, dim, output_size])</code>	See <code>torch.repeat_interleave()</code> .
<code>requires_grad_([requires_grad])</code>	Change if autograd should record operations on this tensor: sets this tensor's <code>requires_grad</code> attribute in-place.
<code>reshape(*shape)</code>	Returns a tensor with the same data and number of elements as <code>self</code> but with the specified shape.
<code>reshape_as(other)</code>	Returns this tensor as the same shape as <code>other</code> .
<code>resize(*sizes)</code>	
<code>resize_(*sizes[, memory_format])</code>	Resizes <code>self</code> tensor to the specified size.
<code>resize_as(tensor)</code>	
<code>resize_as_(tensor[, memory_format])</code>	Resizes the <code>self</code> tensor to be the same size as the specified <code>tensor</code> .
<code>resize_as_sparse_</code>	
<code>resolve_conj()</code>	See <code>torch.resolve_conj()</code>
<code>resolve_neg()</code>	See <code>torch.resolve_neg()</code>
<code>retain_grad()</code>	Enables this Tensor to have their grad populated during <code>backward()</code> .
<code>roll(shifts, dims)</code>	See <code>torch.roll()</code>
<code>rot90(k, dims)</code>	See <code>torch.rot90()</code>
<code>round([decimals])</code>	See <code>torch.round()</code>
<code>round_([decimals])</code>	In-place version of <code>round()</code>
<code>row_indices</code>	
<code>rsqrt()</code>	See <code>torch.rsqrt()</code>
<code>rsqrt_()</code>	In-place version of <code>rsqrt()</code>
<code>scatter(dim, index, src)</code>	Out-of-place version of <code>torch.Tensor.scatter_()</code>

continues on next page

Table 17 – continued from previous page

<code>scatter_(dim, index, src[, reduce])</code>	Writes all values from the tensor <code>src</code> into <code>self</code> at the indices specified in the <code>index</code> tensor.
<code>scatter_add(dim, index, src)</code>	Out-of-place version of <code>torch.Tensor.scatter_()</code> .
<code>scatter_add_(dim, index, src)</code>	Adds all values from the tensor <code>src</code> into <code>self</code> at the indices specified in the <code>index</code> tensor in a similar fashion as <code>scatter_()</code> .
<code>scatter_reduce(dim, index, src, reduce, *[...,])</code>	Out-of-place version of <code>torch.Tensor.scatter_reduce_()</code> .
<code>scatter_reduce_(dim, index, src, reduce, *)</code>	Reduces all values from the <code>src</code> tensor to the indices specified in the <code>index</code> tensor in the <code>self</code> tensor using the applied reduction defined via the <code>reduce</code> argument ("sum", "prod", "mean", "amax", "amin").
<code>select(dim, index)</code>	See <code>torch.select()</code>
<code>select_scatter(src, dim, index)</code>	See <code>torch.select_scatter()</code>
<code>set_([source, storage_offset, size, stride])</code>	Sets the underlying storage, size, and strides.
<code>sgn()</code>	See <code>torch.sgn()</code>
<code>sgn_()</code>	In-place version of <code>sgn()</code>
<code>share_memory_()</code>	Moves the underlying storage to shared memory.
<code>short([memory_format])</code>	<code>self.short()</code> is equivalent to <code>self.to(torch.int16)</code> .
<code>sigmoid()</code>	See <code>torch.sigmoid()</code>
<code>sigmoid_()</code>	In-place version of <code>sigmoid()</code>
<code>sign()</code>	See <code>torch.sign()</code>
<code>sign_()</code>	In-place version of <code>sign()</code>
<code>signbit()</code>	See <code>torch.signbit()</code>
<code>sin()</code>	See <code>torch.sin()</code>
<code>sin_()</code>	In-place version of <code>sin()</code>
<code>sinc()</code>	See <code>torch.sinc()</code>
<code>sinc_()</code>	In-place version of <code>sinc()</code>
<code>sinh()</code>	See <code>torch.sinh()</code>
<code>sinh_()</code>	In-place version of <code>sinh()</code>
<code>size([dim])</code>	Returns the size of the <code>self</code> tensor.
<code>slice_scatter(src[, dim, start, end, step])</code>	See <code>torch.slice_scatter()</code>
<code>slogdet()</code>	See <code>torch.slogdet()</code>
<code>smm(mat)</code>	See <code>torch.smm()</code>
<code>softmax(dim)</code>	Alias for <code>torch.nn.functional.softmax()</code> .
<code>solve(other)</code>	
<code>sort([dim, descending])</code>	See <code>torch.sort()</code>
<code>sparse_dim()</code>	Return the number of sparse dimensions in a sparse tensor <code>self</code> .
<code>sparse_mask(mask)</code>	Returns a new sparse tensor with values from a strided tensor <code>self</code> filtered by the indices of the sparse tensor <code>mask</code> .
<code>sparse_resize_(size, sparse_dim, dense_dim)</code>	Resizes <code>self</code> sparse tensor to the desired size and the number of sparse and dense dimensions.
<code>sparse_resize_and_clear_(size, sparse_dim, ...)</code>	Removes all specified elements from a sparse tensor <code>self</code> and resizes <code>self</code> to the desired size and the number of sparse and dense dimensions.
<code>split(split_size[, dim])</code>	See <code>torch.split()</code>

continues on next page

Table 17 – continued from previous page

split_with_sizes

sqrt()	See <code>torch.sqrt()</code>
sqrt_()	In-place version of <code>sqrt()</code>
square()	See <code>torch.square()</code>
square_()	In-place version of <code>square()</code>
squeeze([dim])	See <code>torch.squeeze()</code>
squeeze_([dim])	In-place version of <code>squeeze()</code>
sspaddmm(mat1, mat2, *[beta, alpha])	See <code>torch.sspaddmm()</code>
std([dim, correction, keepdim])	See <code>torch.std()</code>
stft(n_fft[, hop_length, win_length, ...])	See <code>torch.stft()</code>
storage()	Returns the underlying <code>TypedStorage</code> .
storage_offset()	Returns <code>self</code> tensor's offset in the underlying storage in terms of number of storage elements (not bytes).
storage_type()	Returns the type of the underlying storage.
stride(dim)	Returns the stride of <code>self</code> tensor.
sub(other, *[alpha])	See <code>torch.sub()</code> .
sub_(other, *[alpha])	In-place version of <code>sub()</code>
subtract(other, *[alpha])	See <code>torch.subtract()</code> .
subtract_(other, *[alpha])	In-place version of <code>subtract()</code> .
sum([dim, keepdim, dtype])	See <code>torch.sum()</code>
sum_to_size(*size)	Sum this tensor to <code>size</code> .
svd([some, compute_uv])	See <code>torch.svd()</code>
swapaxes(axis0, axis1)	See <code>torch.swapaxes()</code>
swapaxes_(axis0, axis1)	In-place version of <code>swapaxes()</code>
swapdims(dim0, dim1)	See <code>torch.swapdims()</code>
swapdims_(dim0, dim1)	In-place version of <code>swapdims()</code>
symeig([eigenvectors])	
t()	See <code>torch.t()</code>
t_()	In-place version of <code>t()</code>
take(indices)	See <code>torch.take()</code>
take_along_dim(indices, dim)	See <code>torch.take_along_dim()</code>
tan()	See <code>torch.tan()</code>
tan_()	In-place version of <code>tan()</code>
tanh()	See <code>torch.tanh()</code>
tanh_()	In-place version of <code>tanh()</code>
tensor_split(indices_or_sections[, dim])	See <code>torch.tensor_split()</code>
tile(*reps)	See <code>torch.tile()</code>
to(*args, **kwargs)	Performs Tensor <code>dtype</code> and/or device conversion.
to_dense()	Creates a strided copy of <code>self</code> if <code>self</code> is not a strided tensor, otherwise returns <code>self</code> .
to_mkldnn()	Returns a copy of the tensor in <code>torch.mkldnn</code> layout.
to_padded_tensor(padding[, output_size])	See <code>to_padded_tensor()</code>
to_sparse(sparseDims)	Returns a sparse copy of the tensor.
to_sparse_bsc(blocksize, dense_dim)	Convert a tensor to a block sparse column (BSC) storage format of given blocksize.
to_sparse_bsr(blocksize, dense_dim)	Convert a tensor to a block sparse row (BSR) storage format of given blocksize.

continues on next page

Table 17 – continued from previous page

<code>to_sparse_coo()</code>	Convert a tensor to coordinate format.
<code>to_sparse_csc()</code>	Convert a tensor to compressed column storage (CSC) format.
<code>to_sparse_csr([dense_dim])</code>	Convert a tensor to compressed row storage format (CSR).
<code>tolist()</code>	Returns the tensor as a (nested) list.
<code>topk(k[, dim, largest, sorted])</code>	See <code>torch.topk()</code>
<code>trace()</code>	See <code>torch.trace()</code>
<code>transpose(dim0, dim1)</code>	See <code>torch.transpose()</code>
<code>transpose_(dim0, dim1)</code>	In-place version of <code>transpose()</code>
<code>triangular_solve(A[, upper, transpose, ...])</code>	See <code>torch.triangular_solve()</code>
<code>tril([diagonal])</code>	See <code>torch.tril()</code>
<code>tril_([diagonal])</code>	In-place version of <code>tril()</code>
<code>triu([diagonal])</code>	See <code>torch.triu()</code>
<code>triu_([diagonal])</code>	In-place version of <code>triu()</code>
<code>true_divide(value)</code>	See <code>torch.true_divide()</code>
<code>true_divide_(value)</code>	In-place version of <code>true_divide_()</code>
<code>trunc()</code>	See <code>torch.trunc()</code>
<code>trunc_()</code>	In-place version of <code>trunc()</code>
<code>type([dtype, non_blocking])</code>	Returns the type if <code>dtype</code> is not provided, else casts this object to the specified type.
<code>type_as(tensor)</code>	Returns this tensor cast to the type of the given tensor.
<code>unbind([dim])</code>	See <code>torch.unbind()</code>
<code>unflatten(dim, sizes)</code>	See <code>torch.unflatten()</code> .
<code>unfold(dimension, size, step)</code>	Returns a view of the original tensor which contains all slices of size <code>size</code> from <code>self</code> tensor in the dimension <code>dimension</code> .
<code>uniform_([from, to])</code>	Fills <code>self</code> tensor with numbers sampled from the continuous uniform distribution:
<code>unique([sorted, return_inverse, ...])</code>	Returns the unique elements of the input tensor.
<code>unique_consecutive([return_inverse, ...])</code>	Eliminates all but the first element from every consecutive group of equivalent elements.
<code>unsafe_chunk(chunks[, dim])</code>	See <code>torch.unsafe_chunk()</code>
<code>unsafe_split(split_size[, dim])</code>	See <code>torch.unsafe_split()</code>
<code>unsafe_split_with_sizes</code>	
<code>unsqueeze(dim)</code>	See <code>torch.unsqueeze()</code>
<code>unsqueeze_(dim)</code>	In-place version of <code>unsqueeze()</code>
<code>untyped_storage()</code>	Returns the underlying <code>UntypedStorage</code> .
<code>values()</code>	Return the values tensor of a sparse COO tensor.
<code>var([dim, correction, keepdim])</code>	See <code>torch.var()</code>
<code>vdot(other)</code>	See <code>torch.vdot()</code>
<code>view(*shape)</code>	Returns a new tensor with the same data as the <code>self</code> tensor but of a different <code>shape</code> .
<code>view_as(other)</code>	View this tensor as the same size as <code>other</code> .
<code>vsplit(split_size_or_sections)</code>	See <code>torch.vsplit()</code>
<code>where(condition, y)</code>	<code>self.where(condition, y)</code> is equivalent to <code>torch.where(condition, self, y)</code> .
<code>xlogy(other)</code>	See <code>torch.xlogy()</code>
<code>xlogy_(other)</code>	In-place version of <code>xlogy()</code>
<code>xpu([device, non_blocking, memory_format])</code>	Returns a copy of this object in XPU memory.

continues on next page

Table 17 – continued from previous page

<code>zero_()</code>	Fills <code>self</code> tensor with zeros.
----------------------	--

Attributes

<code>H</code>	Returns a view of a matrix (2-D tensor) conjugated and transposed.
<code>T</code>	Returns a view of this tensor with its dimensions reversed.
<code>data</code>	
<code>device</code>	Is the <code>torch.device</code> where this Tensor is.
<code>dtype</code>	
<code>grad</code>	This attribute is <code>None</code> by default and becomes a Tensor the first time a call to <code>backward()</code> computes gradients for <code>self</code> .
<code>grad_fn</code>	
<code>imag</code>	Returns a new tensor containing imaginary values of the <code>self</code> tensor.
<code>is_cpu</code>	Is <code>True</code> if the Tensor is stored on the CPU, <code>False</code> otherwise.
<code>is_cuda</code>	Is <code>True</code> if the Tensor is stored on the GPU, <code>False</code> otherwise.
<code>is_ipu</code>	Is <code>True</code> if the Tensor is stored on the IPU, <code>False</code> otherwise.
<code>is_leaf</code>	All Tensors that have <code>requires_grad</code> which is <code>False</code> will be leaf Tensors by convention.
<code>is_meta</code>	Is <code>True</code> if the Tensor is a meta tensor, <code>False</code> otherwise.
<code>is_mkldnn</code>	
<code>is_mps</code>	Is <code>True</code> if the Tensor is stored on the MPS device, <code>False</code> otherwise.
<code>is_nested</code>	
<code>is_ort</code>	
<code>is_quantized</code>	Is <code>True</code> if the Tensor is quantized, <code>False</code> otherwise.
<code>is_sparse</code>	Is <code>True</code> if the Tensor uses sparse storage layout, <code>False</code> otherwise.
<code>is_sparse_csr</code>	Is <code>True</code> if the Tensor uses sparse CSR storage layout, <code>False</code> otherwise.
<code>is_vulkan</code>	
<code>is_xpu</code>	Is <code>True</code> if the Tensor is stored on the XPU, <code>False</code> otherwise.
<code>layout</code>	

continues on next page

Table 18 – continued from previous page

mH	Accessing this property is equivalent to calling <code>adjoint()</code> .
mT	Returns a view of this tensor with the last two dimensions transposed.
name	
names	Stores names for each of this tensor's dimensions.
ndim	Alias for <code>dim()</code>
output_nr	
real	Returns a new tensor containing real values of the <code>self</code> tensor for a complex-valued input tensor.
requires_grad	Is <code>True</code> if gradients need to be computed for this Tensor, <code>False</code> otherwise.
retains_grad	Is <code>True</code> if this Tensor is non-leaf and its grad is enabled to be populated during <code>backward()</code> , <code>False</code> otherwise.
shape	
volatile	

property `is_leaf: bool`

All Tensors that have `requires_grad` which is `False` will be leaf Tensors by convention.

For Tensors that have `requires_grad` which is `True`, they will be leaf Tensors if they were created by the user. This means that they are not the result of an operation and so `grad_fn` is `None`.

Only leaf Tensors will have their `grad` populated during a call to `backward()`. To get `grad` populated for non-leaf Tensors, you can use `retain_grad()`.

Example:

```
>>> a = torch.rand(10, requires_grad=True)
>>> a.is_leaf
True
>>> b = torch.rand(10, requires_grad=True).cuda()
>>> b.is_leaf
False
# b was created by the operation that cast a cpu Tensor into a cuda Tensor
>>> c = torch.rand(10, requires_grad=True) + 2
>>> c.is_leaf
False
# c was created by the addition operation
>>> d = torch.rand(10).cuda()
>>> d.is_leaf
True
# d does not require gradients and so has no operation creating it (that is_
# tracked by the autograd engine)
>>> e = torch.rand(10).cuda().requires_grad_()
>>> e.is_leaf
True
# e requires gradients and has no operations creating it
```

(continues on next page)

(continued from previous page)

```
>>> f = torch.rand(10, requires_grad=True, device="cuda")
>>> f.is_leaf
True
# f requires grad, has no operation creating it
```

materialize(shape, device=None, dtype=None)

Create a Parameter with the same properties of the uninitialized one. Given a shape, it materializes a parameter in the same device and with the same *dtype* as the current one or the specified ones in the arguments.

Parameters

- **shape** (*Tuple[int, ...]*) – (tuple): the shape for the materialized tensor.
- **device** (*torch.device*) – the desired device of the parameters and buffers in this module. Optional.
- **dtype** (*torch.dtype*) – the desired floating point type of the floating point parameters and buffers in this module. Optional.

Return type

None

share_memory_()

Moves the underlying storage to shared memory.

This is a no-op if the underlying storage is already in shared memory and for CUDA tensors. Tensors in shared memory cannot be resized.

Return type

UninitializedParameter

pytorch_pfn_extras.nn.modules.lazy_conv**Classes**

<i>pytorch_pfn_extras.nn.modules.lazy_conv.</i>	Conv1d module with lazy weight initialization.
<i>LazyConv1d(...)</i>	
<i>pytorch_pfn_extras.nn.modules.lazy_conv.</i>	Conv2d module with lazy weight initialization.
<i>LazyConv2d(...)</i>	
<i>pytorch_pfn_extras.nn.modules.lazy_conv.</i>	Conv3d module with lazy weight initialization.
<i>LazyConv3d(...)</i>	
<i>pytorch_pfn_extras.nn.modules.lazy_conv.</i>	A mixin for modules that lazily initialize buffers and parameters.
<i>LazyInitializationMixin(...)</i>	
<i>pytorch_pfn_extras.nn.modules.lazy_conv.</i>	
<i>UninitializedParameter(...)</i>	

pytorch_pfn_extras.nn.modules.lazy_conv.LazyConv1d

```
class pytorch_pfn_extras.nn.modules.lazy_conv.LazyConv1d(in_channels, *args, **kwargs)
```

Bases: `_LazyConvNd`, `Conv1d`

Conv1d module with lazy weight initialization.

When `in_channels` is `None`, it is determined at the first time of the forward step.

Initializes internal Module state, shared by both `nn.Module` and `ScriptModule`.

Methods

<code>__init__(in_channels, *args, **kwargs)</code>	Initializes internal Module state, shared by both <code>nn.Module</code> and <code>ScriptModule</code> .
<code>add_module(name, module)</code>	Adds a child module to the current module.
<code>apply(fn)</code>	Applies <code>fn</code> recursively to every submodule (as returned by <code>.children()</code>) as well as self.
<code>bfloat16()</code>	Casts all floating point parameters and buffers to <code>bfloat16</code> datatype.
<code>buffers([recurse])</code>	Returns an iterator over module buffers.
<code>children()</code>	Returns an iterator over immediate children modules.
<code>cpu()</code>	Moves all model parameters and buffers to the CPU.
<code>cuda([device])</code>	Moves all model parameters and buffers to the GPU.
<code>double()</code>	Casts all floating point parameters and buffers to <code>double</code> datatype.
<code>eval()</code>	Sets the module in evaluation mode.
<code>extra_repr()</code>	Set the extra representation of the module
<code>float()</code>	Casts all floating point parameters and buffers to <code>float</code> datatype.
<code>forward(input)</code>	Defines the computation performed at every call.
<code>get_buffer(target)</code>	Returns the buffer given by <code>target</code> if it exists, otherwise throws an error.
<code>get_extra_state()</code>	Returns any extra state to include in the module's <code>state_dict</code> .
<code>get_parameter(target)</code>	Returns the parameter given by <code>target</code> if it exists, otherwise throws an error.
<code>get_submodule(target)</code>	Returns the submodule given by <code>target</code> if it exists, otherwise throws an error.
<code>half()</code>	Casts all floating point parameters and buffers to <code>half</code> datatype.
<code>ipu([device])</code>	Moves all model parameters and buffers to the IPU.
<code>load_state_dict(state_dict[, strict])</code>	Copies parameters and buffers from <code>state_dict</code> into this module and its descendants.
<code>modules()</code>	Returns an iterator over all modules in the network.
<code>named_buffers([prefix, recurse, ...])</code>	Returns an iterator over module buffers, yielding both the name of the buffer as well as the buffer itself.
<code>named_children()</code>	Returns an iterator over immediate children modules, yielding both the name of the module as well as the module itself.

continues on next page

Table 19 – continued from previous page

<code>named_modules([memo, prefix, remove_duplicate])</code>	Returns an iterator over all modules in the network, yielding both the name of the module as well as the module itself.
<code>named_parameters([prefix, recurse, ...])</code>	Returns an iterator over module parameters, yielding both the name of the parameter as well as the parameter itself.
<code>parameters([recurse])</code>	Returns an iterator over module parameters.
<code>register_backward_hook(hook)</code>	Registers a backward hook on the module.
<code>register_buffer(name, tensor[, persistent])</code>	Adds a buffer to the module.
<code>register_forward_hook(hook, *[, prepend, ...])</code>	Registers a forward hook on the module.
<code>register_forward_pre_hook(hook, *[, ...])</code>	Registers a forward pre-hook on the module.
<code>register_full_backward_hook(hook[, prepend])</code>	Registers a backward hook on the module.
<code>register_full_backward_pre_hook(hook[, prepend])</code>	Registers a backward pre-hook on the module.
<code>register_load_state_dict_post_hook(hook)</code>	Registers a post hook to be run after module's <code>load_state_dict</code> is called.
<code>register_module(name, module)</code>	Alias for <code>add_module()</code> .
<code>register_parameter(name, param)</code>	Adds a parameter to the module.
<code>register_state_dict_pre_hook(hook)</code>	These hooks will be called with arguments: <code>self</code> , <code>prefix</code> , and <code>keep_vars</code> before calling <code>state_dict</code> on <code>self</code> .
<code>requires_grad_([requires_grad])</code>	Change if autograd should record operations on parameters in this module.
<code>reset_parameters()</code>	
<code>set_extra_state(state)</code>	This function is called from <code>load_state_dict()</code> to handle any extra state found within the <code>state_dict</code> . See <code>torch.Tensor.share_memory_()</code>
<code>share_memory()</code>	
<code>state_dict(*args, **kwargs)</code>	Returns a dictionary containing a whole state of the module.
<code>to(*args, **kwargs)</code>	Moves and/or casts the parameters and buffers.
<code>to_empty(*, device)</code>	Moves the parameters and buffers to the specified device without copying storage.
<code>train([mode])</code>	Sets the module in training mode.
<code>type(dst_type)</code>	Casts all parameters and buffers to <code>dst_type</code> .
<code>xpu([device])</code>	Moves all model parameters and buffers to the XPU.
<code>zero_grad([set_to_none])</code>	Sets gradients of all model parameters to zero.

Attributes

T_destination	alias of TypeVar('T_destination', bound=Dict[str, Any])
call_super_init	
dump_patches	
lazy_buffer_names	
lazy_parameter_names	
lazy_parameters_determined	Returns if all lazy parameters are determined.

Parameters

- **in_channels** (*Optional[int]*) –
- **args** (*Any*) –
- **kwargs** (*Any*) –

bias: `Optional[Tensor]`

dilation: `Tuple[int, ...]`

groups: `int`

in_channels: `Optional[int]`

kernel_size: `Tuple[int, ...]`

out_channels: `int`

output_padding: `Tuple[int, ...]`

padding: `Union[str, Tuple[int, ...]]`

padding_mode: `str`

stride: `Tuple[int, ...]`

training: `bool`

transposed: `bool`

weight: `Tensor`

[pytorch_pfn_extras.nn.modules.lazy_conv.LazyConv2d](#)

```
class pytorch_pfn_extras.nn.modules.lazy_conv.LazyConv2d(in_channels, *args, **kwargs)
```

Bases: `_LazyConvNd`, `Conv2d`

Conv2d module with lazy weight initialization.

When `in_channels` is `None`, it is determined at the first time of the forward step.

Initializes internal Module state, shared by both `nn.Module` and `ScriptModule`.

Methods

<code>__init__(in_channels, *args, **kwargs)</code>	Initializes internal Module state, shared by both <code>nn.Module</code> and <code>ScriptModule</code> .
<code>add_module(name, module)</code>	Adds a child module to the current module.
<code>apply(fn)</code>	Applies <code>fn</code> recursively to every submodule (as returned by <code>.children()</code>) as well as self.
<code>bfloat16()</code>	Casts all floating point parameters and buffers to <code>bfloat16</code> datatype.
<code>buffers([recurse])</code>	Returns an iterator over module buffers.
<code>children()</code>	Returns an iterator over immediate children modules.
<code>cpu()</code>	Moves all model parameters and buffers to the CPU.
<code>cuda([device])</code>	Moves all model parameters and buffers to the GPU.
<code>double()</code>	Casts all floating point parameters and buffers to <code>double</code> datatype.
<code>eval()</code>	Sets the module in evaluation mode.
<code>extra_repr()</code>	Set the extra representation of the module
<code>float()</code>	Casts all floating point parameters and buffers to <code>float</code> datatype.
<code>forward(input)</code>	Defines the computation performed at every call.
<code>get_buffer(target)</code>	Returns the buffer given by <code>target</code> if it exists, otherwise throws an error.
<code>get_extra_state()</code>	Returns any extra state to include in the module's <code>state_dict</code> .
<code>get_parameter(target)</code>	Returns the parameter given by <code>target</code> if it exists, otherwise throws an error.
<code>get_submodule(target)</code>	Returns the submodule given by <code>target</code> if it exists, otherwise throws an error.
<code>half()</code>	Casts all floating point parameters and buffers to <code>half</code> datatype.
<code>ipu([device])</code>	Moves all model parameters and buffers to the IPU.
<code>load_state_dict(state_dict[, strict])</code>	Copies parameters and buffers from <code>state_dict</code> into this module and its descendants.
<code>modules()</code>	Returns an iterator over all modules in the network.
<code>named_buffers([prefix, recurse, ...])</code>	Returns an iterator over module buffers, yielding both the name of the buffer as well as the buffer itself.
<code>named_children()</code>	Returns an iterator over immediate children modules, yielding both the name of the module as well as the module itself.

continues on next page

Table 20 – continued from previous page

<code>named_modules([memo, prefix, remove_duplicate])</code>	Returns an iterator over all modules in the network, yielding both the name of the module as well as the module itself.
<code>named_parameters([prefix, recurse, ...])</code>	Returns an iterator over module parameters, yielding both the name of the parameter as well as the parameter itself.
<code>parameters([recurse])</code>	Returns an iterator over module parameters.
<code>register_backward_hook(hook)</code>	Registers a backward hook on the module.
<code>register_buffer(name, tensor[, persistent])</code>	Adds a buffer to the module.
<code>register_forward_hook(hook, *[, prepend, ...])</code>	Registers a forward hook on the module.
<code>register_forward_pre_hook(hook, *[, ...])</code>	Registers a forward pre-hook on the module.
<code>register_full_backward_hook(hook[, prepend])</code>	Registers a backward hook on the module.
<code>register_full_backward_pre_hook(hook[, prepend])</code>	Registers a backward pre-hook on the module.
<code>register_load_state_dict_post_hook(hook)</code>	Registers a post hook to be run after module's <code>load_state_dict</code> is called.
<code>register_module(name, module)</code>	Alias for <code>add_module()</code> .
<code>register_parameter(name, param)</code>	Adds a parameter to the module.
<code>register_state_dict_pre_hook(hook)</code>	These hooks will be called with arguments: <code>self</code> , <code>prefix</code> , and <code>keep_vars</code> before calling <code>state_dict</code> on <code>self</code> .
<code>requires_grad_([requires_grad])</code>	Change if autograd should record operations on parameters in this module.
<code>reset_parameters()</code>	
<code>set_extra_state(state)</code>	This function is called from <code>load_state_dict()</code> to handle any extra state found within the <code>state_dict</code> . See <code>torch.Tensor.share_memory_()</code>
<code>share_memory()</code>	
<code>state_dict(*args, **kwargs)</code>	Returns a dictionary containing a whole state of the module.
<code>to(*args, **kwargs)</code>	Moves and/or casts the parameters and buffers.
<code>to_empty(*, device)</code>	Moves the parameters and buffers to the specified device without copying storage.
<code>train([mode])</code>	Sets the module in training mode.
<code>type(dst_type)</code>	Casts all parameters and buffers to <code>dst_type</code> .
<code>xpu([device])</code>	Moves all model parameters and buffers to the XPU.
<code>zero_grad([set_to_none])</code>	Sets gradients of all model parameters to zero.

Attributes

T_destination	alias of TypeVar('T_destination', bound=Dict[str, Any])
call_super_init	
dump_patches	
lazy_buffer_names	
lazy_parameter_names	
lazy_parameters_determined	Returns if all lazy parameters are determined.

Parameters

- **in_channels** (*Optional[int]*) –
- **args** (*Any*) –
- **kwargs** (*Any*) –

bias: *Optional[Tensor]*

dilation: *Tuple[int, ...]*

groups: *int*

in_channels: *Optional[int]*

kernel_size: *Tuple[int, ...]*

out_channels: *int*

output_padding: *Tuple[int, ...]*

padding: *Union[str, Tuple[int, ...]]*

padding_mode: *str*

stride: *Tuple[int, ...]*

training: *bool*

transposed: *bool*

weight: *Tensor*

pytorch_pfn_extras.nn.modules.lazy_conv.LazyConv3d

```
class pytorch_pfn_extras.nn.modules.lazy_conv.LazyConv3d(in_channels, *args, **kwargs)
```

Bases: `_LazyConvNd`, `Conv3d`

Conv3d module with lazy weight initialization.

When `in_channels` is `None`, it is determined at the first time of the forward step.

Initializes internal Module state, shared by both `nn.Module` and `ScriptModule`.

Methods

<code>__init__(in_channels, *args, **kwargs)</code>	Initializes internal Module state, shared by both <code>nn.Module</code> and <code>ScriptModule</code> .
<code>add_module(name, module)</code>	Adds a child module to the current module.
<code>apply(fn)</code>	Applies <code>fn</code> recursively to every submodule (as returned by <code>.children()</code>) as well as self.
<code>bfloat16()</code>	Casts all floating point parameters and buffers to <code>bfloat16</code> datatype.
<code>buffers([recurse])</code>	Returns an iterator over module buffers.
<code>children()</code>	Returns an iterator over immediate children modules.
<code>cpu()</code>	Moves all model parameters and buffers to the CPU.
<code>cuda([device])</code>	Moves all model parameters and buffers to the GPU.
<code>double()</code>	Casts all floating point parameters and buffers to <code>double</code> datatype.
<code>eval()</code>	Sets the module in evaluation mode.
<code>extra_repr()</code>	Set the extra representation of the module
<code>float()</code>	Casts all floating point parameters and buffers to <code>float</code> datatype.
<code>forward(input)</code>	Defines the computation performed at every call.
<code>get_buffer(target)</code>	Returns the buffer given by <code>target</code> if it exists, otherwise throws an error.
<code>get_extra_state()</code>	Returns any extra state to include in the module's <code>state_dict</code> .
<code>get_parameter(target)</code>	Returns the parameter given by <code>target</code> if it exists, otherwise throws an error.
<code>get_submodule(target)</code>	Returns the submodule given by <code>target</code> if it exists, otherwise throws an error.
<code>half()</code>	Casts all floating point parameters and buffers to <code>half</code> datatype.
<code>ipu([device])</code>	Moves all model parameters and buffers to the IPU.
<code>load_state_dict(state_dict[, strict])</code>	Copies parameters and buffers from <code>state_dict</code> into this module and its descendants.
<code>modules()</code>	Returns an iterator over all modules in the network.
<code>named_buffers([prefix, recurse, ...])</code>	Returns an iterator over module buffers, yielding both the name of the buffer as well as the buffer itself.
<code>named_children()</code>	Returns an iterator over immediate children modules, yielding both the name of the module as well as the module itself.

continues on next page

Table 21 – continued from previous page

<code>named_modules([memo, prefix, remove_duplicate])</code>	Returns an iterator over all modules in the network, yielding both the name of the module as well as the module itself.
<code>named_parameters([prefix, recurse, ...])</code>	Returns an iterator over module parameters, yielding both the name of the parameter as well as the parameter itself.
<code>parameters([recurse])</code>	Returns an iterator over module parameters.
<code>register_backward_hook(hook)</code>	Registers a backward hook on the module.
<code>register_buffer(name, tensor[, persistent])</code>	Adds a buffer to the module.
<code>register_forward_hook(hook, *[, prepend, ...])</code>	Registers a forward hook on the module.
<code>register_forward_pre_hook(hook, *[, ...])</code>	Registers a forward pre-hook on the module.
<code>register_full_backward_hook(hook[, prepend])</code>	Registers a backward hook on the module.
<code>register_full_backward_pre_hook(hook[, prepend])</code>	Registers a backward pre-hook on the module.
<code>register_load_state_dict_post_hook(hook)</code>	Registers a post hook to be run after module's <code>load_state_dict</code> is called.
<code>register_module(name, module)</code>	Alias for <code>add_module()</code> .
<code>register_parameter(name, param)</code>	Adds a parameter to the module.
<code>register_state_dict_pre_hook(hook)</code>	These hooks will be called with arguments: <code>self</code> , <code>prefix</code> , and <code>keep_vars</code> before calling <code>state_dict</code> on <code>self</code> .
<code>requires_grad_([requires_grad])</code>	Change if autograd should record operations on parameters in this module.
<code>reset_parameters()</code>	
<code>set_extra_state(state)</code>	This function is called from <code>load_state_dict()</code> to handle any extra state found within the <code>state_dict</code> . See <code>torch.Tensor.share_memory_()</code>
<code>share_memory()</code>	
<code>state_dict(*args, **kwargs)</code>	Returns a dictionary containing a whole state of the module.
<code>to(*args, **kwargs)</code>	Moves and/or casts the parameters and buffers.
<code>to_empty(*, device)</code>	Moves the parameters and buffers to the specified device without copying storage.
<code>train([mode])</code>	Sets the module in training mode.
<code>type(dst_type)</code>	Casts all parameters and buffers to <code>dst_type</code> .
<code>xpu([device])</code>	Moves all model parameters and buffers to the XPU.
<code>zero_grad([set_to_none])</code>	Sets gradients of all model parameters to zero.

Attributes

T_destination	alias of TypeVar('T_destination', bound=Dict[str, Any])
call_super_init	
dump_patches	
lazy_buffer_names	
lazy_parameter_names	
lazy_parameters_determined	Returns if all lazy parameters are determined.

Parameters

- **in_channels** (*Optional[int]*) –
- **args** (*Any*) –
- **kwargs** (*Any*) –

bias: `Optional[Tensor]`

dilation: `Tuple[int, ...]`

groups: `int`

in_channels: `Optional[int]`

kernel_size: `Tuple[int, ...]`

out_channels: `int`

output_padding: `Tuple[int, ...]`

padding: `Union[str, Tuple[int, ...]]`

padding_mode: `str`

stride: `Tuple[int, ...]`

training: `bool`

transposed: `bool`

weight: `Tensor`

[pytorch_pfn_extras.nn.modules.lazy_conv.LazyInitializationMixin](#)

```
class pytorch_pfn_extras.nn.modules.lazy_conv.LazyInitializationMixin(*args, **kwargs)
```

Bases: `object`

A mixin for modules that lazily initialize buffers and parameters.

Unlike regular modules, subclasses of this module can initialize buffers and parameters outside of the constructor (`__init__`). This allows you to, for example, initialize parameters in `forward` method to determine the shape of the weight based on the initial input.

Be sure to run “dummy” forward once to initialize all parameters that should be trained, before passing `module.parameters()` to an optimizer; otherwise weights initialized after `module.parameters()` (e.g., in `forward` function) will never be trained.

Note that lazy modules cannot validate if the shape is correct during deserialization. Also note that the initial weights may become different from the original (non-lazy) module even if the random seed is manually configured, as the order of initialization is different from the original one; especially, `module.cuda()` may cause the initialization to run on a GPU.

The default value of lazy buffers and parameters are `torch.Tensor([])` and `UninitializedParameter()`, respectively.

Methods

`__init__(*args, **kwargs)`

`state_dict(*args, **kwargs)`

Returns a dictionary containing a whole state of the module.

Attributes

`lazy_buffer_names`

`lazy_parameter_names`

`lazy_parameters_determined`

Returns if all lazy parameters are determined.

Parameters

- **args** (*Any*) –
- **kwargs** (*Any*) –

`__init__(*args, **kwargs)`

Parameters

- **self** (*Any*) –
- **args** (*Any*) –
- **kwargs** (*Any*) –

Return type

None

```

lazy_buffer_names: Tuple[str, ...] = ()
lazy_parameter_names: Tuple[str, ...] = ()
property lazy_parameters_determined: bool
    Returns if all lazy parameters are determined.
    Subclasses can perform parameters initialization after all lazy parameters are determined. Note that this may be called during __init__.
state_dict(*args, **kwargs)
    Returns a dictionary containing a whole state of the module.
    This function overrides the default behavior to exclude uninitialized parameter from serialization. This is needed because we need to discriminate lazy parameters (UninitializedParameter()) and initialized empty parameters (torch.nn.Parameter(torch.Tensor())) during deserialization.
    See comments of _lazy_load_hook for details.

```

Parameters

- **self** (Any) –
- **args** (Any) –
- **kwargs** (Any) –

Return type*Dict[str, Any]***[pytorch_pfn_extras.nn.modules.lazy_conv.UninitializedParameter](#)**

```

class pytorch_pfn_extras.nn.modules.lazy_conv.UninitializedParameter(data=None,
requires_grad=True)

```

Bases: Parameter

Methods

`__init__()`

<code>abs()</code>	See <code>torch.abs()</code>
<code>abs_()</code>	In-place version of <code>abs()</code>
<code>absolute()</code>	Alias for <code>abs()</code>
<code>absolute_()</code>	In-place version of <code>absolute()</code> Alias for <code>abs_()</code>
<code>acos()</code>	See <code>torch.acos()</code>
<code>acos_()</code>	In-place version of <code>acos()</code>
<code>acosh()</code>	See <code>torch.acosh()</code>
<code>acosh_()</code>	In-place version of <code>acosh()</code>
<code>add(other, *[, alpha])</code>	Add a scalar or tensor to <code>self</code> tensor.
<code>add_(other, *[, alpha])</code>	In-place version of <code>add()</code>
<code>addbmm(batch1, batch2, *[, beta, alpha])</code>	See <code>torch.addbmm()</code>
<code>addbmm_(batch1, batch2, *[, beta, alpha])</code>	In-place version of <code>addbmm()</code>
<code>addcdiv(tensor1, tensor2, *[, value])</code>	See <code>torch.addcdiv()</code>

continues on next page

Table 22 – continued from previous page

addcddiv_(tensor1, tensor2, *[, value])	In-place version of <code>addcddiv()</code>
addcmul_(tensor1, tensor2, *[, value])	See <code>torch.addcmul()</code>
addcmul_(tensor1, tensor2, *[, value])	In-place version of <code>addcmul()</code>
addmm_(mat1, mat2, *[, beta, alpha])	See <code>torch.addmm()</code>
addmm_(mat1, mat2, *[, beta, alpha])	In-place version of <code>addmm()</code>
addmv_(mat, vec, *[, beta, alpha])	See <code>torch.addmv()</code>
addmv_(mat, vec, *[, beta, alpha])	In-place version of <code>addmv()</code>
addr_(vec1, vec2, *[, beta, alpha])	See <code>torch.addr()</code>
addr_(vec1, vec2, *[, beta, alpha])	In-place version of <code>addr()</code>
adjoint()	Alias for <code>adjoint()</code>
align_as(other)	Permutates the dimensions of the <code>self</code> tensor to match the dimension order in the <code>other</code> tensor, adding size-one dims for any new names.
align_to(*names)	Permutates the dimensions of the <code>self</code> tensor to match the order specified in <code>names</code> , adding size-one dims for any new names.
all([dim, keepdim])	See <code>torch.all()</code>
allclose(other[, rtol, atol, equal_nan])	See <code>torch.allclose()</code>
amax([dim, keepdim])	See <code>torch.amax()</code>
amin([dim, keepdim])	See <code>torch.amin()</code>
aminmax(*[, dim, keepdim])	See <code>torch.aminmax()</code>
angle()	See <code>torch.angle()</code>
any([dim, keepdim])	See <code>torch.any()</code>
apply_(callable)	Applies the function <code>callable</code> to each element in the tensor, replacing each element with the value returned by <code>callable</code> .
arccos()	See <code>torch.arccos()</code>
arccos_()	In-place version of <code>arccos()</code>
arccosh	<code>acosh()</code> -> Tensor
arccosh_	<code>acosh_()</code> -> Tensor
arcsin()	See <code>torch.arcsin()</code>
arcsin_()	In-place version of <code>arcsin()</code>
arcsinh()	See <code>torch.arcsinh()</code>
arcsinh_()	In-place version of <code>arcsinh()</code>
arctan()	See <code>torch.arctan()</code>
arctan2(other)	See <code>torch.arctan2()</code>
arctan2_	<code>atan2_(other)</code> -> Tensor
arctan_()	In-place version of <code>arctan()</code>
arctanh()	See <code>torch.arctanh()</code>
arctanh_(other)	In-place version of <code>arctanh()</code>
argmax([dim, keepdim])	See <code>torch.argmax()</code>
argmin([dim, keepdim])	See <code>torch.argmin()</code>
argsort([dim, descending])	See <code>torch.argsort()</code>
argwhere()	See <code>torch.argwhere()</code>
as_strided(size, stride[, storage_offset])	See <code>torch.as_strided()</code>
as_strided_	
as_strided_scatter(src, size, stride[,...])	See <code>torch.as_strided_scatter()</code>
as_subclass(cls)	Makes a <code>cls</code> instance with the same data pointer as <code>self</code> .
asin()	See <code>torch.asin()</code>

continues on next page

Table 22 – continued from previous page

<code>asin_()</code>	In-place version of <code>asin()</code>
<code>asinh()</code>	See <code>torch.asinh()</code>
<code>asinh_()</code>	In-place version of <code>asinh()</code>
<code>atan()</code>	See <code>torch.atan()</code>
<code>atan2(other)</code>	See <code>torch.atan2()</code>
<code>atan2_(other)</code>	In-place version of <code>atan2()</code>
<code>atan_()</code>	In-place version of <code>atan()</code>
<code>atanh()</code>	See <code>torch.atanh()</code>
<code>atanh_(other)</code>	In-place version of <code>atanh()</code>
<code>backward([gradient, retain_graph, ...])</code>	Computes the gradient of current tensor w.r.t.
<code>baddbmm(batch1, batch2, *[beta, alpha])</code>	See <code>torch.baddbmm()</code>
<code>baddbmm_(batch1, batch2, *[beta, alpha])</code>	In-place version of <code>baddbmm()</code>
<code>bernoulli(*[generator])</code>	Returns a result tensor where each <code>result[i]</code> is independently sampled from <code>Bernoulli(self[i])</code> .
<code>bernoulli_([p, generator])</code>	Fills each location of <code>self</code> with an independent sample from <code>Bernoulli(p)</code> .
<code>bfloat16([memory_format])</code>	<code>self.bfloat16()</code> is equivalent to <code>self.to(torch.bfloat16)</code> .
<code>bincount([weights, minlength])</code>	See <code>torch.bincount()</code>
<code>bitwise_and()</code>	See <code>torch.bitwise_and()</code>
<code>bitwise_and_()</code>	In-place version of <code>bitwise_and()</code>
<code>bitwise_left_shift(other)</code>	See <code>torch.bitwise_left_shift()</code>
<code>bitwise_left_shift_(other)</code>	In-place version of <code>bitwise_left_shift()</code>
<code>bitwise_not()</code>	See <code>torch.bitwise_not()</code>
<code>bitwise_not_()</code>	In-place version of <code>bitwise_not()</code>
<code>bitwise_or()</code>	See <code>torch.bitwise_or()</code>
<code>bitwise_or_()</code>	In-place version of <code>bitwise_or()</code>
<code>bitwise_right_shift(other)</code>	See <code>torch.bitwise_right_shift()</code>
<code>bitwise_right_shift_(other)</code>	In-place version of <code>bitwise_right_shift()</code>
<code>bitwise_xor()</code>	See <code>torch.bitwise_xor()</code>
<code>bitwise_xor_()</code>	In-place version of <code>bitwise_xor()</code>
<code>bmm(batch2)</code>	See <code>torch.bmm()</code>
<code>bool([memory_format])</code>	<code>self.bool()</code> is equivalent to <code>self.to(torch.bool)</code> .
<code>broadcast_to(shape)</code>	See <code>torch.broadcast_to()</code> .
<code>byte([memory_format])</code>	<code>self.byte()</code> is equivalent to <code>self.to(torch.uint8)</code> .
<code>cauchy_([median, sigma, generator])</code>	Fills the tensor with numbers drawn from the Cauchy distribution:
<code>ccol_indices</code>	
<code>cdouble([memory_format])</code>	<code>self.cdouble()</code> is equivalent to <code>self.to(torch.complex128)</code> .
<code>ceil()</code>	See <code>torch.ceil()</code>
<code>ceil_()</code>	In-place version of <code>ceil()</code>
<code>cfloat([memory_format])</code>	<code>self.cfloat()</code> is equivalent to <code>self.to(torch.complex64)</code> .
<code>chalf([memory_format])</code>	<code>self.chalf()</code> is equivalent to <code>self.to(torch.complex32)</code> .
<code>char([memory_format])</code>	<code>self.char()</code> is equivalent to <code>self.to(torch.int8)</code> .

continues on next page

Table 22 – continued from previous page

cholesky([upper])	See <code>torch.cholesky()</code>
cholesky_inverse([upper])	See <code>torch.cholesky_inverse()</code>
cholesky_solve(input2[, upper])	See <code>torch.cholesky_solve()</code>
chunk(chunks[, dim])	See <code>torch.chunk()</code>
clamp([min, max])	See <code>torch.clamp()</code>
clamp_([min, max])	In-place version of <code>clamp()</code>
clamp_max	
clamp_max_	
clamp_min	
clamp_min_	
clip([min, max])	Alias for <code>clamp()</code> .
clip_([min, max])	Alias for <code>clamp_()</code> .
clone(*[, memory_format])	See <code>torch.clone()</code>
coalesce()	Returns a coalesced copy of <code>self</code> if <code>self</code> is an uncoalesced tensor.
col_indices()	Returns the tensor containing the column indices of the <code>self</code> tensor when <code>self</code> is a sparse CSR tensor of layout <code>sparse_csr</code> .
conj()	See <code>torch.conj()</code>
conj_physical()	See <code>torch.conj_physical()</code>
conj_physical_()	In-place version of <code>conj_physical()</code>
contiguous([memory_format])	Returns a contiguous in memory tensor containing the same data as <code>self</code> tensor.
copy_(src[, non_blocking])	Copies the elements from <code>src</code> into <code>self</code> tensor and returns <code>self</code> .
copysign(other)	See <code>torch.copysign()</code>
copysign_(other)	In-place version of <code>copysign()</code>
corrcoef()	See <code>torch.corrcoef()</code>
cos()	See <code>torch.cos()</code>
cos_()	In-place version of <code>cos()</code>
cosh()	See <code>torch.cosh()</code>
cosh_()	In-place version of <code>cosh()</code>
count_nonzero([dim])	See <code>torch.count_nonzero()</code>
cov(*[, correction, fweights, aweights])	See <code>torch.cov()</code>
cpu([memory_format])	Returns a copy of this object in CPU memory.
cross(other[, dim])	See <code>torch.cross()</code>
crow_indices()	Returns the tensor containing the compressed row indices of the <code>self</code> tensor when <code>self</code> is a sparse CSR tensor of layout <code>sparse_csr</code> .
cuda([device, non_blocking, memory_format])	Returns a copy of this object in CUDA memory.
cummax(dim)	See <code>torch.cummax()</code>
cummin(dim)	See <code>torch.cummin()</code>
cumprod(dim[, dtype])	See <code>torch.cumprod()</code>
cumprod_(dim[, dtype])	In-place version of <code>cumprod()</code>
cumsum(dim[, dtype])	See <code>torch.cumsum()</code>
cumsum_(dim[, dtype])	In-place version of <code>cumsum()</code>

continues on next page

Table 22 – continued from previous page

<code>data_ptr()</code>	Returns the address of the first element of <code>self</code> tensor.
<code>deg2rad()</code>	See <code>torch.deg2rad()</code>
<code>deg2rad_()</code>	In-place version of <code>deg2rad()</code>
<code>dense_dim()</code>	Return the number of dense dimensions in a sparse tensor <code>self</code> .
<code>dequantize()</code>	Given a quantized Tensor, dequantize it and return the dequantized float Tensor.
<code>det()</code>	See <code>torch.det()</code>
<code>detach</code>	Returns a new Tensor, detached from the current graph.
<code>detach_</code>	Detaches the Tensor from the graph that created it, making it a leaf.
<code>diag([diagonal])</code>	See <code>torch.diag()</code>
<code>diag_embed([offset, dim1, dim2])</code>	See <code>torch.diag_embed()</code>
<code>diagflat([offset])</code>	See <code>torch.diagflat()</code>
<code>diagonal([offset, dim1, dim2])</code>	See <code>torch.diagonal()</code>
<code>diagonal_scatter(src[, offset, dim1, dim2])</code>	See <code>torch.diagonal_scatter()</code>
<code>diff([n, dim, prepend, append])</code>	See <code>torch.diff()</code>
<code>digamma()</code>	See <code>torch.digamma()</code>
<code>digamma_()</code>	In-place version of <code>digamma()</code>
<code>dim()</code>	Returns the number of dimensions of <code>self</code> tensor.
<code>dist(other[, p])</code>	See <code>torch.dist()</code>
<code>div(value, *[, rounding_mode])</code>	See <code>torch.div()</code>
<code>div_(value, *[, rounding_mode])</code>	In-place version of <code>div()</code>
<code>divide(value, *[, rounding_mode])</code>	See <code>torch.divide()</code>
<code>divide_(value, *[, rounding_mode])</code>	In-place version of <code>divide()</code>
<code>dot(other)</code>	See <code>torch.dot()</code>
<code>double([memory_format])</code>	<code>self.double()</code> is equivalent to <code>self.to(torch.float64)</code> .
<code>dsplit(split_size_or_sections)</code>	See <code>torch.dsplt()</code>
<code>eig([eigenvectors])</code>	
<code>element_size()</code>	Returns the size in bytes of an individual element.
<code>eq(other)</code>	See <code>torch.eq()</code>
<code>eq_(other)</code>	In-place version of <code>eq()</code>
<code>equal(other)</code>	See <code>torch.equal()</code>
<code>erf()</code>	See <code>torch.erf()</code>
<code>erf_()</code>	In-place version of <code>erf()</code>
<code>erfc()</code>	See <code>torch.erfc()</code>
<code>erfc_()</code>	In-place version of <code>erfc()</code>
<code>erfinv()</code>	See <code>torch.erfinv()</code>
<code>erfinv_()</code>	In-place version of <code>erfinv()</code>
<code>exp()</code>	See <code>torch.exp()</code>
<code>exp2()</code>	See <code>torch.exp2()</code>
<code>exp2_()</code>	In-place version of <code>exp2()</code>
<code>exp_()</code>	In-place version of <code>exp()</code>
<code>expand(*sizes)</code>	Returns a new view of the <code>self</code> tensor with singleton dimensions expanded to a larger size.
<code>expand_as(other)</code>	Expand this tensor to the same size as <code>other</code> .
<code>expm1()</code>	See <code>torch.expm1()</code>

continues on next page

Table 22 – continued from previous page

<code>expm1_()</code>	In-place version of <code>expm1()</code>
<code>exponential_([lambda, generator])</code>	Fills <code>self</code> tensor with elements drawn from the exponential distribution:
<code>fill_(value)</code>	Fills <code>self</code> tensor with the specified value.
<code>fill_diagonal_(fill_value[, wrap])</code>	Fill the main diagonal of a tensor that has at least 2-dimensions.
<code>fix()</code>	See <code>torch.fix()</code> .
<code>fix_()</code>	In-place version of <code>fix()</code>
<code>flatten([start_dim, end_dim])</code>	See <code>torch.flatten()</code>
<code>flip(dims)</code>	See <code>torch.flip()</code>
<code>fliplr()</code>	See <code>torch.fliplr()</code>
<code>flipud()</code>	See <code>torch.flipud()</code>
<code>float([memory_format])</code>	<code>self.float()</code> is equivalent to <code>self.to(torch.float32)</code> .
<code>float_power(exponent)</code>	See <code>torch.float_power()</code>
<code>float_power_(exponent)</code>	In-place version of <code>float_power()</code>
<code>floor()</code>	See <code>torch.floor()</code>
<code>floor_()</code>	In-place version of <code>floor()</code>
<code>floor_divide(value)</code>	See <code>torch.floor_divide()</code>
<code>floor_divide_(value)</code>	In-place version of <code>floor_divide()</code>
<code>fmax(other)</code>	See <code>torch.fmax()</code>
<code>fmin(other)</code>	See <code>torch.fmin()</code>
<code>fmod(divisor)</code>	See <code>torch.fmod()</code>
<code>fmod_(divisor)</code>	In-place version of <code>fmod()</code>
<code>frac()</code>	See <code>torch.frac()</code>
<code>frac_()</code>	In-place version of <code>frac()</code>
<code>frexp(input)</code>	See <code>torch.frexp()</code>
<code>gather(dim, index)</code>	See <code>torch.gather()</code>
<code>gcd(other)</code>	See <code>torch.gcd()</code>
<code>gcd_(other)</code>	In-place version of <code>gcd()</code>
<code>ge(other)</code>	See <code>torch.ge()</code> .
<code>ge_(other)</code>	In-place version of <code>ge()</code> .
<code>geometric_(p, *[, generator])</code>	Fills <code>self</code> tensor with elements drawn from the geometric distribution:
<code>geqrft()</code>	See <code>torch.geqrft()</code>
<code>ger(vec2)</code>	See <code>torch.ger()</code>
<code>get_device()</code>	For CUDA tensors, this function returns the device ordinal of the GPU on which the tensor resides.
<code>greater(other)</code>	See <code>torch.greater()</code> .
<code>greater_(other)</code>	In-place version of <code>greater()</code> .
<code>greater_equal(other)</code>	See <code>torch.greater_equal()</code> .
<code>greater_equal_(other)</code>	In-place version of <code>greater_equal()</code> .
<code>gt(other)</code>	See <code>torch.gt()</code> .
<code>gt_(other)</code>	In-place version of <code>gt()</code> .
<code>half([memory_format])</code>	<code>self.half()</code> is equivalent to <code>self.to(torch.float16)</code> .
<code>hardshrink([lambda])</code>	See <code>torch.nn.functional.hardshrink()</code>
<code>has_names</code>	Is True if any of this tensor's dimensions are named.
<code>heaviside(values)</code>	See <code>torch.heaviside()</code>
<code>heaviside_(values)</code>	In-place version of <code>heaviside()</code>

continues on next page

Table 22 – continued from previous page

<code>histc([bins, min, max])</code>	See <code>torch.histc()</code>
<code>histogram(input, bins, *[range, weight, ...])</code>	See <code>torch.histogram()</code>
<code>hsplit(split_size_or_sections)</code>	See <code>torch.hsplit()</code>
<code>hypot(other)</code>	See <code>torch.hypot()</code>
<code>hypot_(other)</code>	In-place version of <code>hypot()</code>
<code>i0()</code>	See <code>torch.i0()</code>
<code>i0_()</code>	In-place version of <code>i0()</code>
<code>igamma(other)</code>	See <code>torch.igamma()</code>
<code>igamma_(other)</code>	In-place version of <code>igamma()</code>
<code>igammac(other)</code>	See <code>torch.igammac()</code>
<code>igammac_(other)</code>	In-place version of <code>igammac()</code>
<code>index_add(dim, index, source, *[alpha])</code>	Out-of-place version of <code>torch.Tensor.index_add_()</code> .
<code>index_add_(dim, index, source, *[alpha])</code>	Accumulate the elements of <code>alpha</code> times <code>source</code> into the <code>self</code> tensor by adding to the indices in the order given in <code>index</code> .
<code>index_copy(dim, index, tensor2)</code>	Out-of-place version of <code>torch.Tensor.index_copy_()</code> .
<code>index_copy_(dim, index, tensor)</code>	Copies the elements of <code>tensor</code> into the <code>self</code> tensor by selecting the indices in the order given in <code>index</code> .
<code>index_fill(dim, index, value)</code>	Out-of-place version of <code>torch.Tensor.index_fill_()</code> .
<code>index_fill_(dim, index, value)</code>	Fills the elements of the <code>self</code> tensor with value <code>value</code> by selecting the indices in the order given in <code>index</code> .
<code>index_put(indices, values[, accumulate])</code>	Out-place version of <code>index_put_()</code> .
<code>index_put_(indices, values[, accumulate])</code>	Puts values from the tensor <code>values</code> into the tensor <code>self</code> using the indices specified in <code>indices</code> (which is a tuple of Tensors).
<code>index_reduce</code>	
<code>index_reduce_(dim, index, source, reduce, *)</code>	Accumulate the elements of <code>source</code> into the <code>self</code> tensor by accumulating to the indices in the order given in <code>index</code> using the reduction given by the <code>reduce</code> argument.
<code>index_select(dim, index)</code>	See <code>torch.index_select()</code>
<code>indices()</code>	Return the indices tensor of a sparse COO tensor.
<code>inner(other)</code>	See <code>torch.inner()</code> .
<code>int([memory_format])</code>	<code>self.int()</code> is equivalent to <code>self.to(torch.int32)</code> .
<code>int_repr()</code>	Given a quantized Tensor, <code>self.int_repr()</code> returns a CPU Tensor with <code>uint8_t</code> as data type that stores the underlying <code>uint8_t</code> values of the given Tensor.
<code>inverse()</code>	See <code>torch.inverse()</code>
<code>ipu([device, non_blocking, memory_format])</code>	Returns a copy of this object in IPU memory.
<code>is_coalesced()</code>	Returns True if <code>self</code> is a sparse COO tensor that is coalesced, False otherwise.
<code>is_complex()</code>	Returns True if the data type of <code>self</code> is a complex data type.
<code>is_conj()</code>	Returns True if the conjugate bit of <code>self</code> is set to true.

continues on next page

Table 22 – continued from previous page

<code>is_contiguous([memory_format])</code>	Returns True if <code>self</code> tensor is contiguous in memory in the order specified by memory format.
<code>is_distributed</code>	
<code>is_floating_point()</code>	Returns True if the data type of <code>self</code> is a floating point data type.
<code>is_inference()</code>	See <code>torch.is_inference()</code>
<code>is_neg()</code>	Returns True if the negative bit of <code>self</code> is set to true.
<code>is_nonzero</code>	
<code>is_pinned</code>	Returns true if this tensor resides in pinned memory.
<code>is_same_size</code>	
<code>is_set_to(tensor)</code>	Returns True if both tensors are pointing to the exact same memory (same storage, offset, size and stride).
<code>is_shared()</code>	Checks if tensor is in shared memory.
<code>is_signed()</code>	Returns True if the data type of <code>self</code> is a signed data type.
<code>isclose(other[, rtol, atol, equal_nan])</code>	See <code>torch.isclose()</code>
<code>isfinite()</code>	See <code>torch.isfinite()</code>
<code>isinf()</code>	See <code>torch.isinf()</code>
<code>isnan()</code>	See <code>torch.isnan()</code>
<code>isneginf()</code>	See <code>torch.isneginf()</code>
<code>isposinf()</code>	See <code>torch.isposinf()</code>
<code>isreal()</code>	See <code>torch.isreal()</code>
<code>istft(n_fft[, hop_length, win_length, ...])</code>	See <code>torch.istft()</code>
<code>item()</code>	Returns the value of this tensor as a standard Python number.
<code>kron(other)</code>	See <code>torch.kron()</code>
<code>kthvalue(k[, dim, keepdim])</code>	See <code>torch.kthvalue()</code>
<code>lcm(other)</code>	See <code>torch.lcm()</code>
<code>lcm_(other)</code>	In-place version of <code>lcm()</code>
<code>ldexp(other)</code>	See <code>torch.ldexp()</code>
<code>ldexp_(other)</code>	In-place version of <code>ldexp()</code>
<code>le(other)</code>	See <code>torch.le()</code> .
<code>le_(other)</code>	In-place version of <code>le()</code> .
<code>lerp(end, weight)</code>	See <code>torch.lerp()</code>
<code>lerp_(end, weight)</code>	In-place version of <code>lerp()</code>
<code>less</code>	<code>lt(other) -> Tensor</code>
<code>less_(other)</code>	In-place version of <code>less()</code> .
<code>less_equal(other)</code>	See <code>torch.less_equal()</code> .
<code>less_equal_(other)</code>	In-place version of <code>less_equal()</code> .
<code>lgamma()</code>	See <code>torch.lgamma()</code>
<code>lgamma_()</code>	In-place version of <code>lgamma()</code>
<code>log()</code>	See <code>torch.log()</code>
<code>log10()</code>	See <code>torch.log10()</code>
<code>log10_(other)</code>	In-place version of <code>log10()</code>
<code>log1p()</code>	See <code>torch.log1p()</code>
<code>log1p_(other)</code>	In-place version of <code>log1p()</code>
<code>log2()</code>	See <code>torch.log2()</code>
<code>log2_(other)</code>	In-place version of <code>log2()</code>

continues on next page

Table 22 – continued from previous page

<code>log_()</code>	In-place version of <code>log()</code>
<code>log_normal_([mean, std, generator])</code>	Fills <code>self</code> tensor with numbers samples from the log-normal distribution parameterized by the given mean μ and standard deviation σ .
<code>log_softmax</code>	
<code>logaddexp(other)</code>	See <code>torch.logaddexp()</code>
<code>logaddexp2(other)</code>	See <code>torch.logaddexp2()</code>
<code>logcumsumexp(dim)</code>	See <code>torch.logcumsumexp()</code>
<code>logdet()</code>	See <code>torch.logdet()</code>
<code>logical_and()</code>	See <code>torch.logical_and()</code>
<code>logical_and_()</code>	In-place version of <code>logical_and()</code>
<code>logical_not()</code>	See <code>torch.logical_not()</code>
<code>logical_not_()</code>	In-place version of <code>logical_not()</code>
<code>logical_or()</code>	See <code>torch.logical_or()</code>
<code>logical_or_()</code>	In-place version of <code>logical_or()</code>
<code>logical_xor()</code>	See <code>torch.logical_xor()</code>
<code>logical_xor_()</code>	In-place version of <code>logical_xor()</code>
<code>logit()</code>	See <code>torch.logit()</code>
<code>logit_()</code>	In-place version of <code>logit()</code>
<code>logsumexp(dim[, keepdim])</code>	See <code>torch.logsumexp()</code>
<code>long([memory_format])</code>	<code>self.long()</code> is equivalent to <code>self.to(torch.int64)</code> .
<code>lstsq(other)</code>	
<code>lt(other)</code>	See <code>torch.lt()</code> .
<code>lt_(other)</code>	In-place version of <code>lt()</code> .
<code>lu([pivot, get_infos])</code>	See <code>torch.lu()</code>
<code>lu_solve(LU_data, LU_pivots)</code>	See <code>torch.lu_solve()</code>
<code>map2_</code>	
<code>map_(tensor, callable)</code>	Applies <code>callable</code> for each element in <code>self</code> tensor and the given <code>tensor</code> and stores the results in <code>self</code> tensor.
<code>masked_fill(mask, value)</code>	Out-of-place version of <code>torch.Tensor.masked_fill_()</code>
<code>masked_fill_(mask, value)</code>	Fills elements of <code>self</code> tensor with <code>value</code> where <code>mask</code> is True.
<code>masked_scatter(mask, tensor)</code>	Out-of-place version of <code>torch.Tensor.masked_scatter_()</code>
<code>masked_scatter_(mask, source)</code>	Copies elements from <code>source</code> into <code>self</code> tensor at positions where the <code>mask</code> is True.
<code>masked_select(mask)</code>	See <code>torch.masked_select()</code>
<code>materialize(shape[, device, dtype])</code>	Create a Parameter with the same properties of the uninitialized one.
<code>matmul(tensor2)</code>	See <code>torch.matmul()</code>
<code>matrix_exp()</code>	See <code>torch.matrix_exp()</code>

continues on next page

Table 22 – continued from previous page

`matrix_power(n)`

Note: `matrix_power()` is deprecated, use `torch.linalg.matrix_power()` instead.

<code>max([dim, keepdim])</code>	See <code>torch.max()</code>
<code>maximum(other)</code>	See <code>torch.maximum()</code>
<code>mean([dim, keepdim, dtype])</code>	See <code>torch.mean()</code>
<code>median([dim, keepdim])</code>	See <code>torch.median()</code>
<code>min([dim, keepdim])</code>	See <code>torch.min()</code>
<code>minimum(other)</code>	See <code>torch.minimum()</code>
<code>mm(mat2)</code>	See <code>torch.mm()</code>
<code>mode([dim, keepdim])</code>	See <code>torch.mode()</code>
<code>moveaxis(source, destination)</code>	See <code>torch.moveaxis()</code>
<code>movedim(source, destination)</code>	See <code>torch.movedim()</code>
<code>msort()</code>	See <code>torch.msort()</code>
<code>mul(value)</code>	See <code>torch.mul()</code> .
<code>mul_(value)</code>	In-place version of <code>mul()</code> .
<code>multinomial(num_samples[, replacement, ...])</code>	See <code>torch.multinomial()</code>
<code>multiply(value)</code>	See <code>torch.multiply()</code> .
<code>multiply_(value)</code>	In-place version of <code>multiply()</code> .
<code>mv(vec)</code>	See <code>torch.mv()</code>
<code>mvlgamma(p)</code>	See <code>torch.mvlgamma()</code>
<code>mvlgamma_(p)</code>	In-place version of <code>mvlgamma()</code>
<code>nan_to_num([nan, posinf, neginf])</code>	See <code>torch.nan_to_num()</code> .
<code>nan_to_num_([nan, posinf, neginf])</code>	In-place version of <code>nan_to_num()</code> .
<code>nanmean([dim, keepdim, dtype])</code>	See <code>torch.nanmean()</code>
<code>nanmedian([dim, keepdim])</code>	See <code>torch.nanmedian()</code>
<code>nanquantile(q[, dim, keepdim, interpolation])</code>	See <code>torch.nanquantile()</code>
<code>nansum([dim, keepdim, dtype])</code>	See <code>torch.nansum()</code>
<code>narrow(dimension, start, length)</code>	See <code>torch.narrow()</code> .
<code>narrow_copy(dimension, start, length)</code>	See <code>torch.narrow_copy()</code> .
<code>ndimension()</code>	Alias for <code>dim()</code>
<code>ne(other)</code>	See <code>torch.ne()</code> .
<code>ne_(other)</code>	In-place version of <code>ne()</code> .
<code>neg()</code>	See <code>torch.neg()</code>
<code>neg_()</code>	In-place version of <code>neg()</code>
<code>negative()</code>	See <code>torch.negative()</code>
<code>negative_()</code>	In-place version of <code>negative()</code>
<code>nelement()</code>	Alias for <code>numel()</code>
<code>new</code>	
<code>new_empty(size, *[, dtype, device, ...])</code>	Returns a Tensor of size <code>size</code> filled with uninitialized data.
<code>new_empty_strided(size, stride[, dtype, ...])</code>	Returns a Tensor of size <code>size</code> and strides <code>stride</code> filled with uninitialized data.
<code>new_full(size, fill_value, *[, dtype, ...])</code>	Returns a Tensor of size <code>size</code> filled with <code>fill_value</code> .
<code>new_ones(size, *[, dtype, device, ...])</code>	Returns a Tensor of size <code>size</code> filled with 1.
<code>new_tensor(data, *[, dtype, device, ...])</code>	Returns a new Tensor with <code>data</code> as the tensor data.

continues on next page

Table 22 – continued from previous page

<code>new_zeros(size, *[..., dtype, device, ...])</code>	Returns a Tensor of size <code>size</code> filled with <code>0</code> .
<code>nextafter(other)</code>	See <code>torch.nextafter()</code>
<code>nextafter_(other)</code>	In-place version of <code>nextafter()</code>
<code>nonzero()</code>	See <code>torch.nonzero()</code>
<code>norm([p, dim, keepdim, dtype])</code>	See <code>torch.norm()</code>
<code>normal_([mean, std, generator])</code>	Fills <code>self</code> tensor with elements samples from the normal distribution parameterized by <code>mean</code> and <code>std</code> .
<code>not_equal(other)</code>	See <code>torch.not_equal()</code> .
<code>not_equal_(other)</code>	In-place version of <code>not_equal()</code> .
<code>numel()</code>	See <code>torch.numel()</code>
<code>numpy(*[..., force])</code>	Returns the tensor as a NumPy ndarray.
<code>orgqr(input2)</code>	See <code>torch.orgqr()</code>
<code>ormqr(input2, input3[, left, transpose])</code>	See <code>torch.ormqr()</code>
<code>outer(vec2)</code>	See <code>torch.outer()</code> .
<code>permute(*dims)</code>	See <code>torch.permute()</code>
<code>pin_memory()</code>	Copies the tensor to pinned memory, if it's not already pinned.
<code>pinverse()</code>	See <code>torch.pinverse()</code>
<code>polygamma(n)</code>	See <code>torch.polygamma()</code>
<code>polygamma_(n)</code>	In-place version of <code>polygamma()</code>
<code>positive()</code>	See <code>torch.positive()</code>
<code>pow(exponent)</code>	See <code>torch.pow()</code>
<code>pow_(exponent)</code>	In-place version of <code>pow()</code>
<code>prelu</code>	
<code>prod([dim, keepdim, dtype])</code>	See <code>torch.prod()</code>
<code>put(input, index, source[, accumulate])</code>	Out-of-place version of <code>torch.Tensor.put_()</code> .
<code>put_(index, source[, accumulate])</code>	Copies the elements from <code>source</code> into the positions specified by <code>index</code> .
<code>q_per_channel_axis()</code>	Given a Tensor quantized by linear (affine) per-channel quantization, returns the index of dimension on which per-channel quantization is applied.
<code>q_per_channel_scales()</code>	Given a Tensor quantized by linear (affine) per-channel quantization, returns a Tensor of scales of the underlying quantizer.
<code>q_per_channel_zero_points()</code>	Given a Tensor quantized by linear (affine) per-channel quantization, returns a tensor of zero_points of the underlying quantizer.
<code>q_scale()</code>	Given a Tensor quantized by linear(affine) quantization, returns the scale of the underlying quantizer().
<code>q_zero_point()</code>	Given a Tensor quantized by linear(affine) quantization, returns the zero_point of the underlying quantizer().
<code>qr([some])</code>	See <code>torch.qr()</code>
<code>qscheme()</code>	Returns the quantization scheme of a given QTensor.
<code>quantile(q[, dim, keepdim, interpolation])</code>	See <code>torch.quantile()</code>
<code>rad2deg()</code>	See <code>torch.rad2deg()</code>
<code>rad2deg_(*)</code>	In-place version of <code>rad2deg()</code>
<code>random_([from, to, generator])</code>	Fills <code>self</code> tensor with numbers sampled from the discrete uniform distribution over <code>[from, to - 1]</code> .
<code>ravel()</code>	see <code>torch.ravel()</code>

continues on next page

Table 22 – continued from previous page

<code>reciprocal()</code>	See <code>torch.reciprocal()</code>
<code>reciprocal_()</code>	In-place version of <code>reciprocal()</code>
<code>record_stream(stream)</code>	Ensures that the tensor memory is not reused for another tensor until all current work queued on <code>stream</code> are complete.
<code>refine_names(*names)</code>	Refines the dimension names of <code>self</code> according to <code>names</code> .
<code>register_hook(hook)</code>	Registers a backward hook.
<code>reinforce(reward)</code>	
<code>relu</code>	
<code>relu_</code>	
<code>remainder(divisor)</code>	See <code>torch.remainder()</code>
<code>remainder_(divisor)</code>	In-place version of <code>remainder()</code>
<code>rename(*names, **rename_map)</code>	Renames dimension names of <code>self</code> .
<code>rename_(*names, **rename_map)</code>	In-place version of <code>rename()</code> .
<code>renorm(p, dim, maxnorm)</code>	See <code>torch.renorm()</code>
<code>renorm_(p, dim, maxnorm)</code>	In-place version of <code>renorm()</code>
<code>repeat(*sizes)</code>	Repeats this tensor along the specified dimensions.
<code>repeat_interleave(repeats[, dim, output_size])</code>	See <code>torch.repeat_interleave()</code> .
<code>requires_grad_([requires_grad])</code>	Change if autograd should record operations on this tensor: sets this tensor's <code>requires_grad</code> attribute in-place.
<code>reshape(*shape)</code>	Returns a tensor with the same data and number of elements as <code>self</code> but with the specified shape.
<code>reshape_as(other)</code>	Returns this tensor as the same shape as <code>other</code> .
<code>resize(*sizes)</code>	
<code>resize_(*sizes[, memory_format])</code>	Resizes <code>self</code> tensor to the specified size.
<code>resize_as(tensor)</code>	
<code>resize_as_(tensor[, memory_format])</code>	Resizes the <code>self</code> tensor to be the same size as the specified <code>tensor</code> .
<code>resize_as_sparse_</code>	
<code>resolve_conj()</code>	See <code>torch.resolve_conj()</code>
<code>resolve_neg()</code>	See <code>torch.resolve_neg()</code>
<code>retain_grad()</code>	Enables this Tensor to have their grad populated during <code>backward()</code> .
<code>roll(shifts, dims)</code>	See <code>torch.roll()</code>
<code>rot90(k, dims)</code>	See <code>torch.rot90()</code>
<code>round([decimals])</code>	See <code>torch.round()</code>
<code>round_([decimals])</code>	In-place version of <code>round()</code>
<code>row_indices</code>	
<code>rsqrt()</code>	See <code>torch.rsqrt()</code>
<code>rsqrt_()</code>	In-place version of <code>rsqrt()</code>
<code>scatter(dim, index, src)</code>	Out-of-place version of <code>torch.Tensor.scatter_()</code>

continues on next page

Table 22 – continued from previous page

<code>scatter_(dim, index, src[, reduce])</code>	Writes all values from the tensor <code>src</code> into <code>self</code> at the indices specified in the <code>index</code> tensor.
<code>scatter_add(dim, index, src)</code>	Out-of-place version of <code>torch.Tensor.scatter_()</code> .
<code>scatter_add_(dim, index, src)</code>	Adds all values from the tensor <code>src</code> into <code>self</code> at the indices specified in the <code>index</code> tensor in a similar fashion as <code>scatter_()</code> .
<code>scatter_reduce(dim, index, src, reduce, *[...,])</code>	Out-of-place version of <code>torch.Tensor.scatter_reduce_()</code> .
<code>scatter_reduce_(dim, index, src, reduce, *)</code>	Reduces all values from the <code>src</code> tensor to the indices specified in the <code>index</code> tensor in the <code>self</code> tensor using the applied reduction defined via the <code>reduce</code> argument ("sum", "prod", "mean", "amax", "amin").
<code>select(dim, index)</code>	See <code>torch.select()</code>
<code>select_scatter(src, dim, index)</code>	See <code>torch.select_scatter()</code>
<code>set_([source, storage_offset, size, stride])</code>	Sets the underlying storage, size, and strides.
<code>sgn()</code>	See <code>torch.sgn()</code>
<code>sgn_()</code>	In-place version of <code>sgn()</code>
<code>share_memory_()</code>	Moves the underlying storage to shared memory.
<code>short([memory_format])</code>	<code>self.short()</code> is equivalent to <code>self.to(torch.int16)</code> .
<code>sigmoid()</code>	See <code>torch.sigmoid()</code>
<code>sigmoid_()</code>	In-place version of <code>sigmoid()</code>
<code>sign()</code>	See <code>torch.sign()</code>
<code>sign_()</code>	In-place version of <code>sign()</code>
<code>signbit()</code>	See <code>torch.signbit()</code>
<code>sin()</code>	See <code>torch.sin()</code>
<code>sin_()</code>	In-place version of <code>sin()</code>
<code>sinc()</code>	See <code>torch.sinc()</code>
<code>sinc_()</code>	In-place version of <code>sinc()</code>
<code>sinh()</code>	See <code>torch.sinh()</code>
<code>sinh_()</code>	In-place version of <code>sinh()</code>
<code>size([dim])</code>	Returns the size of the <code>self</code> tensor.
<code>slice_scatter(src[, dim, start, end, step])</code>	See <code>torch.slice_scatter()</code>
<code>slogdet()</code>	See <code>torch.slogdet()</code>
<code>smm(mat)</code>	See <code>torch.smm()</code>
<code>softmax(dim)</code>	Alias for <code>torch.nn.functional.softmax()</code> .
<code>solve(other)</code>	
<code>sort([dim, descending])</code>	See <code>torch.sort()</code>
<code>sparse_dim()</code>	Return the number of sparse dimensions in a sparse tensor <code>self</code> .
<code>sparse_mask(mask)</code>	Returns a new sparse tensor with values from a strided tensor <code>self</code> filtered by the indices of the sparse tensor <code>mask</code> .
<code>sparse_resize_(size, sparse_dim, dense_dim)</code>	Resizes <code>self</code> sparse tensor to the desired size and the number of sparse and dense dimensions.
<code>sparse_resize_and_clear_(size, sparse_dim, ...)</code>	Removes all specified elements from a sparse tensor <code>self</code> and resizes <code>self</code> to the desired size and the number of sparse and dense dimensions.
<code>split(split_size[, dim])</code>	See <code>torch.split()</code>

continues on next page

Table 22 – continued from previous page

split_with_sizes

sqrt()	See <code>torch.sqrt()</code>
sqrt_()	In-place version of <code>sqrt()</code>
square()	See <code>torch.square()</code>
square_()	In-place version of <code>square()</code>
squeeze([dim])	See <code>torch.squeeze()</code>
squeeze_([dim])	In-place version of <code>squeeze()</code>
sspaddmm(mat1, mat2, *[beta, alpha])	See <code>torch.sspaddmm()</code>
std([dim, correction, keepdim])	See <code>torch.std()</code>
stft(n_fft[, hop_length, win_length, ...])	See <code>torch.stft()</code>
storage()	Returns the underlying <code>TypedStorage</code> .
storage_offset()	Returns <code>self</code> tensor's offset in the underlying storage in terms of number of storage elements (not bytes).
storage_type()	Returns the type of the underlying storage.
stride(dim)	Returns the stride of <code>self</code> tensor.
sub(other, *[alpha])	See <code>torch.sub()</code> .
sub_(other, *[alpha])	In-place version of <code>sub()</code>
subtract(other, *[alpha])	See <code>torch.subtract()</code> .
subtract_(other, *[alpha])	In-place version of <code>subtract()</code> .
sum([dim, keepdim, dtype])	See <code>torch.sum()</code>
sum_to_size(*size)	Sum this tensor to <code>size</code> .
svd([some, compute_uv])	See <code>torch.svd()</code>
swapaxes(axis0, axis1)	See <code>torch.swapaxes()</code>
swapaxes_(axis0, axis1)	In-place version of <code>swapaxes()</code>
swapdims(dim0, dim1)	See <code>torch.swapdims()</code>
swapdims_(dim0, dim1)	In-place version of <code>swapdims()</code>
symeig([eigenvectors])	
t()	See <code>torch.t()</code>
t_()	In-place version of <code>t()</code>
take(indices)	See <code>torch.take()</code>
take_along_dim(indices, dim)	See <code>torch.take_along_dim()</code>
tan()	See <code>torch.tan()</code>
tan_()	In-place version of <code>tan()</code>
tanh()	See <code>torch.tanh()</code>
tanh_()	In-place version of <code>tanh()</code>
tensor_split(indices_or_sections[, dim])	See <code>torch.tensor_split()</code>
tile(*reps)	See <code>torch.tile()</code>
to(*args, **kwargs)	Performs Tensor <code>dtype</code> and/or device conversion.
to_dense()	Creates a strided copy of <code>self</code> if <code>self</code> is not a strided tensor, otherwise returns <code>self</code> .
to_mkldnn()	Returns a copy of the tensor in <code>torch.mkldnn</code> layout.
to_padded_tensor(padding[, output_size])	See <code>to_padded_tensor()</code>
to_sparse(sparseDims)	Returns a sparse copy of the tensor.
to_sparse_bsc(blocksize, dense_dim)	Convert a tensor to a block sparse column (BSC) storage format of given blocksize.
to_sparse_bsr(blocksize, dense_dim)	Convert a tensor to a block sparse row (BSR) storage format of given blocksize.

continues on next page

Table 22 – continued from previous page

<code>to_sparse_coo()</code>	Convert a tensor to coordinate format.
<code>to_sparse_csc()</code>	Convert a tensor to compressed column storage (CSC) format.
<code>to_sparse_csr([dense_dim])</code>	Convert a tensor to compressed row storage format (CSR).
<code>tolist()</code>	Returns the tensor as a (nested) list.
<code>topk(k[, dim, largest, sorted])</code>	See <code>torch.topk()</code>
<code>trace()</code>	See <code>torch.trace()</code>
<code>transpose(dim0, dim1)</code>	See <code>torch.transpose()</code>
<code>transpose_(dim0, dim1)</code>	In-place version of <code>transpose()</code>
<code>triangular_solve(A[, upper, transpose, ...])</code>	See <code>torch.triangular_solve()</code>
<code>tril([diagonal])</code>	See <code>torch.tril()</code>
<code>tril_([diagonal])</code>	In-place version of <code>tril()</code>
<code>triu([diagonal])</code>	See <code>torch.triu()</code>
<code>triu_([diagonal])</code>	In-place version of <code>triu()</code>
<code>true_divide(value)</code>	See <code>torch.true_divide()</code>
<code>true_divide_(value)</code>	In-place version of <code>true_divide_()</code>
<code>trunc()</code>	See <code>torch.trunc()</code>
<code>trunc_()</code>	In-place version of <code>trunc()</code>
<code>type([dtype, non_blocking])</code>	Returns the type if <code>dtype</code> is not provided, else casts this object to the specified type.
<code>type_as(tensor)</code>	Returns this tensor cast to the type of the given tensor.
<code>unbind([dim])</code>	See <code>torch.unbind()</code>
<code>unflatten(dim, sizes)</code>	See <code>torch.unflatten()</code> .
<code>unfold(dimension, size, step)</code>	Returns a view of the original tensor which contains all slices of size <code>size</code> from <code>self</code> tensor in the dimension <code>dimension</code> .
<code>uniform_([from, to])</code>	Fills <code>self</code> tensor with numbers sampled from the continuous uniform distribution:
<code>unique([sorted, return_inverse, ...])</code>	Returns the unique elements of the input tensor.
<code>unique_consecutive([return_inverse, ...])</code>	Eliminates all but the first element from every consecutive group of equivalent elements.
<code>unsafe_chunk(chunks[, dim])</code>	See <code>torch.unsafe_chunk()</code>
<code>unsafe_split(split_size[, dim])</code>	See <code>torch.unsafe_split()</code>
<code>unsafe_split_with_sizes</code>	
<code>unsqueeze(dim)</code>	See <code>torch.unsqueeze()</code>
<code>unsqueeze_(dim)</code>	In-place version of <code>unsqueeze()</code>
<code>untyped_storage()</code>	Returns the underlying <code>UntypedStorage</code> .
<code>values()</code>	Return the values tensor of a sparse COO tensor.
<code>var([dim, correction, keepdim])</code>	See <code>torch.var()</code>
<code>vdot(other)</code>	See <code>torch.vdot()</code>
<code>view(*shape)</code>	Returns a new tensor with the same data as the <code>self</code> tensor but of a different <code>shape</code> .
<code>view_as(other)</code>	View this tensor as the same size as <code>other</code> .
<code>vsplit(split_size_or_sections)</code>	See <code>torch.vsplit()</code>
<code>where(condition, y)</code>	<code>self.where(condition, y)</code> is equivalent to <code>torch.where(condition, self, y)</code> .
<code>xlogy(other)</code>	See <code>torch.xlogy()</code>
<code>xlogy_(other)</code>	In-place version of <code>xlogy()</code>
<code>xpu([device, non_blocking, memory_format])</code>	Returns a copy of this object in XPU memory.

continues on next page

Table 22 – continued from previous page

<code>zero_()</code>	Fills <code>self</code> tensor with zeros.
----------------------	--

Attributes

<code>H</code>	Returns a view of a matrix (2-D tensor) conjugated and transposed.
<code>T</code>	Returns a view of this tensor with its dimensions reversed.
<code>data</code>	
<code>device</code>	Is the <code>torch.device</code> where this Tensor is.
<code>dtype</code>	
<code>grad</code>	This attribute is <code>None</code> by default and becomes a Tensor the first time a call to <code>backward()</code> computes gradients for <code>self</code> .
<code>grad_fn</code>	
<code>imag</code>	Returns a new tensor containing imaginary values of the <code>self</code> tensor.
<code>is_cpu</code>	Is <code>True</code> if the Tensor is stored on the CPU, <code>False</code> otherwise.
<code>is_cuda</code>	Is <code>True</code> if the Tensor is stored on the GPU, <code>False</code> otherwise.
<code>is_ipu</code>	Is <code>True</code> if the Tensor is stored on the IPU, <code>False</code> otherwise.
<code>is_leaf</code>	All Tensors that have <code>requires_grad</code> which is <code>False</code> will be leaf Tensors by convention.
<code>is_meta</code>	Is <code>True</code> if the Tensor is a meta tensor, <code>False</code> otherwise.
<code>is_mkldnn</code>	
<code>is_mps</code>	Is <code>True</code> if the Tensor is stored on the MPS device, <code>False</code> otherwise.
<code>is_nested</code>	
<code>is_ort</code>	
<code>is_quantized</code>	Is <code>True</code> if the Tensor is quantized, <code>False</code> otherwise.
<code>is_sparse</code>	Is <code>True</code> if the Tensor uses sparse storage layout, <code>False</code> otherwise.
<code>is_sparse_csr</code>	Is <code>True</code> if the Tensor uses sparse CSR storage layout, <code>False</code> otherwise.
<code>is_vulkan</code>	
<code>is_xpu</code>	Is <code>True</code> if the Tensor is stored on the XPU, <code>False</code> otherwise.
<code>layout</code>	

continues on next page

Table 23 – continued from previous page

mH	Accessing this property is equivalent to calling <code>adjoint()</code> .
mT	Returns a view of this tensor with the last two dimensions transposed.
name	
names	Stores names for each of this tensor's dimensions.
ndim	Alias for <code>dim()</code>
output_nr	
real	Returns a new tensor containing real values of the <code>self</code> tensor for a complex-valued input tensor.
requires_grad	Is <code>True</code> if gradients need to be computed for this Tensor, <code>False</code> otherwise.
retains_grad	Is <code>True</code> if this Tensor is non-leaf and its grad is enabled to be populated during <code>backward()</code> , <code>False</code> otherwise.
shape	
volatile	

property `is_leaf: bool`

All Tensors that have `requires_grad` which is `False` will be leaf Tensors by convention.

For Tensors that have `requires_grad` which is `True`, they will be leaf Tensors if they were created by the user. This means that they are not the result of an operation and so `grad_fn` is `None`.

Only leaf Tensors will have their `grad` populated during a call to `backward()`. To get `grad` populated for non-leaf Tensors, you can use `retain_grad()`.

Example:

```
>>> a = torch.rand(10, requires_grad=True)
>>> a.is_leaf
True
>>> b = torch.rand(10, requires_grad=True).cuda()
>>> b.is_leaf
False
# b was created by the operation that cast a cpu Tensor into a cuda Tensor
>>> c = torch.rand(10, requires_grad=True) + 2
>>> c.is_leaf
False
# c was created by the addition operation
>>> d = torch.rand(10).cuda()
>>> d.is_leaf
True
# d does not require gradients and so has no operation creating it (that is_
# tracked by the autograd engine)
>>> e = torch.rand(10).cuda().requires_grad_()
>>> e.is_leaf
True
# e requires gradients and has no operations creating it
```

(continues on next page)

(continued from previous page)

```
>>> f = torch.rand(10, requires_grad=True, device="cuda")
>>> f.is_leaf
True
# f requires grad, has no operation creating it
```

materialize(shape, device=None, dtype=None)

Create a Parameter with the same properties of the uninitialized one. Given a shape, it materializes a parameter in the same device and with the same *dtype* as the current one or the specified ones in the arguments.

Parameters

- **shape** (*Tuple[int, ...]*) – (tuple): the shape for the materialized tensor.
- **device** (*torch.device*) – the desired device of the parameters and buffers in this module. Optional.
- **dtype** (*torch.dtype*) – the desired floating point type of the floating point parameters and buffers in this module. Optional.

Return type

None

share_memory_()

Moves the underlying storage to shared memory.

This is a no-op if the underlying storage is already in shared memory and for CUDA tensors. Tensors in shared memory cannot be resized.

Return type*UninitializedParameter***pytorch_pfn_extras.nn.modules.lazy_linear****Classes**

<i>pytorch_pfn_extras.nn.modules.lazy_linear.LazyInitializationMixin(...)</i>	A mixin for modules that lazily initialize buffers and parameters.
<i>pytorch_pfn_extras.nn.modules.lazy_linear.LazyLinear(...)</i>	Linear module with lazy weight initialization.
<i>pytorch_pfn_extras.nn.modules.lazy_linear.UninitializedParameter(...)</i>	

pytorch_pfn_extras.nn.modules.lazy_linear.LazyInitializationMixin

```
class pytorch_pfn_extras.nn.modules.lazy_linear.LazyInitializationMixin(*args, **kwargs)
Bases: object
```

A mixin for modules that lazily initialize buffers and parameters.

Unlike regular modules, subclasses of this module can initialize buffers and parameters outside of the constructor (`__init__`). This allows you to, for example, initialize parameters in `forward` method to determine the shape of the weight based on the initial input.

Be sure to run “dummy” forward once to initialize all parameters that should be trained, before passing `module.parameters()` to an optimizer; otherwise weights initialized after `module.parameters()` (e.g., in `forward` function) will never be trained.

Note that lazy modules cannot validate if the shape is correct during deserialization. Also note that the initial weights may become different from the original (non-lazy) module even if the random seed is manually configured, as the order of initialization is different from the original one; especially, `module.cuda()` may cause the initialization to run on a GPU.

The default value of lazy buffers and parameters are `torch.Tensor([])` and `UninitializedParameter()`, respectively.

Methods

`__init__(*args, **kwargs)`

`state_dict(*args, **kwargs)` Returns a dictionary containing a whole state of the module.

Attributes

`lazy_buffer_names`

`lazy_parameter_names`

`lazy_parameters_determined` Returns if all lazy parameters are determined.

Parameters

- `args (Any)` –
- `kwargs (Any)` –

`__init__(*args, **kwargs)`

Parameters

- `self (Any)` –
- `args (Any)` –
- `kwargs (Any)` –

Return type

None

`lazy_buffer_names: Tuple[str, ...] = ()`

`lazy_parameter_names: Tuple[str, ...] = ()`

`property lazy_parameters_determined: bool`

Returns if all lazy parameters are determined.

Subclasses can perform parameters initialization after all lazy parameters are determined. Note that this may be called during `__init__`.

state_dict(*args, **kwargs)

Returns a dictionary containing a whole state of the module.

This function overrides the default behavior to exclude uninitialized parameter from serialization. This is needed because we need to discriminate lazy parameters (`UninitializedParameter()`) and initialized empty parameters (`torch.nn.Parameter(torch.Tensor())`) during deserialization.

See comments of `_lazy_load_hook` for details.

Parameters

- **self** (Any) –
- **args** (Any) –
- **kwargs** (Any) –

Return type

Dict[str, Any]

[pytorch_pfn_extras.nn.modules.lazy_linear.LazyLinear](#)

class `pytorch_pfn_extras.nn.modules.lazy_linear.LazyLinear(in_features, *args, **kwargs)`

Bases: `LazyInitializationMixin`, `Linear`

Linear module with lazy weight initialization.

When `in_features` is `None`, it is determined at the first time of the forward step.

Initializes internal Module state, shared by both `nn.Module` and `ScriptModule`.

Methods

<code>__init__(in_features, *args, **kwargs)</code>	Initializes internal Module state, shared by both <code>nn.Module</code> and <code>ScriptModule</code> .
<code>add_module(name, module)</code>	Adds a child module to the current module.
<code>apply(fn)</code>	Applies <code>fn</code> recursively to every submodule (as returned by <code>.children()</code>) as well as self.
<code>bfloat16()</code>	Casts all floating point parameters and buffers to <code>bfloat16</code> datatype.
<code>buffers([recurse])</code>	Returns an iterator over module buffers.
<code>children()</code>	Returns an iterator over immediate children modules.
<code>cpu()</code>	Moves all model parameters and buffers to the CPU.
<code>cuda([device])</code>	Moves all model parameters and buffers to the GPU.
<code>double()</code>	Casts all floating point parameters and buffers to <code>double</code> datatype.
<code>eval()</code>	Sets the module in evaluation mode.
<code>extra_repr()</code>	Set the extra representation of the module
<code>float()</code>	Casts all floating point parameters and buffers to <code>float</code> datatype.
<code>forward(input)</code>	Defines the computation performed at every call.
<code>get_buffer(target)</code>	Returns the buffer given by <code>target</code> if it exists, otherwise throws an error.

continues on next page

Table 24 – continued from previous page

<code>get_extra_state()</code>	Returns any extra state to include in the module's <code>state_dict</code> .
<code>get_parameter(target)</code>	Returns the parameter given by <code>target</code> if it exists, otherwise throws an error.
<code>get_submodule(target)</code>	Returns the submodule given by <code>target</code> if it exists, otherwise throws an error.
<code>half()</code>	Casts all floating point parameters and buffers to <code>half</code> datatype.
<code>ipu([device])</code>	Moves all model parameters and buffers to the IPU.
<code>load_state_dict(state_dict[, strict])</code>	Copies parameters and buffers from <code>state_dict</code> into this module and its descendants.
<code>modules()</code>	Returns an iterator over all modules in the network.
<code>named_buffers([prefix, recurse, ...])</code>	Returns an iterator over module buffers, yielding both the name of the buffer as well as the buffer itself.
<code>named_children()</code>	Returns an iterator over immediate children modules, yielding both the name of the module as well as the module itself.
<code>named_modules([memo, prefix, remove_duplicate])</code>	Returns an iterator over all modules in the network, yielding both the name of the module as well as the module itself.
<code>named_parameters([prefix, recurse, ...])</code>	Returns an iterator over module parameters, yielding both the name of the parameter as well as the parameter itself.
<code>parameters([recurse])</code>	Returns an iterator over module parameters.
<code>register_backward_hook(hook)</code>	Registers a backward hook on the module.
<code>register_buffer(name, tensor[, persistent])</code>	Adds a buffer to the module.
<code>register_forward_hook(hook, *[, prepend, ...])</code>	Registers a forward hook on the module.
<code>register_forward_pre_hook(hook, *[, ...])</code>	Registers a forward pre-hook on the module.
<code>register_full_backward_hook(hook[, prepend])</code>	Registers a backward hook on the module.
<code>register_full_backward_pre_hook(hook[, prepend])</code>	Registers a backward pre-hook on the module.
<code>register_load_state_dict_post_hook(hook)</code>	Registers a post hook to be run after module's <code>load_state_dict</code> is called.
<code>register_module(name, module)</code>	Alias for <code>add_module()</code> .
<code>register_parameter(name, param)</code>	Adds a parameter to the module.
<code>register_state_dict_pre_hook(hook)</code>	These hooks will be called with arguments: <code>self</code> , <code>prefix</code> , and <code>keep_vars</code> before calling <code>state_dict</code> on <code>self</code> .
<code>requires_grad_(requires_grad)</code>	Change if autograd should record operations on parameters in this module.
<code>reset_parameters()</code>	
<code>set_extra_state(state)</code>	This function is called from <code>load_state_dict()</code> to handle any extra state found within the <code>state_dict</code> . See <code>torch.Tensor.share_memory_()</code>
<code>share_memory()</code>	
<code>state_dict(*args, **kwargs)</code>	Returns a dictionary containing a whole state of the module.
<code>to(*args, **kwargs)</code>	Moves and/or casts the parameters and buffers.
<code>to_empty(*, device)</code>	Moves the parameters and buffers to the specified device without copying storage.

continues on next page

Table 24 – continued from previous page

<code>train([mode])</code>	Sets the module in training mode.
<code>type(dst_type)</code>	Casts all parameters and buffers to <code>dst_type</code> .
<code>xpu([device])</code>	Moves all model parameters and buffers to the XPU.
<code>zero_grad([set_to_none])</code>	Sets gradients of all model parameters to zero.

Attributes

<code>T_destination</code>	alias of TypeVar('T_destination', bound=Dict[str, Any])
<code>call_super_init</code>	
<code>dump_patches</code>	
<code>lazy_buffer_names</code>	
<code>lazy_parameter_names</code>	
<code>lazy_parameters_determined</code>	Returns if all lazy parameters are determined.

Parameters

- **in_features** (*Optional[int]*) –
- **args** (*Any*) –
- **kwargs** (*Any*) –

`__init__(in_features, *args, **kwargs)`

Initializes internal Module state, shared by both nn.Module and ScriptModule.

Parameters

- **in_features** (*Optional[int]*) –
- **args** (*Any*) –
- **kwargs** (*Any*) –

Return type

None

`forward(input)`

Defines the computation performed at every call.

Should be overridden by all subclasses.

Note: Although the recipe for forward pass needs to be defined within this function, one should call the Module instance afterwards instead of this since the former takes care of running the registered hooks while the latter silently ignores them.

Parameters

- **input** (*Tensor*) –

```

Return type  

Tensor

in_features: int  

lazy_parameter_names: Tuple[str, ...] = ('weight',)  

out_features: int  

reset_parameters()

Return type  

None

training: bool

weight: Tensor

```

pytorch_pfn_extras.nn.modules.lazy_linear.UninitializedParameter

```

class pytorch_pfn_extras.nn.modules.lazy_linear.UninitializedParameter(data=None,
                                                                     requires_grad=True)

Bases: Parameter

```

Methods

<code>__init__()</code>	
<code>abs()</code>	See <code>torch.abs()</code>
<code>abs_()</code>	In-place version of <code>abs()</code>
<code>absolute()</code>	Alias for <code>abs()</code>
<code>absolute_()</code>	In-place version of <code>absolute()</code> Alias for <code>abs_()</code>
<code>acos()</code>	See <code>torch.acos()</code>
<code>acos_()</code>	In-place version of <code>acos()</code>
<code>acosh()</code>	See <code>torch.acosh()</code>
<code>acosh_()</code>	In-place version of <code>acosh()</code>
<code>add(other, *[, alpha])</code>	Add a scalar or tensor to <code>self</code> tensor.
<code>add_(other, *[, alpha])</code>	In-place version of <code>add()</code>
<code>addbmm(batch1, batch2, *[, beta, alpha])</code>	See <code>torch.addbmm()</code>
<code>addbmm_(batch1, batch2, *[, beta, alpha])</code>	In-place version of <code>addbmm()</code>
<code>addcdim(tensor1, tensor2, *[, value])</code>	See <code>torch.addcdim()</code>
<code>addcdim_(tensor1, tensor2, *[, value])</code>	In-place version of <code>addcdim()</code>
<code>addcmul(tensor1, tensor2, *[, value])</code>	See <code>torch.addcmul()</code>
<code>addcmul_(tensor1, tensor2, *[, value])</code>	In-place version of <code>addcmul()</code>
<code>addmm(mat1, mat2, *[, beta, alpha])</code>	See <code>torch.addmm()</code>
<code>addmm_(mat1, mat2, *[, beta, alpha])</code>	In-place version of <code>addmm()</code>
<code>addmv(mat, vec, *[, beta, alpha])</code>	See <code>torch.addmv()</code>
<code>addmv_(mat, vec, *[, beta, alpha])</code>	In-place version of <code>addmv()</code>
<code>addr(vec1, vec2, *[, beta, alpha])</code>	See <code>torch.addr()</code>
<code>addr_(vec1, vec2, *[, beta, alpha])</code>	In-place version of <code>addr()</code>
<code>adjoint()</code>	Alias for <code>adjoint()</code>

continues on next page

Table 25 – continued from previous page

<code>align_as(other)</code>	Permutes the dimensions of the <code>self</code> tensor to match the dimension order in the <code>other</code> tensor, adding size-one dims for any new names.
<code>align_to(*names)</code>	Permutes the dimensions of the <code>self</code> tensor to match the order specified in <code>names</code> , adding size-one dims for any new names.
<code>all([dim, keepdim])</code>	See <code>torch.all()</code>
<code>allclose(other[, rtol, atol, equal_nan])</code>	See <code>torch.allclose()</code>
<code>amax([dim, keepdim])</code>	See <code>torch.amax()</code>
<code>amin([dim, keepdim])</code>	See <code>torch.amin()</code>
<code>aminmax(*[, dim, keepdim])</code>	See <code>torch.aminmax()</code>
<code>angle()</code>	See <code>torch.angle()</code>
<code>any([dim, keepdim])</code>	See <code>torch.any()</code>
<code>apply_(callable)</code>	Applies the function <code>callable</code> to each element in the tensor, replacing each element with the value returned by <code>callable</code> .
<code>arccos()</code>	See <code>torch.arccos()</code>
<code>arccos_()</code>	In-place version of <code>arccos()</code>
<code>arccosh</code>	<code>acosh() -> Tensor</code>
<code>arccosh_</code>	<code>acosh_() -> Tensor</code>
<code>arcsin()</code>	See <code>torch.arcsin()</code>
<code>arcsin_()</code>	In-place version of <code>arcsin()</code>
<code>arcsinh()</code>	See <code>torch.arcsinh()</code>
<code>arcsinh_()</code>	In-place version of <code>arcsinh()</code>
<code>arctan()</code>	See <code>torch.arctan()</code>
<code>arctan2(other)</code>	See <code>torch.arctan2()</code>
<code>arctan2_</code>	<code>atan2_(other) -> Tensor</code>
<code>arctan_()</code>	In-place version of <code>arctan()</code>
<code>arctanh()</code>	See <code>torch.arctanh()</code>
<code>arctanh_(other)</code>	In-place version of <code>arctanh()</code>
<code>argmax([dim, keepdim])</code>	See <code>torch.argmax()</code>
<code>argmin([dim, keepdim])</code>	See <code>torch.argmin()</code>
<code>argsort([dim, descending])</code>	See <code>torch.argsort()</code>
<code>argwhere()</code>	See <code>torch.argwhere()</code>
<code>as_strided(size, stride[, storage_offset])</code>	See <code>torch.as_strided()</code>
<code>as_strided_</code>	
<code>as_strided_scatter(src, size, stride[, ...])</code>	See <code>torch.as_strided_scatter()</code>
<code>as_subclass(cls)</code>	Makes a <code>cls</code> instance with the same data pointer as <code>self</code> .
<code>asin()</code>	See <code>torch.asin()</code>
<code>asin_()</code>	In-place version of <code>asin()</code>
<code>asinh()</code>	See <code>torch.asinh()</code>
<code>asinh_()</code>	In-place version of <code>asinh()</code>
<code>atan()</code>	See <code>torch.atan()</code>
<code>atan2(other)</code>	See <code>torch.atan2()</code>
<code>atan2_(other)</code>	In-place version of <code>atan2()</code>
<code>atan_()</code>	In-place version of <code>atan()</code>
<code>atanh()</code>	See <code>torch.atanh()</code>
<code>atanh_(other)</code>	In-place version of <code>atanh()</code>
<code>backward([gradient, retain_graph, ...])</code>	Computes the gradient of current tensor w.r.t.

continues on next page

Table 25 – continued from previous page

baddbmm(batch1, batch2, *[beta, alpha])	See <code>torch.baddbmm()</code>
baddbmm_(batch1, batch2, *[beta, alpha])	In-place version of <code>baddbmm()</code>
bernoulli(*[generator])	Returns a result tensor where each <code>result[i]</code> is independently sampled from Bernoulli(<code>self[i]</code>).
bernoulli_([p, generator])	Fills each location of <code>self</code> with an independent sample from Bernoulli(<code>p</code>).
bfloat16([memory_format])	<code>self.bfloat16()</code> is equivalent to <code>self.to(torch.bfloat16)</code> .
bincount([weights, minlength])	See <code>torch.bincount()</code>
bitwise_and()	See <code>torch.bitwise_and()</code>
bitwise_and_()	In-place version of <code>bitwise_and()</code>
bitwise_left_shift(other)	See <code>torch.bitwise_left_shift()</code>
bitwise_left_shift_(other)	In-place version of <code>bitwise_left_shift()</code>
bitwise_not()	See <code>torch.bitwise_not()</code>
bitwise_not_()	In-place version of <code>bitwise_not()</code>
bitwise_or()	See <code>torch.bitwise_or()</code>
bitwise_or_()	In-place version of <code>bitwise_or()</code>
bitwise_right_shift(other)	See <code>torch.bitwise_right_shift()</code>
bitwise_right_shift_(other)	In-place version of <code>bitwise_right_shift()</code>
bitwise_xor()	See <code>torch.bitwise_xor()</code>
bitwise_xor_()	In-place version of <code>bitwise_xor()</code>
bmm(batch2)	See <code>torch.bmm()</code>
bool([memory_format])	<code>self.bool()</code> is equivalent to <code>self.to(torch.bool)</code> .
broadcast_to(shape)	See <code>torch.broadcast_to()</code> .
byte([memory_format])	<code>self.byte()</code> is equivalent to <code>self.to(torch.uint8)</code> .
cauchy_([median, sigma, generator])	Fills the tensor with numbers drawn from the Cauchy distribution:
<hr/>	
ccol_indices	
cdouble([memory_format])	<code>self.cdouble()</code> is equivalent to <code>self.to(torch.complex128)</code> .
ceil()	See <code>torch.ceil()</code>
ceil_()	In-place version of <code>ceil()</code>
cfloat([memory_format])	<code>self.cfloat()</code> is equivalent to <code>self.to(torch.complex64)</code> .
chalf([memory_format])	<code>self.chalf()</code> is equivalent to <code>self.to(torch.complex32)</code> .
char([memory_format])	<code>self.char()</code> is equivalent to <code>self.to(torch.int8)</code> .
cholesky(upper)	See <code>torch.cholesky()</code>
cholesky_inverse(upper)	See <code>torch.cholesky_inverse()</code>
cholesky_solve(input2[, upper])	See <code>torch.cholesky_solve()</code>
chunk(chunks[, dim])	See <code>torch.chunk()</code>
clamp([min, max])	See <code>torch.clamp()</code>
clamp_([min, max])	In-place version of <code>clamp()</code>
clamp_max	
<hr/>	
clamp_max_	

continues on next page

Table 25 – continued from previous page

clamp_min	
clamp_min_	
clip([min, max])	Alias for <code>clamp()</code> .
clip_([min, max])	Alias for <code>clamp_()</code> .
clone(*[, memory_format])	See <code>torch.clone()</code>
coalesce()	Returns a coalesced copy of <code>self</code> if <code>self</code> is an uncoalesced tensor.
col_indices()	Returns the tensor containing the column indices of the <code>self</code> tensor when <code>self</code> is a sparse CSR tensor of layout <code>sparse_csr</code> .
conj()	See <code>torch.conj()</code>
conj_physical()	See <code>torch.conj_physical()</code>
conj_physical_()	In-place version of <code>conj_physical()</code>
contiguous([memory_format])	Returns a contiguous in memory tensor containing the same data as <code>self</code> tensor.
copy_(src[, non_blocking])	Copies the elements from <code>src</code> into <code>self</code> tensor and returns <code>self</code> .
copysign(other)	See <code>torch.copysign()</code>
copysign_(other)	In-place version of <code>copysign()</code>
corrcoef()	See <code>torch.corrcoef()</code>
cos()	See <code>torch.cos()</code>
cos_()	In-place version of <code>cos()</code>
cosh()	See <code>torch.cosh()</code>
cosh_()	In-place version of <code>cosh()</code>
count_nonzero([dim])	See <code>torch.count_nonzero()</code>
cov(*[, correction, fweights, aweights])	See <code>torch.cov()</code>
cpu([memory_format])	Returns a copy of this object in CPU memory.
cross(other[, dim])	See <code>torch.cross()</code>
crow_indices()	Returns the tensor containing the compressed row indices of the <code>self</code> tensor when <code>self</code> is a sparse CSR tensor of layout <code>sparse_csr</code> .
cuda([device, non_blocking, memory_format])	Returns a copy of this object in CUDA memory.
cummax(dim)	See <code>torch.cummax()</code>
cummin(dim)	See <code>torch.cummin()</code>
cumprod(dim[, dtype])	See <code>torch.cumprod()</code>
cumprod_(dim[, dtype])	In-place version of <code>cumprod()</code>
cumsum(dim[, dtype])	See <code>torch.cumsum()</code>
cumsum_(dim[, dtype])	In-place version of <code>cumsum()</code>
data_ptr()	Returns the address of the first element of <code>self</code> tensor.
deg2rad()	See <code>torch.deg2rad()</code>
deg2rad_()	In-place version of <code>deg2rad()</code>
dense_dim()	Return the number of dense dimensions in a sparse tensor <code>self</code> .
dequantize()	Given a quantized Tensor, dequantize it and return the dequantized float Tensor.
det()	See <code>torch.det()</code>
detach	Returns a new Tensor, detached from the current graph.

continues on next page

Table 25 – continued from previous page

<code>detach_</code>	Detaches the Tensor from the graph that created it, making it a leaf.
<code>diag([diagonal])</code>	See <code>torch.diag()</code>
<code>diag_embed([offset, dim1, dim2])</code>	See <code>torch.diag_embed()</code>
<code>diagflat([offset])</code>	See <code>torch.diagflat()</code>
<code>diagonal([offset, dim1, dim2])</code>	See <code>torch.diagonal()</code>
<code>diagonal_scatter(src[, offset, dim1, dim2])</code>	See <code>torch.diagonal_scatter()</code>
<code>diff([n, dim, prepend, append])</code>	See <code>torch.diff()</code>
<code>digamma()</code>	See <code>torch.digamma()</code>
<code>digamma_()</code>	In-place version of <code>digamma()</code>
<code>dim()</code>	Returns the number of dimensions of <code>self</code> tensor.
<code>dist(other[, p])</code>	See <code>torch.dist()</code>
<code>div(value, *[, rounding_mode])</code>	See <code>torch.div()</code>
<code>div_(value, *[, rounding_mode])</code>	In-place version of <code>div()</code>
<code>divide(value, *[, rounding_mode])</code>	See <code>torch.divide()</code>
<code>divide_(value, *[, rounding_mode])</code>	In-place version of <code>divide()</code>
<code>dot(other)</code>	See <code>torch.dot()</code>
<code>double([memory_format])</code>	<code>self.double()</code> is equivalent to <code>self.to(torch.float64)</code> .
<code>dsplit(split_size_or_sections)</code>	See <code>torch.dsplit()</code>
<code>eig([eigenvectors])</code>	
<code>element_size()</code>	Returns the size in bytes of an individual element.
<code>eq(other)</code>	See <code>torch.eq()</code>
<code>eq_(other)</code>	In-place version of <code>eq()</code>
<code>equal(other)</code>	See <code>torch.equal()</code>
<code>erf()</code>	See <code>torch.erf()</code>
<code>erf_() erfc()</code>	In-place version of <code>erf()</code>
<code>erfc_() erfcinv()</code>	See <code>torch.erfc()</code>
<code>erfcinv_() erfinv()</code>	In-place version of <code>erfcinv()</code>
<code>erfinv_() exp()</code>	See <code>torch.erfinv()</code>
<code>exp2()</code>	See <code>torch.exp()</code>
<code>exp2_() exp_()</code>	In-place version of <code>exp2()</code>
<code>exp_()</code>	In-place version of <code>exp()</code>
<code>expand(*sizes)</code>	Returns a new view of the <code>self</code> tensor with singleton dimensions expanded to a larger size.
<code>expand_as(other)</code>	Expand this tensor to the same size as <code>other</code> .
<code>expm1()</code>	See <code>torch.expm1()</code>
<code>expm1_()</code>	In-place version of <code>expm1()</code>
<code>exponential_([lambda, generator])</code>	Fills <code>self</code> tensor with elements drawn from the exponential distribution:
<code>fill_(value)</code>	Fills <code>self</code> tensor with the specified value.
<code>fill_diagonal_(fill_value[, wrap])</code>	Fill the main diagonal of a tensor that has at least 2-dimensions.
<code>fix()</code>	See <code>torch.fix()</code> .
<code>fix_()</code>	In-place version of <code>fix()</code>
<code>flatten([start_dim, end_dim])</code>	See <code>torch.flatten()</code>
<code>flip(dims)</code>	See <code>torch.flip()</code>

continues on next page

Table 25 – continued from previous page

<code>fliplr()</code>	See <code>torch.flip lr()</code>
<code>flipud()</code>	See <code>torch.flip ud()</code>
<code>float([memory_format])</code>	<code>self.float()</code> is equivalent to <code>self.to(torch.float32)</code> .
<code>float_power(exponent)</code>	See <code>torch.float_power()</code>
<code>float_power_(exponent)</code>	In-place version of <code>float_power()</code>
<code>floor()</code>	See <code>torch.floor()</code>
<code>floor_()</code>	In-place version of <code>floor()</code>
<code>floor_divide(value)</code>	See <code>torch.floor_divide()</code>
<code>floor_divide_(value)</code>	In-place version of <code>floor_divide()</code>
<code>fmax(other)</code>	See <code>torch.fmax()</code>
<code>fmin(other)</code>	See <code>torch.fmin()</code>
<code>fmod(divisor)</code>	See <code>torch.fmod()</code>
<code>fmod_(divisor)</code>	In-place version of <code>fmod()</code>
<code>frac()</code>	See <code>torch.frac()</code>
<code>frac_()</code>	In-place version of <code>frac()</code>
<code>frexp(input)</code>	See <code>torch.frexp()</code>
<code>gather(dim, index)</code>	See <code>torch.gather()</code>
<code>gcd(other)</code>	See <code>torch.gcd()</code>
<code>gcd_(other)</code>	In-place version of <code>gcd()</code>
<code>ge(other)</code>	See <code>torch.ge()</code> .
<code>ge_(other)</code>	In-place version of <code>ge()</code> .
<code>geometric_(p, *[, generator])</code>	Fills <code>self</code> tensor with elements drawn from the geometric distribution:
<code>geqrdf()</code>	See <code>torch.geqrdf()</code>
<code>ger(vec2)</code>	See <code>torch.ger()</code>
<code>get_device()</code>	For CUDA tensors, this function returns the device ordinal of the GPU on which the tensor resides.
<code>greater(other)</code>	See <code>torch.greater()</code> .
<code>greater_(other)</code>	In-place version of <code>greater()</code> .
<code>greater_equal(other)</code>	See <code>torch.greater_equal()</code> .
<code>greater_equal_(other)</code>	In-place version of <code>greater_equal()</code> .
<code>gt(other)</code>	See <code>torch.gt()</code> .
<code>gt_(other)</code>	In-place version of <code>gt()</code> .
<code>half([memory_format])</code>	<code>self.half()</code> is equivalent to <code>self.to(torch.float16)</code> .
<code>hardshrink([lambd])</code>	See <code>torch.nn.functional.hardshrink()</code>
<code>has_names</code>	Is True if any of this tensor's dimensions are named.
<code>heaviside(values)</code>	See <code>torch.heaviside()</code>
<code>heaviside_(values)</code>	In-place version of <code>heaviside()</code>
<code>histc([bins, min, max])</code>	See <code>torch.histc()</code>
<code>histogram(input, bins, *[, range, weight, ...])</code>	See <code>torch.histogram()</code>
<code>hsplit(split_size_or_sections)</code>	See <code>torch.hsplit()</code>
<code>hypot(other)</code>	See <code>torch.hypot()</code>
<code>hypot_(other)</code>	In-place version of <code>hypot()</code>
<code>i0()</code>	See <code>torch.i0()</code>
<code>i0_()</code>	In-place version of <code>i0()</code>
<code>igamma(other)</code>	See <code>torch.igamma()</code>
<code>igamma_(other)</code>	In-place version of <code>igamma()</code>
<code>igammac(other)</code>	See <code>torch.igammac()</code>

continues on next page

Table 25 – continued from previous page

<code>igammac_(other)</code>	In-place version of <code>igammac()</code>
<code>index_add(dim, index, source, *[, alpha])</code>	Out-of-place version of <code>torch.Tensor.index_add_()</code> .
<code>index_add_(dim, index, source, *[, alpha])</code>	Accumulate the elements of <code>alpha</code> times <code>source</code> into the <code>self</code> tensor by adding to the indices in the order given in <code>index</code> .
<code>index_copy(dim, index, tensor2)</code>	Out-of-place version of <code>torch.Tensor.index_copy_()</code> .
<code>index_copy_(dim, index, tensor)</code>	Copies the elements of <code>tensor</code> into the <code>self</code> tensor by selecting the indices in the order given in <code>index</code> .
<code>index_fill(dim, index, value)</code>	Out-of-place version of <code>torch.Tensor.index_fill_()</code> .
<code>index_fill_(dim, index, value)</code>	Fills the elements of the <code>self</code> tensor with value <code>value</code> by selecting the indices in the order given in <code>index</code> .
<code>index_put(indices, values[, accumulate])</code>	Out-place version of <code>index_put_()</code> .
<code>index_put_(indices, values[, accumulate])</code>	Puts values from the tensor <code>values</code> into the tensor <code>self</code> using the indices specified in <code>indices</code> (which is a tuple of Tensors).
<code>index_reduce</code>	
<code>index_reduce_(dim, index, source, reduce, *)</code>	Accumulate the elements of <code>source</code> into the <code>self</code> tensor by accumulating to the indices in the order given in <code>index</code> using the reduction given by the <code>reduce</code> argument.
<code>index_select(dim, index)</code>	See <code>torch.index_select()</code>
<code>indices()</code>	Return the indices tensor of a sparse COO tensor.
<code>inner(other)</code>	See <code>torch.inner()</code> .
<code>int([memory_format])</code>	<code>self.int()</code> is equivalent to <code>self.to(torch.int32)</code> .
<code>int_repr()</code>	Given a quantized Tensor, <code>self.int_repr()</code> returns a CPU Tensor with <code>uint8_t</code> as data type that stores the underlying <code>uint8_t</code> values of the given Tensor.
<code>inverse()</code>	See <code>torch.inverse()</code>
<code>ipu([device, non_blocking, memory_format])</code>	Returns a copy of this object in IPU memory.
<code>is_coalesced()</code>	Returns True if <code>self</code> is a sparse COO tensor that is coalesced, False otherwise.
<code>is_complex()</code>	Returns True if the data type of <code>self</code> is a complex data type.
<code>is_conj()</code>	Returns True if the conjugate bit of <code>self</code> is set to true.
<code>is_contiguous([memory_format])</code>	Returns True if <code>self</code> tensor is contiguous in memory in the order specified by memory format.
<code>is_distributed</code>	
<code>is_floating_point()</code>	Returns True if the data type of <code>self</code> is a floating point data type.
<code>is_inference()</code>	See <code>torch.is_inference()</code>
<code>is_neg()</code>	Returns True if the negative bit of <code>self</code> is set to true.
<code>is_nonzero</code>	

continues on next page

Table 25 – continued from previous page

<code>is_pinned</code>	Returns true if this tensor resides in pinned memory.
<code>is_same_size</code>	
<code>is_set_to(tensor)</code>	Returns True if both tensors are pointing to the exact same memory (same storage, offset, size and stride).
<code>is_shared()</code>	Checks if tensor is in shared memory.
<code>is_signed()</code>	Returns True if the data type of <code>self</code> is a signed data type.
<code>isclose(other[, rtol, atol, equal_nan])</code>	See <code>torch.isclose()</code>
<code>isfinite()</code>	See <code>torch.isfinite()</code>
<code>isinf()</code>	See <code>torch.isinf()</code>
<code>isnan()</code>	See <code>torch.isnan()</code>
<code>isneginf()</code>	See <code>torch.isneginf()</code>
<code>isposinf()</code>	See <code>torch.isposinf()</code>
<code>isreal()</code>	See <code>torch.isreal()</code>
<code>istft(n_fft[, hop_length, win_length, ...])</code>	See <code>torch.istft()</code>
<code>item()</code>	Returns the value of this tensor as a standard Python number.
<code>kron(other)</code>	See <code>torch.kron()</code>
<code>kthvalue(k[, dim, keepdim])</code>	See <code>torch.kthvalue()</code>
<code>lcm(other)</code>	See <code>torch.lcm()</code>
<code>lcm_(other)</code>	In-place version of <code>lcm()</code>
<code>ldexp(other)</code>	See <code>torch.ldexp()</code>
<code>ldexp_(other)</code>	In-place version of <code>ldexp()</code>
<code>le(other)</code>	See <code>torch.le()</code> .
<code>le_(other)</code>	In-place version of <code>le()</code> .
<code>lerp(end, weight)</code>	See <code>torch.lerp()</code>
<code>lerp_(end, weight)</code>	In-place version of <code>lerp()</code>
<code>less</code>	<code>lt(other) -> Tensor</code>
<code>less_(other)</code>	In-place version of <code>less()</code> .
<code>less_equal(other)</code>	See <code>torch.less_equal()</code> .
<code>less_equal_(other)</code>	In-place version of <code>less_equal()</code> .
<code>lgamma()</code>	See <code>torch.lgamma()</code>
<code>lgamma_()</code>	In-place version of <code>lgamma()</code>
<code>log()</code>	See <code>torch.log()</code>
<code>log10()</code>	See <code>torch.log10()</code>
<code>log10_(other)</code>	In-place version of <code>log10()</code>
<code>log1p()</code>	See <code>torch.log1p()</code>
<code>log1p_(other)</code>	In-place version of <code>log1p()</code>
<code>log2()</code>	See <code>torch.log2()</code>
<code>log2_(other)</code>	In-place version of <code>log2()</code>
<code>log_(other)</code>	In-place version of <code>log()</code>
<code>log_normal_([mean, std, generator])</code>	Fills <code>self</code> tensor with numbers samples from the log-normal distribution parameterized by the given mean μ and standard deviation σ .
<code>log_softmax</code>	
<code>logaddexp(other)</code>	See <code>torch.logaddexp()</code>
<code>logaddexp2(other)</code>	See <code>torch.logaddexp2()</code>
<code>logcumsumexp(dim)</code>	See <code>torch.logcumsumexp()</code>

continues on next page

Table 25 – continued from previous page

<code>logdet()</code>	See <code>torch.logdet()</code>
<code>logical_and()</code>	See <code>torch.logical_and()</code>
<code>logical_and_()</code>	In-place version of <code>logical_and()</code>
<code>logical_not()</code>	See <code>torch.logical_not()</code>
<code>logical_not_()</code>	In-place version of <code>logical_not()</code>
<code>logical_or()</code>	See <code>torch.logical_or()</code>
<code>logical_or_()</code>	In-place version of <code>logical_or()</code>
<code>logical_xor()</code>	See <code>torch.logical_xor()</code>
<code>logical_xor_()</code>	In-place version of <code>logical_xor()</code>
<code>logit()</code>	See <code>torch.logit()</code>
<code>logit_()</code>	In-place version of <code>logit()</code>
<code>logsumexp(dim[, keepdim])</code>	See <code>torch.logsumexp()</code>
<code>long([memory_format])</code>	<code>self.long()</code> is equivalent to <code>self.to(torch.int64)</code> .
<code>lstsq(other)</code>	
<code>lt(other)</code>	See <code>torch.lt()</code> .
<code>lt_(other)</code>	In-place version of <code>lt()</code> .
<code>lu([pivot, get_infos])</code>	See <code>torch.lu()</code>
<code>lu_solve(LU_data, LU_pivots)</code>	See <code>torch.lu_solve()</code>
<code>map2_</code>	
<code>map_(tensor, callable)</code>	Applies <code>callable</code> for each element in <code>self</code> tensor and the given <code>tensor</code> and stores the results in <code>self</code> tensor.
<code>masked_fill(mask, value)</code>	Out-of-place version of <code>torch.Tensor.masked_fill_()</code>
<code>masked_fill_(mask, value)</code>	Fills elements of <code>self</code> tensor with <code>value</code> where <code>mask</code> is True.
<code>masked_scatter(mask, tensor)</code>	Out-of-place version of <code>torch.Tensor.masked_scatter_()</code>
<code>masked_scatter_(mask, source)</code>	Copies elements from <code>source</code> into <code>self</code> tensor at positions where the <code>mask</code> is True.
<code>masked_select(mask)</code>	See <code>torch.masked_select()</code>
<code>materialize(shape[, device, dtype])</code>	Create a Parameter with the same properties of the uninitialized one.
<code>matmul(tensor2)</code>	See <code>torch.matmul()</code>
<code>matrix_exp()</code>	See <code>torch.matrix_exp()</code>
<code>matrix_power(n)</code>	
<hr/> Note: <code>matrix_power()</code> is deprecated, use <code>torch.linalg.matrix_power()</code> instead. <hr/>	
<code>max([dim, keepdim])</code>	See <code>torch.max()</code>
<code>maximum(other)</code>	See <code>torch.maximum()</code>
<code>mean([dim, keepdim, dtype])</code>	See <code>torch.mean()</code>
<code>median([dim, keepdim])</code>	See <code>torch.median()</code>
<code>min([dim, keepdim])</code>	See <code>torch.min()</code>
<code>minimum(other)</code>	See <code>torch.minimum()</code>
<code>mm(mat2)</code>	See <code>torch.mm()</code>

continues on next page

Table 25 – continued from previous page

mode([dim, keepdim])	See <code>torch.mode()</code>
moveaxis(source, destination)	See <code>torch.moveaxis()</code>
movedim(source, destination)	See <code>torch.movedim()</code>
msort()	See <code>torch.msort()</code>
mul(value)	See <code>torch.mul()</code> .
mul_(value)	In-place version of <code>mul()</code> .
multinomial(num_samples[, replacement, ...])	See <code>torch.multinomial()</code>
multiply(value)	See <code>torch.multiply()</code> .
multiply_(value)	In-place version of <code>multiply()</code> .
mv(vec)	See <code>torch.mv()</code>
mvlgamma(p)	See <code>torch.mvlgamma()</code>
mvlgamma_(p)	In-place version of <code>mvlgamma()</code>
nan_to_num([nan, posinf, neginf])	See <code>torch.nan_to_num()</code> .
nan_to_num_([nan, posinf, neginf])	In-place version of <code>nan_to_num()</code> .
nanmean([dim, keepdim, dtype])	See <code>torch.nanmean()</code>
nanmedian([dim, keepdim])	See <code>torch.nanmedian()</code>
nanquantile(q[, dim, keepdim, interpolation])	See <code>torch.nanquantile()</code>
nansum([dim, keepdim, dtype])	See <code>torch.nansum()</code>
narrow(dimension, start, length)	See <code>torch.narrow()</code> .
narrow_copy(dimension, start, length)	See <code>torch.narrow_copy()</code> .
ndimension()	Alias for <code>dim()</code>
ne(other)	See <code>torch.ne()</code> .
ne_(other)	In-place version of <code>ne()</code> .
neg()	See <code>torch.neg()</code>
neg_()	In-place version of <code>neg()</code>
negative()	See <code>torch.negative()</code>
negative_()	In-place version of <code>negative()</code>
nelement()	Alias for <code>numel()</code>
new	
new_empty(size, *[, dtype, device, ...])	Returns a Tensor of size <code>size</code> filled with uninitialized data.
new_empty_strided(size, stride[, dtype, ...])	Returns a Tensor of size <code>size</code> and strides <code>stride</code> filled with uninitialized data.
new_full(size, fill_value, *[, dtype, ...])	Returns a Tensor of size <code>size</code> filled with <code>fill_value</code> .
new_ones(size, *[, dtype, device, ...])	Returns a Tensor of size <code>size</code> filled with 1.
new_tensor(data, *[, dtype, device, ...])	Returns a new Tensor with <code>data</code> as the tensor data.
new_zeros(size, *[, dtype, device, ...])	Returns a Tensor of size <code>size</code> filled with 0.
nextafter(other)	See <code>torch.nextafter()</code>
nextafter_(other)	In-place version of <code>nextafter()</code>
nonzero()	See <code>torch.nonzero()</code>
norm([p, dim, keepdim, dtype])	See <code>torch.norm()</code>
normal_([mean, std, generator])	Fills self tensor with elements samples from the normal distribution parameterized by <code>mean</code> and <code>std</code> .
not_equal(other)	See <code>torch.not_equal()</code> .
not_equal_(other)	In-place version of <code>not_equal()</code> .
numel()	See <code>torch.numel()</code>
numpy(*[, force])	Returns the tensor as a NumPy ndarray.
orgqr(input2)	See <code>torch.orgqr()</code>

continues on next page

Table 25 – continued from previous page

ormqr(input2, input3[, left, transpose])	See <code>torch.ormqr()</code>
outer(vec2)	See <code>torch.outer()</code> .
permute(*dims)	See <code>torch.permute()</code>
pin_memory()	Copies the tensor to pinned memory, if it's not already pinned.
pinverse()	See <code>torch.pinvse()</code>
polygamma(n)	See <code>torch.polygamma()</code>
polygamma_(n)	In-place version of <code>polygamma()</code>
positive()	See <code>torch.positive()</code>
pow(exponent)	See <code>torch.pow()</code>
pow_(exponent)	In-place version of <code>pow()</code>
prelu	
prod([dim, keepdim, dtype])	See <code>torch.prod()</code>
put(input, index, source[, accumulate])	Out-of-place version of <code>torch.Tensor.put_()</code> .
put_(index, source[, accumulate])	Copies the elements from <code>source</code> into the positions specified by <code>index</code> .
q_per_channel_axis()	Given a Tensor quantized by linear (affine) per-channel quantization, returns the index of dimension on which per-channel quantization is applied.
q_per_channel_scales()	Given a Tensor quantized by linear (affine) per-channel quantization, returns a Tensor of scales of the underlying quantizer.
q_per_channel_zero_points()	Given a Tensor quantized by linear (affine) per-channel quantization, returns a tensor of zero_points of the underlying quantizer.
q_scale()	Given a Tensor quantized by linear(affine) quantization, returns the scale of the underlying quantizer().
q_zero_point()	Given a Tensor quantized by linear(affine) quantization, returns the zero_point of the underlying quantizer().
qr([some])	See <code>torch.qr()</code>
qscheme()	Returns the quantization scheme of a given QTensor.
quantile(q[, dim, keepdim, interpolation])	See <code>torch.quantile()</code>
rad2deg()	See <code>torch.rad2deg()</code>
rad2deg_()	In-place version of <code>rad2deg()</code>
random_([from, to, generator])	Fills <code>self</code> tensor with numbers sampled from the discrete uniform distribution over [from, to - 1].
ravel()	see <code>torch.ravel()</code>
reciprocal()	See <code>torch.reciprocal()</code>
reciprocal_()	In-place version of <code>reciprocal()</code>
record_stream(stream)	Ensures that the tensor memory is not reused for another tensor until all current work queued on <code>stream</code> are complete.
refine_names(*names)	Refines the dimension names of <code>self</code> according to <code>names</code> .
register_hook(hook)	Registers a backward hook.
reinforce(reward)	
relu	

continues on next page

Table 25 – continued from previous page

<code>relu_</code>	
<code>remainder(divisor)</code>	See <code>torch.remainder()</code>
<code>remainder_(divisor)</code>	In-place version of <code>remainder()</code>
<code>rename(*names, **rename_map)</code>	Renames dimension names of <code>self</code> .
<code>rename_(*names, **rename_map)</code>	In-place version of <code>rename()</code> .
<code>renorm(p, dim, maxnorm)</code>	See <code>torch.renorm()</code>
<code>renorm_(p, dim, maxnorm)</code>	In-place version of <code>renorm()</code>
<code>repeat(*sizes)</code>	Repeats this tensor along the specified dimensions.
<code>repeat_interleave(repeats[, dim, output_size])</code>	See <code>torch.repeat_interleave()</code> .
<code>requires_grad_([requires_grad])</code>	Change if autograd should record operations on this tensor: sets this tensor's <code>requires_grad</code> attribute in-place.
<code>reshape(*shape)</code>	Returns a tensor with the same data and number of elements as <code>self</code> but with the specified shape.
<code>reshape_as(other)</code>	Returns this tensor as the same shape as <code>other</code> .
<code>resize(*sizes)</code>	
<code>resize_(*sizes[, memory_format])</code>	Resizes <code>self</code> tensor to the specified size.
<code>resize_as(tensor)</code>	
<code>resize_as_(tensor[, memory_format])</code>	Resizes the <code>self</code> tensor to be the same size as the specified <code>tensor</code> .
<code>resize_as_sparse_</code>	
<code>resolve_conj()</code>	See <code>torch.resolve_conj()</code>
<code>resolve_neg()</code>	See <code>torch.resolve_neg()</code>
<code>retain_grad()</code>	Enables this Tensor to have their <code>grad</code> populated during <code>backward()</code> .
<code>roll(shifts, dims)</code>	See <code>torch.roll()</code>
<code>rot90(k, dims)</code>	See <code>torch.rot90()</code>
<code>round([decimals])</code>	See <code>torch.round()</code>
<code>round_([decimals])</code>	In-place version of <code>round()</code>
<code>row_indices</code>	
<code>rsqrt()</code>	See <code>torch.rsqrt()</code>
<code>rsqrt_()</code>	In-place version of <code>rsqrt()</code>
<code>scatter(dim, index, src)</code>	Out-of-place version of <code>torch.Tensor.scatter_()</code>
<code>scatter_(dim, index, src[, reduce])</code>	Writes all values from the tensor <code>src</code> into <code>self</code> at the indices specified in the <code>index</code> tensor.
<code>scatter_add(dim, index, src)</code>	Out-of-place version of <code>torch.Tensor.scatter_add_()</code>
<code>scatter_add_(dim, index, src)</code>	Adds all values from the tensor <code>src</code> into <code>self</code> at the indices specified in the <code>index</code> tensor in a similar fashion as <code>scatter_()</code> .
<code>scatter_reduce(dim, index, src, reduce, *[...,])</code>	Out-of-place version of <code>torch.Tensor.scatter_reduce_()</code>

continues on next page

Table 25 – continued from previous page

<code>scatter_reduce_(dim, index, src, reduce, *)</code>	Reduces all values from the <code>src</code> tensor to the indices specified in the <code>index</code> tensor in the <code>self</code> tensor using the applied reduction defined via the <code>reduce</code> argument ("sum", "prod", "mean", "amax", "amin").
<code>select(dim, index)</code>	See <code>torch.select()</code>
<code>select_scatter(src, dim, index)</code>	See <code>torch.select_scatter()</code>
<code>set_([source, storage_offset, size, stride])</code>	Sets the underlying storage, size, and strides.
<code>sgn()</code>	See <code>torch.sgn()</code>
<code>sgn_()</code>	In-place version of <code>sgn()</code>
<code>share_memory_()</code>	Moves the underlying storage to shared memory.
<code>short([memory_format])</code>	<code>self.short()</code> is equivalent to <code>self.to(torch.int16)</code> .
<code>sigmoid()</code>	See <code>torch.sigmoid()</code>
<code>sigmoid_()</code>	In-place version of <code>sigmoid()</code>
<code>sign()</code>	See <code>torch.sign()</code>
<code>sign_()</code>	In-place version of <code>sign()</code>
<code>signbit()</code>	See <code>torch.signbit()</code>
<code>sin()</code>	See <code>torch.sin()</code>
<code>sin_()</code>	In-place version of <code>sin()</code>
<code>sinc()</code>	See <code>torch.sinc()</code>
<code>sinc_()</code>	In-place version of <code>sinc()</code>
<code>sinh()</code>	See <code>torch.sinh()</code>
<code>sinh_()</code>	In-place version of <code>sinh()</code>
<code>size([dim])</code>	Returns the size of the <code>self</code> tensor.
<code>slice_scatter(src[, dim, start, end, step])</code>	See <code>torch.slice_scatter()</code>
<code>slogdet()</code>	See <code>torch.slogdet()</code>
<code>smm(mat)</code>	See <code>torch.smm()</code>
<code>softmax(dim)</code>	Alias for <code>torch.nn.functional.softmax()</code> .
<code>solve(other)</code>	
<code>sort([dim, descending])</code>	See <code>torch.sort()</code>
<code>sparse_dim()</code>	Return the number of sparse dimensions in a sparse tensor <code>self</code> .
<code>sparse_mask(mask)</code>	Returns a new sparse tensor with values from a strided tensor <code>self</code> filtered by the indices of the sparse tensor <code>mask</code> .
<code>sparse_resize_(size, sparse_dim, dense_dim)</code>	Resizes <code>self</code> sparse tensor to the desired size and the number of sparse and dense dimensions.
<code>sparse_resize_and_clear_(size, sparse_dim, ...)</code>	Removes all specified elements from a sparse tensor <code>self</code> and resizes <code>self</code> to the desired size and the number of sparse and dense dimensions.
<code>split(split_size[, dim])</code>	See <code>torch.split()</code>
<code>split_with_sizes</code>	
<code>sqrt()</code>	See <code>torch.sqrt()</code>
<code>sqrt_()</code>	In-place version of <code>sqrt()</code>
<code>square()</code>	See <code>torch.square()</code>
<code>square_()</code>	In-place version of <code>square()</code>
<code>squeeze([dim])</code>	See <code>torch.squeeze()</code>
<code>squeeze_([dim])</code>	In-place version of <code>squeeze()</code>
<code>sspaddmm(mat1, mat2, *[beta, alpha])</code>	See <code>torch.sspaddmm()</code>

continues on next page

Table 25 – continued from previous page

<code>std([dim, correction, keepdim])</code>	See <code>torch.std()</code>
<code>stft(n_fft[, hop_length, win_length, ...])</code>	See <code>torch.stft()</code>
<code>storage()</code>	Returns the underlying <code>TypedStorage</code> .
<code>storage_offset()</code>	Returns <code>self</code> tensor's offset in the underlying storage in terms of number of storage elements (not bytes).
<code>storage_type()</code>	Returns the type of the underlying storage.
<code>stride(dim)</code>	Returns the stride of <code>self</code> tensor.
<code>sub(other, *[, alpha])</code>	See <code>torch.sub()</code> .
<code>sub_(other, *[, alpha])</code>	In-place version of <code>sub()</code>
<code>subtract(other, *[, alpha])</code>	See <code>torch.subtract()</code> .
<code>subtract_(other, *[, alpha])</code>	In-place version of <code>subtract()</code> .
<code>sum([dim, keepdim, dtype])</code>	See <code>torch.sum()</code>
<code>sum_to_size(*size)</code>	Sum this tensor to <code>size</code> .
<code>svd([some, compute_uv])</code>	See <code>torch.svd()</code>
<code>swapaxes(axis0, axis1)</code>	See <code>torch.swapaxes()</code>
<code>swapaxes_(axis0, axis1)</code>	In-place version of <code>swapaxes()</code>
<code>swapdims(dim0, dim1)</code>	See <code>torch.swapdims()</code>
<code>swapdims_(dim0, dim1)</code>	In-place version of <code>swapdims()</code>
<code>symeig([eigenvectors])</code>	
<code>t()</code>	See <code>torch.t()</code>
<code>t_()</code>	In-place version of <code>t()</code>
<code>take(indices)</code>	See <code>torch.take()</code>
<code>take_along_dim(indices, dim)</code>	See <code>torch.take_along_dim()</code>
<code>tan()</code>	See <code>torch.tan()</code>
<code>tan_()</code>	In-place version of <code>tan()</code>
<code>tanh()</code>	See <code>torch.tanh()</code>
<code>tanh_()</code>	In-place version of <code>tanh()</code>
<code>tensor_split(indices_or_sections[, dim])</code>	See <code>torch.tensor_split()</code>
<code>tile(*reps)</code>	See <code>torch.tile()</code>
<code>to(*args, **kwargs)</code>	Performs Tensor <code>dtype</code> and/or device conversion.
<code>to_dense()</code>	Creates a strided copy of <code>self</code> if <code>self</code> is not a strided tensor, otherwise returns <code>self</code> .
<code>to_mkldnn()</code>	Returns a copy of the tensor in <code>torch.mkldnn</code> layout.
<code>to_padded_tensor(padding[, output_size])</code>	See <code>to_padded_tensor()</code>
<code>to_sparse(sparseDims)</code>	Returns a sparse copy of the tensor.
<code>to_sparse_bsc(blocksize, dense_dim)</code>	Convert a tensor to a block sparse column (BSC) storage format of given blocksize.
<code>to_sparse_bsr(blocksize, dense_dim)</code>	Convert a tensor to a block sparse row (BSR) storage format of given blocksize.
<code>to_sparse_coo()</code>	Convert a tensor to coordinate format.
<code>to_sparse_csc()</code>	Convert a tensor to compressed column storage (CSC) format.
<code>to_sparse_csr([dense_dim])</code>	Convert a tensor to compressed row storage format (CSR).
<code>tolist()</code>	Returns the tensor as a (nested) list.
<code>topk(k[, dim, largest, sorted])</code>	See <code>torch.topk()</code>
<code>trace()</code>	See <code>torch.trace()</code>
<code>transpose(dim0, dim1)</code>	See <code>torch.transpose()</code>
<code>transpose_(dim0, dim1)</code>	In-place version of <code>transpose()</code>

continues on next page

Table 25 – continued from previous page

<code>triangular_solve(A[, upper, transpose, ...])</code>	See <code>torch.triangular_solve()</code>
<code>tril([diagonal])</code>	See <code>torch.tril()</code>
<code>tril_([diagonal])</code>	In-place version of <code>tril()</code>
<code>triu([diagonal])</code>	See <code>torch.triu()</code>
<code>triu_([diagonal])</code>	In-place version of <code>triu()</code>
<code>true_divide(value)</code>	See <code>torch.true_divide()</code>
<code>true_divide_(value)</code>	In-place version of <code>true_divide_()</code>
<code>trunc()</code>	See <code>torch.trunc()</code>
<code>trunc_()</code>	In-place version of <code>trunc()</code>
<code>type([dtype, non_blocking])</code>	Returns the type if <code>dtype</code> is not provided, else casts this object to the specified type.
<code>type_as(tensor)</code>	Returns this tensor cast to the type of the given tensor.
<code>unbind([dim])</code>	See <code>torch.unbind()</code>
<code>unflatten(dim, sizes)</code>	See <code>torch.unflatten()</code> .
<code>unfold(dimension, size, step)</code>	Returns a view of the original tensor which contains all slices of size <code>size</code> from <code>self</code> tensor in the dimension <code>dimension</code> .
<code>uniform_([from, to])</code>	Fills <code>self</code> tensor with numbers sampled from the continuous uniform distribution:
<code>unique([sorted, return_inverse, ...])</code>	Returns the unique elements of the input tensor.
<code>unique_consecutive([return_inverse, ...])</code>	Eliminates all but the first element from every consecutive group of equivalent elements.
<code>unsafe_chunk(chunks[, dim])</code>	See <code>torch.unsafe_chunk()</code>
<code>unsafe_split(split_size[, dim])</code>	See <code>torch.unsafe_split()</code>
<code>unsafe_split_with_sizes</code>	
<code>unsqueeze(dim)</code>	See <code>torch.unsqueeze()</code>
<code>unsqueeze_(dim)</code>	In-place version of <code>unsqueeze()</code>
<code>untyped_storage()</code>	Returns the underlying <code>UntypedStorage</code> .
<code>values()</code>	Return the values tensor of a sparse COO tensor.
<code>var([dim, correction, keepdim])</code>	See <code>torch.var()</code>
<code>vdot(other)</code>	See <code>torch.vdot()</code>
<code>view(*shape)</code>	Returns a new tensor with the same data as the <code>self</code> tensor but of a different <code>shape</code> .
<code>view_as(other)</code>	View this tensor as the same size as <code>other</code> .
<code>vsplit(split_size_or_sections)</code>	See <code>torch.vsplit()</code>
<code>where(condition, y)</code>	<code>self.where(condition, y)</code> is equivalent to <code>torch.where(condition, self, y)</code> .
<code>xlogy(other)</code>	See <code>torch.xlogy()</code>
<code>xlogy_(other)</code>	In-place version of <code>xlogy()</code>
<code>xpu([device, non_blocking, memory_format])</code>	Returns a copy of this object in XPU memory.
<code>zero_()</code>	Fills <code>self</code> tensor with zeros.

Attributes

H	Returns a view of a matrix (2-D tensor) conjugated and transposed.
T	Returns a view of this tensor with its dimensions reversed.
data	
device	Is the <code>torch.device</code> where this Tensor is.
dtype	
grad	This attribute is <code>None</code> by default and becomes a Tensor the first time a call to <code>backward()</code> computes gradients for <code>self</code> .
grad_fn	
imag	Returns a new tensor containing imaginary values of the <code>self</code> tensor.
is_cpu	Is <code>True</code> if the Tensor is stored on the CPU, <code>False</code> otherwise.
is_cuda	Is <code>True</code> if the Tensor is stored on the GPU, <code>False</code> otherwise.
is_ipu	Is <code>True</code> if the Tensor is stored on the IPU, <code>False</code> otherwise.
is_leaf	All Tensors that have <code>requires_grad</code> which is <code>False</code> will be leaf Tensors by convention.
is_meta	Is <code>True</code> if the Tensor is a meta tensor, <code>False</code> otherwise.
is_mkldnn	
is_mps	Is <code>True</code> if the Tensor is stored on the MPS device, <code>False</code> otherwise.
is_nested	
is_ort	
is_quantized	Is <code>True</code> if the Tensor is quantized, <code>False</code> otherwise.
is_sparse	Is <code>True</code> if the Tensor uses sparse storage layout, <code>False</code> otherwise.
is_sparse_csr	Is <code>True</code> if the Tensor uses sparse CSR storage layout, <code>False</code> otherwise.
is_vulkan	
is_xpu	Is <code>True</code> if the Tensor is stored on the XPU, <code>False</code> otherwise.
layout	
mH	Accessing this property is equivalent to calling <code>adjoint()</code> .
mT	Returns a view of this tensor with the last two dimensions transposed.

continues on next page

Table 26 – continued from previous page

name	
names	Stores names for each of this tensor's dimensions.
ndim	Alias for dim()
output_nr	
real	Returns a new tensor containing real values of the self tensor for a complex-valued input tensor.
requires_grad	Is True if gradients need to be computed for this Tensor, False otherwise.
retains_grad	Is True if this Tensor is non-leaf and its grad is enabled to be populated during backward(), False otherwise.
shape	
volatile	

property is_leaf: bool

All Tensors that have requires_grad which is False will be leaf Tensors by convention.

For Tensors that have requires_grad which is True, they will be leaf Tensors if they were created by the user. This means that they are not the result of an operation and so grad_fn is None.

Only leaf Tensors will have their grad populated during a call to backward(). To get grad populated for non-leaf Tensors, you can use retain_grad().

Example:

```
>>> a = torch.rand(10, requires_grad=True)
>>> a.is_leaf
True
>>> b = torch.rand(10, requires_grad=True).cuda()
>>> b.is_leaf
False
# b was created by the operation that cast a cpu Tensor into a cuda Tensor
>>> c = torch.rand(10, requires_grad=True) + 2
>>> c.is_leaf
False
# c was created by the addition operation
>>> d = torch.rand(10).cuda()
>>> d.is_leaf
True
# d does not require gradients and so has no operation creating it (that is
# tracked by the autograd engine)
>>> e = torch.rand(10).cuda().requires_grad_()
>>> e.is_leaf
True
# e requires gradients and has no operations creating it
>>> f = torch.rand(10, requires_grad=True, device="cuda")
>>> f.is_leaf
True
# f requires grad, has no operation creating it
```

`materialize(shape, device=None, dtype=None)`

Create a Parameter with the same properties of the uninitialized one. Given a shape, it materializes a parameter in the same device and with the same *dtype* as the current one or the specified ones in the arguments.

Parameters

- **shape** (`Tuple[int, ...]`) – (tuple): the shape for the materialized tensor.
- **device** (`torch.device`) – the desired device of the parameters and buffers in this module. Optional.
- **dtype** (`torch.dtype`) – the desired floating point type of the floating point parameters and buffers in this module. Optional.

Return type

`None`

`share_memory_()`

Moves the underlying storage to shared memory.

This is a no-op if the underlying storage is already in shared memory and for CUDA tensors. Tensors in shared memory cannot be resized.

Return type

`UninitializedParameter`

`pytorch_pfn_extras.nn.parallel`

Classes

<code>pytorch_pfn_extras.nn.parallel.DistributedDataParallel(module)</code>	Module for distributed data parallelism
---	---

`pytorch_pfn_extras.nn.parallel.DistributedDataParallel`

```
class pytorch_pfn_extras.nn.parallel.DistributedDataParallel(module, broadcast_buffers=True,
                                                               negotiate_grads=True,
                                                               process_group=None,
                                                               reduce_function=None,
                                                               broadcast_function=None,
                                                               **kwargs)
```

Bases: `Module`

Module for distributed data parallelism

This class synchronizes the gradients and the buffers after backward computations.

Parameters

- **module** (`Module`) – `torch.nn.Module` object to be trained
- **broadcast_buffers** (`bool`) – Boolean flag to broadcast buffers after backward computations. Broadcasting buffers may be helpful when the module includes BatchNormalization. However, it will degrade training throughput. (default: `True`)

- **negotiate_grads** (*bool*) – Boolean flag to choose gradients to be sent before all-reduce. This flag is necessary when the computation graph of the module is dynamic. (default: *True*)
- **process_group** (*Optional[ProcessGroup]*) – Process group used for broadcasting and reducing. (default: *torch.distributed.group.WORLD*)
- **reduce_function** (*Optional[Callable[[Sequence[Tensor], Optional[ProcessGroup]], None]]*) – All-reduce function
- **broadcast_function** (*Optional[Callable[[Sequence[Tensor], Optional[ProcessGroup]], None]]*) – Broadcast function
- **kwargs** (*Any*) –

This module receives keyword arguments for the compatibility with *torch.nn.parallel.DistributedDataParallel*. It shows a warning when setting the ignored arguments.

Methods

<code>__init__(module[, broadcast_buffers, ...])</code>	This module receives keyword arguments for the compatibility with <i>torch.nn.parallel.DistributedDataParallel</i> .
<code>add_module(name, module)</code>	Adds a child module to the current module.
<code>apply(fn)</code>	Applies <i>fn</i> recursively to every submodule (as returned by <code>.children()</code>) as well as self.
<code>bfloat16()</code>	Casts all floating point parameters and buffers to <code>bfloat16</code> datatype.
<code>buffers([reuse])</code>	Returns an iterator over module buffers.
<code>children()</code>	Returns an iterator over immediate children modules.
<code>cpu()</code>	Moves all model parameters and buffers to the CPU.
<code>cuda([device])</code>	Moves all model parameters and buffers to the GPU.
<code>double()</code>	Casts all floating point parameters and buffers to <code>double</code> datatype.
<code>eval()</code>	Sets the module in evaluation mode.
<code>extra_repr()</code>	Set the extra representation of the module
<code>float()</code>	Casts all floating point parameters and buffers to <code>float</code> datatype.
<code>forward(*args, **kwargs)</code>	Defines the computation performed at every call.
<code>get_buffer(target)</code>	Returns the buffer given by <i>target</i> if it exists, otherwise throws an error.
<code>get_extra_state()</code>	Returns any extra state to include in the module's <code>state_dict</code> .
<code>get_parameter(target)</code>	Returns the parameter given by <i>target</i> if it exists, otherwise throws an error.
<code>get_submodule(target)</code>	Returns the submodule given by <i>target</i> if it exists, otherwise throws an error.
<code>half()</code>	Casts all floating point parameters and buffers to <code>half</code> datatype.
<code>ipu([device])</code>	Moves all model parameters and buffers to the IPU.
<code>load_state_dict(state_dict[, strict])</code>	Copies parameters and buffers from <code>state_dict</code> into this module and its descendants.
<code>modules()</code>	Returns an iterator over all modules in the network.

continues on next page

Table 27 – continued from previous page

<code>named_buffers([prefix, recurse, ...])</code>	Returns an iterator over module buffers, yielding both the name of the buffer as well as the buffer itself.
<code>named_children()</code>	Returns an iterator over immediate children modules, yielding both the name of the module as well as the module itself.
<code>named_modules([memo, prefix, remove_duplicate])</code>	Returns an iterator over all modules in the network, yielding both the name of the module as well as the module itself.
<code>named_parameters([prefix, recurse, ...])</code>	Returns an iterator over module parameters, yielding both the name of the parameter as well as the parameter itself.
<code>no_sync()</code>	A context manager to disable synchronization after backward
<code>parameters([recurse])</code>	Returns an iterator over module parameters.
<code>register_backward_hook(hook)</code>	Registers a backward hook on the module.
<code>register_buffer(name, tensor[, persistent])</code>	Adds a buffer to the module.
<code>register_comm_hook(hook)</code>	Registers a hook function.
<code>register_forward_hook(hook, *[, prepend, ...])</code>	Registers a forward hook on the module.
<code>register_forward_pre_hook(hook, *[, ...])</code>	Registers a forward pre-hook on the module.
<code>register_full_backward_hook(hook[, prepend])</code>	Registers a backward hook on the module.
<code>register_full_backward_pre_hook(hook[, prepend])</code>	Registers a backward pre-hook on the module.
<code>register_load_state_dict_post_hook(hook)</code>	Registers a post hook to be run after module's <code>load_state_dict</code> is called.
<code>register_module(name, module)</code>	Alias for <code>add_module()</code> .
<code>register_parameter(name, param)</code>	Adds a parameter to the module.
<code>register_state_dict_pre_hook(hook)</code>	These hooks will be called with arguments: <code>self</code> , <code>prefix</code> , and <code>keep_vars</code> before calling <code>state_dict</code> on <code>self</code> .
<code>requires_grad_([requires_grad])</code>	Change if autograd should record operations on parameters in this module.
<code>set_extra_state(state)</code>	This function is called from <code>load_state_dict()</code> to handle any extra state found within the <code>state_dict</code> .
<code>share_memory()</code>	See <code>torch.Tensor.share_memory_()</code>
<code>state_dict()</code>	Returns a dictionary containing references to the whole state of the module.
<code>to(*args, **kwargs)</code>	Moves and/or casts the parameters and buffers.
<code>to_empty(*, device)</code>	Moves the parameters and buffers to the specified device without copying storage.
<code>train([mode])</code>	Sets the module in training mode.
<code>type(dst_type)</code>	Casts all parameters and buffers to <code>dst_type</code> .
<code>xpu([device])</code>	Moves all model parameters and buffers to the XPU.
<code>zero_grad([set_to_none])</code>	Sets gradients of all model parameters to zero.

Attributes

<code>T_destination</code>	alias of TypeVar('T_destination', bound=Mapping[str, Tensor])
<code>call_super_init</code>	
<code>dump_patches</code>	

`T_destination`

alias of TypeVar('T_destination', bound=Mapping[str, Tensor])

`__init__(module, broadcast_buffers=True, negotiate_grads=True, process_group=None, reduce_function=None, broadcast_function=None, **kwargs)`

This module receives keyword arguments for the compatibility with `torch.nn.parallel.DistributedDataParallel`. It shows a warning when setting the ignored arguments.

Parameters

- `module (Module)` –
- `broadcast_buffers (bool)` –
- `negotiate_grads (bool)` –
- `process_group (Optional[ProcessGroup])` –
- `reduce_function (Optional[Callable[[Sequence[Tensor], Optional[ProcessGroup]], None]])` –
- `broadcast_function (Optional[Callable[[Sequence[Tensor], Optional[ProcessGroup]], None]])` –
- `kwargs (Any)` –

Return type

`None`

`forward(*args, **kwargs)`

Defines the computation performed at every call.

Should be overridden by all subclasses.

Note: Although the recipe for forward pass needs to be defined within this function, one should call the `Module` instance afterwards instead of this since the former takes care of running the registered hooks while the latter silently ignores them.

Parameters

- `args (Any)` –
- `kwargs (Any)` –

Return type

`Any`

load_state_dict(state_dict, strict=True)

Copies parameters and buffers from `state_dict` into this module and its descendants. If `strict` is True, then the keys of `state_dict` must exactly match the keys returned by this module's `state_dict()` function.

Parameters

- `state_dict (dict)` – a dict containing parameters and persistent buffers.
- `strict (bool, optional)` – whether to strictly enforce that the keys in `state_dict` match the keys returned by this module's `state_dict()` function. Default: True

Returns

- `missing_keys` is a list of str containing the missing keys
- `unexpected_keys` is a list of str containing the unexpected keys

Return type

`NamedTuple` with `missing_keys` and `unexpected_keys` fields

Note: If a parameter or buffer is registered as `None` and its corresponding key exists in `state_dict`, `load_state_dict()` will raise a `RuntimeError`.

no_sync()

A context manager to disable synchronization after backward

Return type

`Generator[None, None, None]`

register_comm_hook(hook)

Registers a hook function. This module will invoke the hook before starting the synchronization.

Args: `hook`: Callable object that will be invoked before synchronization

Parameters

`hook (Callable[[DistributedDataParallel], None])` –

Return type

`RemovableHandle`

state_dict()

Returns a dictionary containing references to the whole state of the module.

Both parameters and persistent buffers (e.g. running averages) are included. Keys are corresponding parameter and buffer names. Parameters and buffers set to `None` are not included.

Note: The returned object is a shallow copy. It contains references to the module's parameters and buffers.

Warning: Currently `state_dict()` also accepts positional arguments for `destination`, `prefix` and `keep_vars` in order. However, this is being deprecated and keyword arguments will be enforced in future releases.

Warning: Please avoid the use of argument `destination` as it is not designed for end-users.

Parameters

- **destination** (*dict, optional*) – If provided, the state of module will be updated into the dict and the same object is returned. Otherwise, an `OrderedDict` will be created and returned. Default: `None`.
- **prefix** (*str, optional*) – a prefix added to parameter and buffer names to compose the keys in state_dict. Default: ''.
- **keep_vars** (*bool, optional*) – by default the `Tensor`s returned in the state dict are detached from autograd. If it's set to `True`, detaching will not be performed. Default: `False`.

Returns

a dictionary containing a whole state of the module

Return type

`dict`

Example:

```
>>> # xdoctest: +SKIP("undefined vars")
>>> module.state_dict().keys()
['bias', 'weight']
```

training: `bool`

Modules

`pytorch_pfn_extras.nn.parallel.distributed`

pytorch_pfn_extras.nn.parallel.distributed**Functions**

<code>pytorch_pfn_extras.nn.parallel.distributed.contextmanager(func)</code>	@contextmanager decorator.
<code>pytorch_pfn_extras.nn.parallel.distributed.get_foreach_wrapper()</code>	
<code>pytorch_pfn_extras.nn.parallel.distributed.record(tag)</code>	

[pytorch_pfn_extras.nn.parallel.distributed.contextmanager](#)

`pytorch_pfn_extras.nn.parallel.distributed.contextmanager(func)`

@contextmanager decorator.

Typical usage:

```
@contextmanager def some_generator(<arguments>):
    <setup> try:
        yield <value>
    finally:
        <cleanup>
```

This makes this:

```
with some_generator(<arguments>) as <variable>:
    <body>
```

equivalent to this:

```
<setup> try:
    <variable> = <value> <body>
finally:
    <cleanup>
```

[pytorch_pfn_extras.nn.parallel.distributed.get_FOREACH_wrapper](#)

`pytorch_pfn_extras.nn.parallel.distributed.get_FOREACH_wrapper()`

Return type

_ForEachWrapper

[pytorch_pfn_extras.nn.parallel.distributed.record](#)

`pytorch_pfn_extras.nn.parallel.distributed.record(tag, metric=None, use_cuda=False, enable=True, device='cpu')`

Parameters

- **tag** (*Optional[str]*) –
- **metric** (*Optional[str]*) –
- **use_cuda** (*bool*) –
- **enable** (*bool*) –
- **device** (*DeviceLike*) –

Return type

Generator[_ReportNotification, None, None]

Classes

<code>pytorch_pfn_extras.nn.parallel. distributed.DistributedDataParallel(module)</code>	Module for distributed data parallelism
<code>pytorch_pfn_extras.nn.parallel. distributed.OrderedDict</code>	Dictionary that remembers insertion order
<code>pytorch_pfn_extras.nn.parallel. distributed.TypeVar(...)</code>	Type variable.
<code>pytorch_pfn_extras.nn.parallel. distributed.Variable</code>	
<code>pytorch_pfn_extras.nn.parallel. distributed.record_function(name)</code>	Context manager/function decorator that adds a label to a block of Python code (or function) when running autograd profiler.

`pytorch_pfn_extras.nn.parallel.distributed.DistributedDataParallel`

```
class pytorch_pfn_extras.nn.parallel.distributed.DistributedDataParallel(module, broadcast_buffers=True,  
negotiate_grads=True,  
process_group=None,  
reduce_function=None,  
broadcast_function=None,  
**kwargs)
```

Bases: `Module`

Module for distributed data parallelism

This class synchronizes the gradients and the buffers after backward computations.

Parameters

- **module** (`Module`) – `torch.nn.Module` object to be trained
- **broadcast_buffers** (`bool`) – Boolean flag to broadcast buffers after backward computations. Broadcasting buffers may be helpful when the module includes BatchNormalization. However, it will degrade training throughput. (default: `True`)
- **negotiate_grads** (`bool`) – Boolean flag to choose gradients to be sent before all-reduce. This flag is necessary when the computation graph of the module is dynamic. (default: `True`)
- **process_group** (`Optional[ProcessGroup]`) – Process group used for broadcasting and reducing. (default: `torch.distributed.group.WORLD`)
- **reduce_function** (`Optional[Callable[[Sequence[Tensor],
Optional[ProcessGroup]], None]]`) – All-reduce function
- **broadcast_function** (`Optional[Callable[[Sequence[Tensor],
Optional[ProcessGroup]], None]]`) – Broadcast function
- **kwargs** (`Any`) –

This module receives keyword arguments for the compatibility with `torch.nn.parallel.DistributedDataParallel`. It shows a warning when setting the ignored arguments.

Methods

<code>__init__(module[, broadcast_buffers, ...])</code>	This module receives keyword arguments for the compatibility with <code>torch.nn.parallel.DistributedDataParallel</code> .
<code>add_module(name, module)</code>	Adds a child module to the current module.
<code>apply(fn)</code>	Applies <code>fn</code> recursively to every submodule (as returned by <code>.children()</code>) as well as self.
<code>bfloat16()</code>	Casts all floating point parameters and buffers to <code>bfloat16</code> datatype.
<code>buffers([recurse])</code>	Returns an iterator over module buffers.
<code>children()</code>	Returns an iterator over immediate children modules.
<code>cpu()</code>	Moves all model parameters and buffers to the CPU.
<code>cuda([device])</code>	Moves all model parameters and buffers to the GPU.
<code>double()</code>	Casts all floating point parameters and buffers to <code>double</code> datatype.
<code>eval()</code>	Sets the module in evaluation mode.
<code>extra_repr()</code>	Set the extra representation of the module
<code>float()</code>	Casts all floating point parameters and buffers to <code>float</code> datatype.
<code>forward(*args, **kwargs)</code>	Defines the computation performed at every call.
<code>get_buffer(target)</code>	Returns the buffer given by <code>target</code> if it exists, otherwise throws an error.
<code>get_extra_state()</code>	Returns any extra state to include in the module's <code>state_dict</code> .
<code>get_parameter(target)</code>	Returns the parameter given by <code>target</code> if it exists, otherwise throws an error.
<code>get_submodule(target)</code>	Returns the submodule given by <code>target</code> if it exists, otherwise throws an error.
<code>half()</code>	Casts all floating point parameters and buffers to <code>half</code> datatype.
<code>ipu([device])</code>	Moves all model parameters and buffers to the IPU.
<code>load_state_dict(state_dict[, strict])</code>	Copies parameters and buffers from <code>state_dict</code> into this module and its descendants.
<code>modules()</code>	Returns an iterator over all modules in the network.
<code>named_buffers([prefix, recurse, ...])</code>	Returns an iterator over module buffers, yielding both the name of the buffer as well as the buffer itself.
<code>named_children()</code>	Returns an iterator over immediate children modules, yielding both the name of the module as well as the module itself.
<code>named_modules([memo, prefix, remove_duplicate])</code>	Returns an iterator over all modules in the network, yielding both the name of the module as well as the module itself.
<code>named_parameters([prefix, recurse, ...])</code>	Returns an iterator over module parameters, yielding both the name of the parameter as well as the parameter itself.
<code>no_sync()</code>	A context manager to disable synchronization after backward

continues on next page

Table 28 – continued from previous page

<code>parameters([reuse])</code>	Returns an iterator over module parameters.
<code>register_backward_hook(hook)</code>	Registers a backward hook on the module.
<code>register_buffer(name, tensor[, persistent])</code>	Adds a buffer to the module.
<code>register_comm_hook(hook)</code>	Registers a hook function.
<code>register_forward_hook(hook, *[, prepend, ...])</code>	Registers a forward hook on the module.
<code>register_forward_pre_hook(hook, *[, ...])</code>	Registers a forward pre-hook on the module.
<code>register_full_backward_hook(hook[, prepend])</code>	Registers a backward hook on the module.
<code>register_full_backward_pre_hook(hook[, prepend])</code>	Registers a backward pre-hook on the module.
<code>register_load_state_dict_post_hook(hook)</code>	Registers a post hook to be run after module's <code>load_state_dict</code> is called.
<code>register_module(name, module)</code>	Alias for <code>add_module()</code> .
<code>register_parameter(name, param)</code>	Adds a parameter to the module.
<code>register_state_dict_pre_hook(hook)</code>	These hooks will be called with arguments: <code>self</code> , <code>prefix</code> , and <code>keep_vars</code> before calling <code>state_dict</code> on <code>self</code> .
<code>requires_grad_([requires_grad])</code>	Change if autograd should record operations on parameters in this module.
<code>set_extra_state(state)</code>	This function is called from <code>load_state_dict()</code> to handle any extra state found within the <code>state_dict</code> .
<code>share_memory()</code>	See <code>torch.Tensor.share_memory_()</code>
<code>state_dict()</code>	Returns a dictionary containing references to the whole state of the module.
<code>to(*args, **kwargs)</code>	Moves and/or casts the parameters and buffers.
<code>to_empty(*, device)</code>	Moves the parameters and buffers to the specified device without copying storage.
<code>train([mode])</code>	Sets the module in training mode.
<code>type(dst_type)</code>	Casts all parameters and buffers to <code>dst_type</code> .
<code>xpu([device])</code>	Moves all model parameters and buffers to the XPU.
<code>zero_grad([set_to_none])</code>	Sets gradients of all model parameters to zero.

Attributes

<code>T_destination</code>	alias of TypeVar('T_destination', bound=Mapping[str, Tensor])
<code>call_super_init</code>	
<code>dump_patches</code>	

`T_destination`

alias of TypeVar('T_destination', bound=Mapping[str, Tensor])

`__init__(module, broadcast_buffers=True, negotiate_grads=True, process_group=None, reduce_function=None, broadcast_function=None, **kwargs)`

This module receives keyword arguments for the compatibility with `torch.nn.parallel.DistributedDataParallel`. It shows a warning when setting the ignored arguments.

Parameters

- **module** (*Module*) –
- **broadcast_buffers** (*bool*) –
- **negotiate_grads** (*bool*) –
- **process_group** (*Optional[ProcessGroup]*) –
- **reduce_function** (*Optional[Callable[[Sequence[Tensor]], Optional[ProcessGroup]], None]*) –
- **broadcast_function** (*Optional[Callable[[Sequence[Tensor]], Optional[ProcessGroup]], None]*) –
- **kwargs** (*Any*) –

Return type

None

forward(**args*, ***kwargs*)

Defines the computation performed at every call.

Should be overridden by all subclasses.

Note: Although the recipe for forward pass needs to be defined within this function, one should call the *Module* instance afterwards instead of this since the former takes care of running the registered hooks while the latter silently ignores them.

Parameters

- **args** (*Any*) –
- **kwargs** (*Any*) –

Return type

Any

load_state_dict(*state_dict*, *strict=True*)

Copies parameters and buffers from *state_dict* into this module and its descendants. If *strict* is True, then the keys of *state_dict* must exactly match the keys returned by this module’s *state_dict()* function.

Parameters

- **state_dict** (*dict*) – a dict containing parameters and persistent buffers.
- **strict** (*bool, optional*) – whether to strictly enforce that the keys in *state_dict* match the keys returned by this module’s *state_dict()* function. Default: True

Returns

- **missing_keys** is a list of str containing the missing keys
- **unexpected_keys** is a list of str containing the unexpected keys

Return type

NamedTuple with *missing_keys* and *unexpected_keys* fields

Note: If a parameter or buffer is registered as *None* and its corresponding key exists in *state_dict*, *load_state_dict()* will raise a *RuntimeError*.

no_sync()

A context manager to disable synchronization after backward

Return type

Generator[None, None, None]

register_comm_hook(hook)

Registers a hook function. This module will invoke the hook before starting the synchronization.

Args: hook: Callable object that will be invoked before synchronization

Parameters

`hook (Callable[[DistributedDataParallel], None]) –`

Return type

RemovableHandle

state_dict()

Returns a dictionary containing references to the whole state of the module.

Both parameters and persistent buffers (e.g. running averages) are included. Keys are corresponding parameter and buffer names. Parameters and buffers set to None are not included.

Note: The returned object is a shallow copy. It contains references to the module's parameters and buffers.

Warning: Currently `state_dict()` also accepts positional arguments for `destination`, `prefix` and `keep_vars` in order. However, this is being deprecated and keyword arguments will be enforced in future releases.

Warning: Please avoid the use of argument `destination` as it is not designed for end-users.

Parameters

- **destination** (`dict`, *optional*) – If provided, the state of module will be updated into the dict and the same object is returned. Otherwise, an `OrderedDict` will be created and returned. Default: `None`.
- **prefix** (`str`, *optional*) – a prefix added to parameter and buffer names to compose the keys in `state_dict`. Default: ''.
- **keep_vars** (`bool`, *optional*) – by default the `Tensor`'s returned in the state dict are detached from autograd. If it's set to `True`, detaching will not be performed. Default: `False`.

Returns

a dictionary containing a whole state of the module

Return type

`dict`

Example:

```
>>> # xdoctest: +SKIP("undefined vars")
>>> module.state_dict().keys()
['bias', 'weight']
```

training: bool

[pytorch_pfn_extras.nn.parallel.distributed.OrderedDict](#)

class [pytorch_pfn_extras.nn.parallel.distributed.OrderedDict](#)

Bases: dict

Dictionary that remembers insertion order

Methods

`__init__(*args, **kwargs)`

`clear()`

`copy()`

`fromkeys([value])` Create a new ordered dictionary with keys from iterable and values set to value.

`get(key[, default])` Return the value for key if key is in the dictionary, else default.

`items()`

`keys()`

`move_to_end(key[, last])` Move an existing element to the end (or beginning if last is false).

`pop(k[,d])` value.

`popitem([last])` Remove and return a (key, value) pair from the dictionary.

`setdefault(key[, default])` Insert key with a value of default if key is not in the dictionary.

`update([E,]**F)` If E is present and has a .keys() method, then does: for k in E: D[k] = E[k] If E is present and lacks a .keys() method, then does: for k, v in E: D[k] = v In either case, this is followed by: for k in F: D[k] = F[k]

`values()`

`__init__(*args, **kwargs)`

`clear()` → None. Remove all items from od.

`copy()` → a shallow copy of od

`fromkeys(value=None)`

Create a new ordered dictionary with keys from iterable and values set to value.

items() → a set-like object providing a view on D's items

keys() → a set-like object providing a view on D's keys

move_to_end(key, last=True)

Move an existing element to the end (or beginning if last is false).

Raise KeyError if the element does not exist.

pop(k[, d]) → v, remove specified key and return the corresponding

value. If key is not found, d is returned if given, otherwise KeyError is raised.

popitem(last=True)

Remove and return a (key, value) pair from the dictionary.

Pairs are returned in LIFO order if last is true or FIFO order if false.

setdefault(key, default=None)

Insert key with a value of default if key is not in the dictionary.

Return the value for key if key is in the dictionary, else default.

update([E], **F) → None. Update D from dict/iterable E and F.

If E is present and has a .keys() method, then does: for k in E: D[k] = E[k] If E is present and lacks a .keys() method, then does: for k, v in E: D[k] = v In either case, this is followed by: for k in F: D[k] = F[k]

values() → an object providing a view on D's values

pytorch_pfn_extras.nn.parallel.distributed.TypeVar

```
class pytorch_pfn_extras.nn.parallel.distributed.TypeVar(name, *constraints, bound=None,
                                                       covariant=False, contravariant=False)
```

Bases: `_Final, _Immutable`

Type variable.

Usage:

```
T = TypeVar('T') # Can be anything
A = TypeVar('A', str, bytes) # Must be str or bytes
```

Type variables exist primarily for the benefit of static type checkers. They serve as the parameters for generic types as well as for generic function definitions. See class Generic for more information on generic types. Generic functions work as follows:

```
def repeat(x: T, n: int) -> List[T]:
```

"Return a list containing n references to x." return [x]*n

```
def longest(x: A, y: A) -> A:
```

"Return the longest of two strings." return x if len(x) >= len(y) else y

The latter example's signature is essentially the overloading of (str, str) -> str and (bytes, bytes) -> bytes. Also note that if the arguments are instances of some subclass of str, the return type is still plain str.

At runtime, `isinstance(x, T)` and `issubclass(C, T)` will raise `TypeError`.

Type variables defined with `covariant=True` or `contravariant=True` can be used to declare covariant or contravariant generic types. See PEP 484 for more details. By default generic types are invariant in all type variables.

Type variables can be introspected. e.g.:

```
T.__name__ == 'T' T.__constraints__ == () T.__covariant__ == False T.__contravariant__ = False  
A.__constraints__ == (str, bytes)
```

Note that only type variables defined in global scope can be pickled.

Methods

```
__init__(name, *constraints[, bound, ...])
```

```
__init__(name, *constraints, bound=None, covariant=False, contravariant=False)
```

pytorch_pfn_extras.nn.parallel.distributed.Variable

```
class pytorch_pfn_extras.nn.parallel.distributed.Variable  
Bases: _LegacyVariableBase
```

Methods

```
__init__()
```

pytorch_pfn_extras.nn.parallel.distributed.record_function

```
class pytorch_pfn_extras.nn.parallel.distributed.record_function(name, args=None)  
Bases: ContextDecorator  
  
Context manager/function decorator that adds a label to a block of Python code (or function) when running autograd profiler. It is useful when tracing the code profile.
```

Parameters

- **name** (*str*) – Label assigned to the block of code.
- **node_id** (*int*) – ID of node, for distributed profiling. Unset in
- **cases**. (*non-distributed*) –
- **args** (*Optional[str]*) –

Example

```
>>> # xdoctest: +REQUIRES(env:TORCH_DOCTEST_AUTOGRAD_PROFILER)
>>> x = torch.randn((1, 1), requires_grad=True)
>>> with torch.autograd.profiler.profile() as prof:
...     y = x ** 2
...     with torch.autograd.profiler.record_function("label-z"): # label the block
...         z = y ** 3
...     y.backward()
```

(continues on next page)

(continued from previous page)

```

...
>>> # xdoctest: +IGNORE_WANT
>>> # NOTE: some columns were removed for brevity
>>> print(prof.key_averages().table(sort_by="self_cpu_time_total"))

<---
Name          Self CPU total %  CPU time avg      Number of
Calls

<---
pow           60.77%        47.470us       3
mul            21.73%        25.465us       2
PowBackward@  12.03%        121.891us      1
torch::autograd::AccumulateGrad  2.70%        6.324us       1
label-z        2.13%         12.421us       1
torch::autograd::GraphRoot       0.64%        1.503us       1
<---

Self CPU time total: 234.344us
CUDA time total: 0.000us

```

Methods

`__init__(name[, args])`

`__init__(name, args=None)`

Parameters

- **name** (*str*) –
- **args** (*Optional[str]*) –

pytorch_pfn_extras.onnx

Functions

<code>pytorch_pfn_extras.onnx.annotate(**attrs)</code>	Annotation parameters to the target function.
<code>pytorch_pfn_extras.onnx.</code>	Annotation applier to the target function
<code>apply_annotation(fn, ...)</code>	
<code>pytorch_pfn_extras.onnx.as_output(name,</code>	
<code>value)</code>	
<code>pytorch_pfn_extras.onnx.export(model, args, f)</code>	Export model into ONNX Graph.
<code>pytorch_pfn_extras.onnx.export_testcase(...)</code>	Export model and I/O tensors of the model in protobuf format.
<code>pytorch_pfn_extras.onnx.grad(output, inputs)</code>	
<code>pytorch_pfn_extras.onnx.is_large_tensor(...)</code>	
<code>pytorch_pfn_extras.onnx.load_model(f[, ...])</code>	Load model from ONNX file.
<code>pytorch_pfn_extras.onnx.no_grad(fn, *args, ...)</code>	
<code>pytorch_pfn_extras.onnx.</code>	Add anchor node to the scoped modules
<code>scoped_anchor(**attrs)</code>	

pytorch_pfn_extras.onnx.annotate

`pytorch_pfn_extras.onnx.annotate(**attrs)`

Annotation parameters to the target function.

Usage:

```
>>> class Net(nn.Module):
...     def __init__(self):
...         super(Net, self).__init__()
...         self.conv = nn.Conv2d(1, 6, 3)
...         self.conv2 = nn.Conv2d(6, 12, 3)
...     def forward(self, x):
...         with pytorch_pfn_extras.onnx.annotate(key='value'):
...             h = self.conv(x)
...             h = self.conv2(h)
...         return h
```

Use this annotate function under with statement, then the first Conv operator will be emit with customized attributes. Customized attributes are invalid for ONNX format, so pay attention that some ONNX runtimes cannot run the output ONNX graph.

This annotation is enabled with either `pytorch_pfn_extras.onnx.export testcase` or `pytorch_pfn_extras.onnx.export`.

Parameters

`attrs (dict)` – annotation parameters

Return type

`AbstractContextManager[None]`

pytorch_pfn_extras.onnx.apply_annotation

`pytorch_pfn_extras.onnx.apply_annotation(fn, *args, **attrs)`

Annotation applier to the target function

Usage:

```
>>> class Net(nn.Module):
...     def __init__(self):
...         super(Net, self).__init__()
...         self.conv = nn.Conv2d(1, 6, 3)
...         self.conv2 = nn.Conv2d(6, 12, 3)
...     def forward(self, x):
...         def _conv(x):
...             h = self.conv(x)
...             return torch.relu(h)
...         h = pytorch_pfn_extras.onnx.apply_annotation(
...             _conv, key='value')
...         h = self.conv2(h)
...         return h
```

Annotate into all operators emitted from the target function even if included not `nn.Module` function. On the above code, the first Conv and ReLu operator will be emit with customized attributes. Customized attributes are invalid for ONNX format, so pay attention that some ONNX runtimes cannot run the output ONNX graph.

This applier is enabled with either `pytorch_pfn_extras.onnx.export_testcase` or `pytorch_pfn_extras.onnx.export`.

Parameters

- **fn** (*func*) – the target function to be annotated, args is used for this function. Cannot pass `kwargs` for the function.
- **args** (*tuple*) – arguments for the target function
- **attrs** (*dict*) – annotation parameters

Return type

Any

pytorch_pfn_extras.onnx.as_output

`pytorch_pfn_extras.onnx.as_output(name, value, add_identity=True)`

Parameters

- **name** (*str*) –
- **value** (*Tensor*) –
- **add_identity** (*bool*) –

Return type

Tensor

[pytorch_pfn_extras.onnx.export](#)

```
pytorch_pfn_extras.onnx.export(model, args, f, return_output=False, strip_large_tensor_data=False,  
                               large_tensor_threshold=100, **kwargs)
```

Export model into ONNX Graph.

Parameters

- **f** ([IO](#)) – A file-like object or a string file path to be written to this file.
- **return_output** (*bool*) – If True, return output values come from the model.
- **strip_large_tensor_data** (*bool*) – If True, this function will strip data of large tensors to reduce ONNX file size for benchmarking
- **large_tensor_threshold** (*int*) – If number of elements of tensor is larger than this value, the tensor is stripped when *strip_large_tensor_data* is True
- **model** (*Module*) –
- **args** (*Sequence[Any]*) –
- **kwargs** (*Any*) –

Return type

Any

Warning: This function is not thread safe.

[pytorch_pfn_extras.onnx.export_testcase](#)

```
pytorch_pfn_extras.onnx.export_testcase(model, args, out_dir, *, output_grad=False, metadata=True,  
                                         model_overwrite=True, strip_large_tensor_data=False,  
                                         large_tensor_threshold=100, return_output=False,  
                                         user_meta=None, export_torch_script=False,  
                                         export_torch_trace=False, **kwargs)
```

Export model and I/O tensors of the model in protobuf format.

Parameters

- **output_grad** (*bool or Tensor*) – If True, this function will output model's gradient with names ‘gradient_%d.pb’. If set Tensor, use it as gradient *input*. The gradient inputs are output as ‘gradient_input_%d.pb’ along with gradient.
- **metadata** (*bool*) – If True, output meta information taken from git log.
- **model_overwrite** (*bool*) – If False and model.onnx has already existed, only export input/output data as another test dataset.
- **strip_large_tensor_data** (*bool*) – If True, this function will strip data of large tensors to reduce ONNX file size for benchmarking
- **large_tensor_threshold** (*int*) – If number of elements of tensor is larger than this value, the tensor is stripped when *strip_large_tensor_data* is True
- **return_output** (*bool*) – If True, return output values come from the model.
- **export_torch_script** (*bool*) – Output model_script.pt using torch.jit.script
- **export_torch_trace** (*bool*) – Output model_trace.pt using torch.jit.trace

- **model** (*Union[Module, ScriptModule]*) –
- **args** (*Any*) –
- **out_dir** (*str*) –
- **user_meta** (*Optional[Mapping[str, Any]]*) –
- **kwargs** (*Any*) –

Return type*Any*

Warning: This function is not thread safe.

Note: When exporting a model whose forward takes keyword arguments of `torch.Tensor` type, you can pass them by putting a dict as the last element of `args`. When the keyword arguments have default values, you need to explicitly include them into the dict. Also, you must explicitly specify `input_names` that are the names of both positional and keyword arguments.

pytorch_pfn_extras.onnx.grad

```
pytorch_pfn_extras.onnx.grad(output, inputs, retain_graph=None, create_graph=False, only_inputs=True, allow_unused=False)
```

Parameters

- **output** (`Tensor`) –
- **inputs** (`Tuple[Tensor, ...]`) –
- **retain_graph** (*Optional[bool]*) –
- **create_graph** (*bool*) –
- **only_inputs** (*bool*) –
- **allow_unused** (*bool*) –

Return type*Tuple[Optional[Tensor], ...]***pytorch_pfn_extras.onnx.is_large_tensor**

```
pytorch_pfn_extras.onnx.is_large_tensor(tensor, threshold)
```

Parameters

- **tensor** (`TensorProto`) –
- **threshold** (*int*) –

Return type*bool*

[pytorch_pfn_extras.onnx.load_model](#)

`pytorch_pfn_extras.onnx.load_model(f, format=None, load_external_data=True)`

Load model from ONNX file.

This is a wrapper to `onnx.load_model` that automatically falls back to `load_external_data=False` when tensors are stripped.

Parameters

- **f** (`Union[IO, str]`) – A file-like object or a string file path to be written to this file.
- **format** (`Optional[Any]`) – A reserved arg
- **load_external_data** (`bool`) – If True and the external data under the same directory of the model, load the external data

Return type

`ModelProto`

[pytorch_pfn_extras.onnx.no_grad](#)

`pytorch_pfn_extras.onnx.no_grad(fn, *args, **kwargs)`

Parameters

- **fn** (`Callable[..., Any]`) –
- **args** (`Any`) –
- **kwargs** (`Any`) –

Return type

`Any`

[pytorch_pfn_extras.onnx.scoped_anchor](#)

`pytorch_pfn_extras.onnx.scoped_anchor(**attrs)`

Add anchor node to the scoped modules

Usage:

```
>>> class Net(nn.Module):
...     def __init__(self):
...         super(Net, self).__init__()
...         self.conv = nn.Conv2d(1, 6, 3)
...         self.conv2 = nn.Conv2d(6, 12, 3)
...     def forward(self, x):
...         with pytorch_pfn_extras.onnx.scoped_anchor(key='value'):
...             h = self.conv(x)
...             h = self.conv2(h)
...         return h
```

Use this scoped anchoring under with statement, then dummy Identity nodes are added before/after the first Conv operator with customized attributes.

This anchoring is triggered by `nn.Module` applying function, cannot use this with `torch.*` functions.

This annotation is enabled with either `pytorch_pfn_extras.onnx.export_testcase` or `pytorch_pfn_extras.onnx.export`.

Parameters

`attrs (dict)` – annotation parameters

Return type

`AbstractContextManager[None]`

Modules

<code>pytorch_pfn_extras.onnx.annotate(**attrs)</code>	Annotation parameters to the target function.
<code>pytorch_pfn_extras.onnx.export_testcase(...)</code>	Export model and I/O tensors of the model in protobuf format.
<code>pytorch_pfn_extras.onnx.load</code>	
<code>pytorch_pfn_extras.onnx.pfto_exporter</code>	
<code>pytorch_pfn_extras.onnx.strip_large_tensor</code>	
<code>pytorch_pfn_extras.onnx.symbolic_registry</code>	
<code>pytorch_pfn_extras.onnx.unstrip_tensor</code>	

pytorch_pfn_extras.onnx.load

Functions

<code>pytorch_pfn_extras.onnx.load.load_model(f[, ...])</code>	Load model from ONNX file.
--	----------------------------

pytorch_pfn_extras.onnx.load.load_model

`pytorch_pfn_extras.onnx.load.load_model(f, format=None, load_external_data=True)`

Load model from ONNX file.

This is a wrapper to `onnx.load_model` that automatically falls back to `load_external_data=False` when tensors are stripped.

Parameters

- `f (Union[IO, str])` – A file-like object or a string file path to be written to this file.
- `format (Optional[Any])` – A reserved arg
- `load_external_data (bool)` – If True and the external data under the same directory of the model, load the external data

Return type

`ModelProto`

Classes

<code>pytorch_pfn_extras.onnx.load.IO(*args, **kwds)</code>	Generic base class for TextIO and BinaryIO.
<code>pytorch_pfn_extras.onnx.load.Path(*args, ...)</code>	PurePath subclass that can make system calls.
<code>pytorch_pfn_extras.onnx.load.Text</code>	alias of <code>str</code>

`pytorch_pfn_extras.onnx.load.IO`

```
class pytorch_pfn_extras.onnx.load.IO(*args, **kwds)
```

Bases: `Generic`

Generic base class for TextIO and BinaryIO.

This is an abstract, generic version of the return of `open()`.

NOTE: This does not distinguish between the different possible classes (text vs. binary, read vs. write vs. read/write, append-only, unbuffered). The TextIO and BinaryIO subclasses below capture the distinctions between text vs. binary, which is pervasive in the interface; however we currently do not offer a way to track the other distinctions in the type system.

Methods

`__init__()`

`close()`

`fileno()`

`flush()`

`isatty()`

`read([n])`

`readable()`

`readline([limit])`

`readlines([hint])`

`seek(offset[, whence])`

`seekable()`

`tell()`

`truncate([size])`

`writable()`

`write(s)`

`writelines(lines)`

Attributes

`closed`

`mode`

`name`

`abstract close()`

Return type

None

abstract property closed: bool

```
abstract fileno()

    Return type
        int

abstract flush()

    Return type
        None

abstract isatty()

    Return type
        bool

abstract property mode: str

abstract property name: str

abstract read(n=-1)

    Parameters
        n (int) –
    Return type
        AnyStr

abstract readable()

    Return type
        bool

abstract readline(limit=-1)

    Parameters
        limit (int) –
    Return type
        AnyStr

abstract readlines(hint=-1)

    Parameters
        hint (int) –
    Return type
        List

abstract seek(offset, whence=0)

    Parameters
        • offset (int) –
        • whence (int) –
    Return type
        int

abstract seekable()

    Return type
        bool
```

```
abstract tell()

    Return type
        int

abstract truncate(size=None)

    Parameters
        size (Optional[int]) –

    Return type
        int

abstract writable()

    Return type
        bool

abstract write(s)

    Parameters
        s (AnyStr) –

    Return type
        int

abstract writelines(lines)

    Parameters
        lines (List) –

    Return type
        None
```

[pytorch_pfn_extras.onnx.load.Path](#)

```
class pytorch_pfn_extras.onnx.load.Path(*args, **kwargs)
```

Bases: PurePath

PurePath subclass that can make system calls.

Path represents a filesystem path but unlike PurePath, also offers methods to do system calls on path objects. Depending on your system, instantiating a Path will return either a PosixPath or a WindowsPath object. You can also instantiate a PosixPath or WindowsPath directly, but cannot instantiate a WindowsPath on a POSIX system or vice versa.

Construct a PurePath from one or several strings and/or existing PurePath objects. The strings and path objects are combined so as to yield a canonicalized path, which is incorporated into the new PurePath object.

Methods

<code>__init__()</code>	
<code>absolute()</code>	Return an absolute version of this path.
<code>as_posix()</code>	Return the string representation of the path with forward (/) slashes.
<code>as_uri()</code>	Return the path as a 'file' URI.
<code>chmod(mode)</code>	Change the permissions of the path, like os.chmod().
<code>cwd()</code>	Return a new path pointing to the current working directory (as returned by os.getcwd()).
<code>exists()</code>	Whether this path exists.
<code>expanduser()</code>	Return a new path with expanded ~ and ~user constructs (as returned by os.path.expanduser)
<code>glob(pattern)</code>	Iterate over this subtree and yield all existing files (of any kind, including directories) matching the given relative pattern.
<code>group()</code>	Return the group name of the file gid.
<code>home()</code>	Return a new path pointing to the user's home directory (as returned by os.path.expanduser('~')).
<code>is_absolute()</code>	True if the path is absolute (has both a root and, if applicable, a drive).
<code>is_block_device()</code>	Whether this path is a block device.
<code>is_char_device()</code>	Whether this path is a character device.
<code>is_dir()</code>	Whether this path is a directory.
<code>is_fifo()</code>	Whether this path is a FIFO.
<code>is_file()</code>	Whether this path is a regular file (also True for symbolic links pointing to regular files).
<code>is_mount()</code>	Check if this path is a POSIX mount point
<code>is_reserved()</code>	Return True if the path contains one of the special names reserved by the system, if any.
<code>is_socket()</code>	Whether this path is a socket.
<code>is_symlink()</code>	Whether this path is a symbolic link.
<code>iterdir()</code>	Iterate over the files in this directory.
<code>joinpath(*args)</code>	Combine this path with one or several arguments, and return a new path representing either a subpath (if all arguments are relative paths) or a totally different path (if one of the arguments is anchored).
<code>lchmod(mode)</code>	Like chmod(), except if the path points to a symlink, the symlink's permissions are changed, rather than its target's.
<code>link_to(target)</code>	Make the target path a hard link pointing to this path.
<code>lstat()</code>	Like stat(), except if the path points to a symlink, the symlink's status information is returned, rather than its target's.
<code>match(path_pattern)</code>	Return True if this path matches the given pattern.
<code>mkdir([mode, parents, exist_ok])</code>	Create a new directory at this given path.
<code>open([mode, buffering, encoding, errors, ...])</code>	Open the file pointed by this path and return a file object, as the built-in open() function does.
<code>owner()</code>	Return the login name of the file owner.
<code>read_bytes()</code>	Open the file in bytes mode, read it, and close the file.

continues on next page

Table 29 – continued from previous page

<code>read_text([encoding, errors])</code>	Open the file in text mode, read it, and close the file.
<code>relative_to(*other)</code>	Return the relative path to another path identified by the passed arguments.
<code>rename(target)</code>	Rename this path to the target path.
<code>replace(target)</code>	Rename this path to the target path, overwriting if that path exists.
<code>resolve([strict])</code>	Make the path absolute, resolving all symlinks on the way and also normalizing it (for example turning slashes into backslashes under Windows).
<code>rglob(pattern)</code>	Recursively yield all existing files (of any kind, including directories) matching the given relative pattern, anywhere in this subtree.
<code>rmdir()</code>	Remove this directory.
<code>samefile(other_path)</code>	Return whether other_path is the same or not as this file (as returned by os.path.samefile()).
<code>stat()</code>	Return the result of the stat() system call on this path, like os.stat() does.
<code>symlink_to(target[, target_is_directory])</code>	Make this path a symlink pointing to the target path.
<code>touch([mode, exist_ok])</code>	Create this file with the given access mode, if it doesn't exist.
<code>unlink([missing_ok])</code>	Remove this file or link.
<code>with_name(name)</code>	Return a new path with the file name changed.
<code>with_suffix(suffix)</code>	Return a new path with the file suffix changed.
<code>write_bytes(data)</code>	Open the file in bytes mode, write to it, and close the file.
<code>write_text(data[, encoding, errors])</code>	Open the file in text mode, write to it, and close the file.

Attributes

<code>anchor</code>	The concatenation of the drive and root, or <code>".</code>
<code>drive</code>	The drive prefix (letter or UNC path), if any.
<code>name</code>	The final path component, if any.
<code>parent</code>	The logical parent of the path.
<code>parents</code>	A sequence of this path's logical parents.
<code>parts</code>	An object providing sequence-like access to the components in the filesystem path.
<code>root</code>	The root of the path, if any.
<code>stem</code>	The final path component, minus its last suffix.
<code>suffix</code>	The final component's last suffix, if any.
<code>suffixes</code>	A list of the final component's suffixes, if any.

`absolute()`

Return an absolute version of this path. This function works even if the path doesn't point to anything.

No normalization is done, i.e. all `'.'` and `'..'` will be kept along. Use `resolve()` to get the canonical path to a file.

`chmod(mode)`

Change the permissions of the path, like `os.chmod()`.

classmethod cwd()

Return a new path pointing to the current working directory (as returned by os.getcwd()).

exists()

Whether this path exists.

expanduser()

Return a new path with expanded ~ and ~user constructs (as returned by os.path.expanduser)

glob(pattern)

Iterate over this subtree and yield all existing files (of any kind, including directories) matching the given relative pattern.

group()

Return the group name of the file gid.

classmethod home()

Return a new path pointing to the user's home directory (as returned by os.path.expanduser('~')).

is_block_device()

Whether this path is a block device.

is_char_device()

Whether this path is a character device.

is_dir()

Whether this path is a directory.

is_fifo()

Whether this path is a FIFO.

is_file()

Whether this path is a regular file (also True for symlinks pointing to regular files).

is_mount()

Check if this path is a POSIX mount point

is_socket()

Whether this path is a socket.

is_symlink()

Whether this path is a symbolic link.

iterdir()

Iterate over the files in this directory. Does not yield any result for the special paths '.' and '..'.

lchmod(mode)

Like chmod(), except if the path points to a symlink, the symlink's permissions are changed, rather than its target's.

link_to(target)

Make the target path a hard link pointing to this path.

Note this function does not make this path a hard link to *target*, despite the implication of the function and argument names. The order of arguments (target, link) is the reverse of Path.symlink_to, but matches that of os.link.

lstat()

Like stat(), except if the path points to a symlink, the symlink's status information is returned, rather than its target's.

mkdir(mode=511, parents=False, exist_ok=False)

Create a new directory at this given path.

open(mode='r', buffering=-1, encoding=None, errors=None, newline=None)

Open the file pointed by this path and return a file object, as the built-in open() function does.

owner()

Return the login name of the file owner.

read_bytes()

Open the file in bytes mode, read it, and close the file.

read_text(encoding=None, errors=None)

Open the file in text mode, read it, and close the file.

rename(target)

Rename this path to the target path.

The target path may be absolute or relative. Relative paths are interpreted relative to the current working directory, *not* the directory of the Path object.

Returns the new Path instance pointing to the target path.

replace(target)

Rename this path to the target path, overwriting if that path exists.

The target path may be absolute or relative. Relative paths are interpreted relative to the current working directory, *not* the directory of the Path object.

Returns the new Path instance pointing to the target path.

resolve(strict=False)

Make the path absolute, resolving all symlinks on the way and also normalizing it (for example turning slashes into backslashes under Windows).

rglob(pattern)

Recursively yield all existing files (of any kind, including directories) matching the given relative pattern, anywhere in this subtree.

rmdir()

Remove this directory. The directory must be empty.

samefile(other_path)

Return whether other_path is the same or not as this file (as returned by os.path.samefile()).

stat()

Return the result of the stat() system call on this path, like os.stat() does.

symlink_to(target, target_is_directory=False)

Make this path a symlink pointing to the target path. Note the order of arguments (link, target) is the reverse of os.symlink.

touch(mode=438, exist_ok=True)

Create this file with the given access mode, if it doesn't exist.

unlink(*missing_ok=False*)

Remove this file or link. If the path is a directory, use rmdir() instead.

write_bytes(*data*)

Open the file in bytes mode, write to it, and close the file.

write_text(*data, encoding=None, errors=None*)

Open the file in text mode, write to it, and close the file.

pytorch_pfn_extras.onnx.load.Text

pytorch_pfn_extras.onnx.load.Text

alias of `str`

pytorch_pfn_extras.onnx.pfto_exporter

Modules

`pytorch_pfn_extras.onnx.pfto_exporter.`
`export`

pytorch_pfn_extras.onnx.strip_large_tensor

Functions

`pytorch_pfn_extras.onnx.`
`strip_large_tensor.is_large_tensor(...)`

`pytorch_pfn_extras.onnx.`
`strip_large_tensor.reduce(...)`

Apply a function of two arguments cumulatively to the items of a sequence, from left to right, so as to reduce the sequence to a single value.

pytorch_pfn_extras.onnx.strip_large_tensor.is_large_tensor

`pytorch_pfn_extras.onnx.strip_large_tensor.is_large_tensor(tensor, threshold)`

Parameters

- **tensor** (`TensorProto`) –
- **threshold** (`int`) –

Return type

`bool`

pytorch_pfn_extras.onnx.strip_large_tensor.reduce

```
pytorch_pfn_extras.onnx.strip_large_tensor.reduce(function, sequence[, initial]) → value
```

Apply a function of two arguments cumulatively to the items of a sequence, from left to right, so as to reduce the sequence to a single value. For example, reduce(lambda x, y: x+y, [1, 2, 3, 4, 5]) calculates (((1+2)+3)+4)+5). If initial is present, it is placed before the items of the sequence in the calculation, and serves as a default when the sequence is empty.

pytorch_pfn_extras.onnx.symbolic_registry

Functions

```
pytorch_pfn_extras.onnx.symbolic_registry.cast(...) → value
```

```
pytorch_pfn_extras.onnx.symbolic_registry.get_registered_op(...)
```

```
pytorch_pfn_extras.onnx.symbolic_registry.is_registered_op(...)
```

```
pytorch_pfn_extras.onnx.symbolic_registry.register_op(...)
```

Classes

```
pytorch_pfn_extras.onnx.symbolic_registry.Value
```

pytorch_pfn_extras.onnx.unstrip_tensor

Functions

```
pytorch_pfn_extras.onnx.unstrip_tensor.unstrip(path) → None
```

pytorch_pfn_extras.onnx.unstrip_tensor.unstrip

```
pytorch_pfn_extras.onnx.unstrip_tensor.unstrip(path, out_path='')
```

Unstrip ONNX models and test data(.pb).

Add tensor(raw data) to the target ONNXs (and test data). Values are random following mean and variance written in meta information.

Parameters

- **path (str)** – The target directory path, ONNX file, or Tensor (Protobuf) file path.
- **out_path (str)** – Output path to be written.

Return type

None

Classes

<code>pytorch_pfn_extras.onnx.unstrip_tensor. Path(...)</code>	PurePath subclass that can make system calls.
--	---

`pytorch_pfn_extras.onnx.unstrip_tensor.Path`

`class pytorch_pfn_extras.onnx.unstrip_tensor.Path(*args, **kwargs)`

Bases: PurePath

PurePath subclass that can make system calls.

Path represents a filesystem path but unlike PurePath, also offers methods to do system calls on path objects. Depending on your system, instantiating a Path will return either a PosixPath or a WindowsPath object. You can also instantiate a PosixPath or WindowsPath directly, but cannot instantiate a WindowsPath on a POSIX system or vice versa.

Construct a PurePath from one or several strings and/or existing PurePath objects. The strings and path objects are combined so as to yield a canonicalized path, which is incorporated into the new PurePath object.

Methods

`__init__()`

<code>absolute()</code>	Return an absolute version of this path.
<code>as_posix()</code>	Return the string representation of the path with forward (/) slashes.
<code>as_uri()</code>	Return the path as a 'file' URI.
<code>chmod(mode)</code>	Change the permissions of the path, like os.chmod().
<code>cwd()</code>	Return a new path pointing to the current working directory (as returned by os.getcwd()).
<code>exists()</code>	Whether this path exists.
<code>expanduser()</code>	Return a new path with expanded ~ and ~user constructs (as returned by os.path.expanduser)
<code>glob(pattern)</code>	Iterate over this subtree and yield all existing files (of any kind, including directories) matching the given relative pattern.
<code>group()</code>	Return the group name of the file gid.
<code>home()</code>	Return a new path pointing to the user's home directory (as returned by os.path.expanduser('~/')).
<code>is_absolute()</code>	True if the path is absolute (has both a root and, if applicable, a drive).
<code>is_block_device()</code>	Whether this path is a block device.
<code>is_char_device()</code>	Whether this path is a character device.
<code>is_dir()</code>	Whether this path is a directory.
<code>is_fifo()</code>	Whether this path is a FIFO.
<code>is_file()</code>	Whether this path is a regular file (also True for symbolic links pointing to regular files).
<code>is_mount()</code>	Check if this path is a POSIX mount point

continues on next page

Table 30 – continued from previous page

<code>is_reserved()</code>	Return True if the path contains one of the special names reserved by the system, if any.
<code>is_socket()</code>	Whether this path is a socket.
<code>is_symlink()</code>	Whether this path is a symbolic link.
<code>iterdir()</code>	Iterate over the files in this directory.
<code>joinpath(*args)</code>	Combine this path with one or several arguments, and return a new path representing either a subpath (if all arguments are relative paths) or a totally different path (if one of the arguments is anchored).
<code>lchmod(mode)</code>	Like chmod(), except if the path points to a symlink, the symlink's permissions are changed, rather than its target's.
<code>link_to(target)</code>	Make the target path a hard link pointing to this path.
<code>lstat()</code>	Like stat(), except if the path points to a symlink, the symlink's status information is returned, rather than its target's.
<code>match(path_pattern)</code>	Return True if this path matches the given pattern.
<code>mkdir([mode, parents, exist_ok])</code>	Create a new directory at this given path.
<code>open([mode, buffering, encoding, errors, ...])</code>	Open the file pointed by this path and return a file object, as the built-in open() function does.
<code>owner()</code>	Return the login name of the file owner.
<code>read_bytes()</code>	Open the file in bytes mode, read it, and close the file.
<code>read_text([encoding, errors])</code>	Open the file in text mode, read it, and close the file.
<code>relative_to(*other)</code>	Return the relative path to another path identified by the passed arguments.
<code>rename(target)</code>	Rename this path to the target path.
<code>replace(target)</code>	Rename this path to the target path, overwriting if that path exists.
<code>resolve([strict])</code>	Make the path absolute, resolving all symlinks on the way and also normalizing it (for example turning slashes into backslashes under Windows).
<code>rglob(pattern)</code>	Recursively yield all existing files (of any kind, including directories) matching the given relative pattern, anywhere in this subtree.
<code>rmdir()</code>	Remove this directory.
<code>samefile(other_path)</code>	Return whether other_path is the same or not as this file (as returned by os.path.samefile()).
<code>stat()</code>	Return the result of the stat() system call on this path, like os.stat() does.
<code>symlink_to(target[, target_is_directory])</code>	Make this path a symlink pointing to the target path.
<code>touch([mode, exist_ok])</code>	Create this file with the given access mode, if it doesn't exist.
<code>unlink([missing_ok])</code>	Remove this file or link.
<code>with_name(name)</code>	Return a new path with the file name changed.
<code>with_suffix(suffix)</code>	Return a new path with the file suffix changed.
<code>write_bytes(data)</code>	Open the file in bytes mode, write to it, and close the file.
<code>write_text(data[, encoding, errors])</code>	Open the file in text mode, write to it, and close the file.

Attributes

<code>anchor</code>	The concatenation of the drive and root, or <code>"</code> .
<code>drive</code>	The drive prefix (letter or UNC path), if any.
<code>name</code>	The final path component, if any.
<code>parent</code>	The logical parent of the path.
<code>parents</code>	A sequence of this path's logical parents.
<code>parts</code>	An object providing sequence-like access to the components in the filesystem path.
<code>root</code>	The root of the path, if any.
<code>stem</code>	The final path component, minus its last suffix.
<code>suffix</code>	The final component's last suffix, if any.
<code>suffixes</code>	A list of the final component's suffixes, if any.

`absolute()`

Return an absolute version of this path. This function works even if the path doesn't point to anything.

No normalization is done, i.e. all `'.'` and `'..'` will be kept along. Use `resolve()` to get the canonical path to a file.

`chmod(mode)`

Change the permissions of the path, like `os.chmod()`.

`classmethod cwd()`

Return a new path pointing to the current working directory (as returned by `os.getcwd()`).

`exists()`

Whether this path exists.

`expanduser()`

Return a new path with expanded `~` and `~user` constructs (as returned by `os.path.expanduser()`)

`glob(pattern)`

Iterate over this subtree and yield all existing files (of any kind, including directories) matching the given relative pattern.

`group()`

Return the group name of the file gid.

`classmethod home()`

Return a new path pointing to the user's home directory (as returned by `os.path.expanduser('~')`).

`is_block_device()`

Whether this path is a block device.

`is_char_device()`

Whether this path is a character device.

`is_dir()`

Whether this path is a directory.

`is_fifo()`

Whether this path is a FIFO.

`is_file()`

Whether this path is a regular file (also True for symlinks pointing to regular files).

is_mount()

Check if this path is a POSIX mount point

is_socket()

Whether this path is a socket.

is_symlink()

Whether this path is a symbolic link.

iterdir()

Iterate over the files in this directory. Does not yield any result for the special paths ‘.’ and ‘..’.

lchmod(mode)

Like chmod(), except if the path points to a symlink, the symlink’s permissions are changed, rather than its target’s.

link_to(target)

Make the target path a hard link pointing to this path.

Note this function does not make this path a hard link to *target*, despite the implication of the function and argument names. The order of arguments (target, link) is the reverse of Path.symlink_to, but matches that of os.link.

lstat()

Like stat(), except if the path points to a symlink, the symlink’s status information is returned, rather than its target’s.

mkdir(mode=511, parents=False, exist_ok=False)

Create a new directory at this given path.

open(mode='r', buffering=-1, encoding=None, errors=None, newline=None)

Open the file pointed by this path and return a file object, as the built-in open() function does.

owner()

Return the login name of the file owner.

read_bytes()

Open the file in bytes mode, read it, and close the file.

read_text(encoding=None, errors=None)

Open the file in text mode, read it, and close the file.

rename(target)

Rename this path to the target path.

The target path may be absolute or relative. Relative paths are interpreted relative to the current working directory, *not* the directory of the Path object.

Returns the new Path instance pointing to the target path.

replace(target)

Rename this path to the target path, overwriting if that path exists.

The target path may be absolute or relative. Relative paths are interpreted relative to the current working directory, *not* the directory of the Path object.

Returns the new Path instance pointing to the target path.

resolve(*strict=False*)

Make the path absolute, resolving all symlinks on the way and also normalizing it (for example turning slashes into backslashes under Windows).

rglob(*pattern*)

Recursively yield all existing files (of any kind, including directories) matching the given relative pattern, anywhere in this subtree.

rmdir()

Remove this directory. The directory must be empty.

samefile(*other_path*)

Return whether other_path is the same or not as this file (as returned by os.path.samefile()).

stat()

Return the result of the stat() system call on this path, like os.stat() does.

symlink_to(*target*, *target_is_directory=False*)

Make this path a symlink pointing to the target path. Note the order of arguments (link, target) is the reverse of os.symlink.

touch(*mode=438*, *exist_ok=True*)

Create this file with the given access mode, if it doesn't exist.

unlink(*missing_ok=False*)

Remove this file or link. If the path is a directory, use rmdir() instead.

write_bytes(*data*)

Open the file in bytes mode, write to it, and close the file.

write_text(*data*, *encoding=None*, *errors=None*)

Open the file in text mode, write to it, and close the file.

pytorch_pfn_extras.profiler

Functions

`pytorch_pfn_extras.profiler.`

`get_time_summary()`

`pytorch_pfn_extras.profiler.record(tag[, ...])`

`pytorch_pfn_extras.profiler.`

`record_function(tag)`

`pytorch_pfn_extras.profiler.`

`record_iterable(...)`

pytorch_pfn_extras.profiler.get_time_summary

```
pytorch_pfn_extras.profiler.get_time_summary()
```

Return type

TimeSummary

pytorch_pfn_extras.profiler.record

```
pytorch_pfn_extras.profiler.record(tag=None, metric=None, use_cuda=False, enable=True, device='cpu')
```

Parameters

- **tag** (*Optional[str]*) –
- **metric** (*Optional[str]*) –
- **use_cuda** (*bool*) –
- **enable** (*bool*) –
- **device** (*DeviceLike*) –

Return type

Generator[_ReportNotification, None, None]

pytorch_pfn_extras.profiler.record_function

```
pytorch_pfn_extras.profiler.record_function(tag, use_cuda=False, enable=True)
```

Parameters

- **tag** (*Optional[str]*) –
- **use_cuda** (*bool*) –
- **enable** (*bool*) –

Return type

Callable[[Callable[[], _T]], Callable[[], _T]]

pytorch_pfn_extras.profiler.record_iterable

```
pytorch_pfn_extras.profiler.record_iterable(tag, iter, divide_metric=False, use_cuda=False, enable=True)
```

Parameters

- **tag** (*Optional[str]*) –
- **iter** (*Iterable[_T]*) –
- **divide_metric** (*bool*) –
- **use_cuda** (*bool*) –
- **enable** (*bool*) –

Return type

Iterable[_T]

Classes

`pytorch_pfn_extras.profiler.TimeSummary(*[, ...])` Online summarization of execution times.

`pytorch_pfn_extras.profiler.TimeSummary`

`class pytorch_pfn_extras.profiler.TimeSummary(*, max_queue_size=1000, auto_init=True)`

Bases: `object`

Online summarization of execution times.

`TimeSummary` computes the average and standard deviation of execution times in both cpu and gpu devices.

Parameters

- `max_queue_size (int)` – Length limit of the internal queues that keep reported time info until they are summarized.
- `auto_init (bool)` – Whether to automatically call `initialize()` when the instance is created.

Methods

`__init__(*[, max_queue_size, auto_init])`

`add(name, value)`

`complete_report(tag, use_cuda, begin_event, ...)`

`finalize()`

`initialize()` Initializes the worker threads for `TimeSummary`.

`report(tag[, use_cuda])` Context manager to automatically report execution times.

`summary([clear])`

`synchronize()`

`__init__(*, max_queue_size=1000, auto_init=True)`

Parameters

- `max_queue_size (int)` –
- `auto_init (bool)` –

Return type

`None`

`add(name, value)`

Parameters

- **name** (*str*) –
- **value** (*float*) –

Return type

None

complete_report(*tag*, *use_cuda*, *begin_event*, *begin*)**Parameters**

- **tag** (*str*) –
- **use_cuda** (*bool*) –
- **begin_event** (*Optional[Event]*) –
- **begin** (*float*) –

Return type

None

finalize()**Return type**

None

initialize()

Initializes the worker threads for TimeSummary.

Usually you do not have to call it for yourself. However in case you directly use `ppe.time_summary` outside of `pytorch_pfn_extras.training.extensions.ProfileReport`, you have to explicitly call `initialize()` in advance.

Return type

None

report(*tag*, *use_cuda=False*)

Context manager to automatically report execution times.

The start and completion times are obtained automatically, the user only needs to provide a tag to identify the value in the summary values.

Parameters

- **tag** (*str*) – A name to identify the section of code being profiled.
- **use_cuda** (*bool*) – Indicates if GPU time should also be profiled.

Return type`Generator[_ReportNotification, None, None]`**summary**(*clear=False*)**Parameters****clear** (*bool*) –**Return type**`Generator[Tuple[DictSummary, Dict[str, float]], None, None]`**synchronize()****Return type**

None

[pytorch_pfn_extras.reporting](#)

Functions

<code>pytorch_pfn_extras.reporting.get_current_reporter()</code>	Returns the current reporter object.
<code>pytorch_pfn_extras.reporting.overload(func)</code>	Decorator for overloaded functions/methods.
<code>pytorch_pfn_extras.reporting.report(values)</code>	Reports observed values with the current reporter object.
<code>pytorch_pfn_extras.reporting.report_scope(...)</code>	Returns a report scope with the current reporter.

[pytorch_pfn_extras.reporting.get_current_reporter](#)

`pytorch_pfn_extras.reporting.get_current_reporter()`

Returns the current reporter object.

Return type

Reporter

[pytorch_pfn_extras.reporting.overload](#)

`pytorch_pfn_extras.reporting.overload(func)`

Decorator for overloaded functions/methods.

In a stub file, place two or more stub definitions for the same function in a row, each decorated with @overload. For example:

```
@overload def utf8(value: None) -> None: ...
@overload def utf8(value: bytes) -> bytes: ...
@overload def utf8(value: str) -> bytes: ...
```

In a non-stub file (i.e. a regular .py file), do the same but follow it with an implementation. The implementation should *not* be decorated with @overload. For example:

```
@overload def utf8(value: None) -> None: ...
@overload def utf8(value: bytes) -> bytes: ...
@overload def utf8(value: str) -> bytes: ...
def utf8(value):
    # implementation goes here
```

[pytorch_pfn_extras.reporting.report](#)

`pytorch_pfn_extras.reporting.report(values, observer=None)`

Reports observed values with the current reporter object.

Any reporter object can be set current by the `with` statement. This function calls the `Reporter.report()` method of the current reporter. If no reporter object is current, this function does nothing.

Example

The most typical example is a use within `nn.Module`. Suppose that a module is registered to the current reporter as an observer (for example, the target module of the optimizer is automatically registered to the main reporter). We can report some values from the link as follows:

```

class MyRegressor:
    def __init__(self, predictor):
        super().__init__(predictor=predictor)

    def __call__(self, x, y):
        # This chain just computes the mean absolute and squared
        # errors between the prediction and y.
        pred = self.predictor(x)
        abs_error = F.sum(abs(pred - y)) / len(x)
        loss = F.mean_squared_error(pred, y)

        # Report the mean absolute and squared errors.
        reporter.report({
            'abs_error': abs_error,
            'squared_error': loss,
        }, self)

    return loss

```

If the module is named 'main' in the hierarchy these reported values are named 'main/abs_error' and 'main/squared_error'.

Parameters

- **values** (*dict*) – Dictionary of observed values.
- **observer** (*Optional[Module]*) – Observer object. Its object ID is used to retrieve the observer name, which is used as the prefix of the registration name of the observed value.

Return type

None

pytorch_pfn_extras.reporting.report_scope

`pytorch_pfn_extras.reporting.report_scope(observation)`

Returns a report scope with the current reporter.

This is equivalent to `get_current_reporter().scope(observation)`, except that it does not make the reporter current redundantly.

Parameters

observation (*Dict[str, Union[Tensor, ndarray, floating, float, Callable[[], float]]]*) –

Return type

Generator[None, None, None]

Classes

<code>pytorch_pfn_extras.reporting.DictSummary()</code>	Online summarization of a sequence of dictionaries.
<code>pytorch_pfn_extras.reporting.Reporter()</code>	Object to which observed values are reported.
<code>pytorch_pfn_extras.reporting.Summary()</code>	Online summarization of a sequence of scalars.

`pytorch_pfn_extras.reporting.DictSummary`

```
class pytorch_pfn_extras.reporting.DictSummary
```

Bases: `object`

Online summarization of a sequence of dictionaries.

`DictSummary` computes the statistics of a given set of scalars online. It only computes the statistics for scalar values and variables of scalar values in the dictionaries.

Methods

`__init__()`

<code>add(d)</code>	Adds a dictionary of scalars.
<code>compute_mean()</code>	Creates a dictionary of mean values.
<code>load_state_dict(to_load)</code>	
<code>make_statistics()</code>	Creates a dictionary of statistics.
<code>state_dict()</code>	

`__init__()`

Return type

`None`

`add(d)`

Adds a dictionary of scalars.

Parameters

`d(dict)` – Dictionary of scalars to accumulate. Only elements of scalars, zero-dimensional arrays, and variables of zero-dimensional arrays are accumulated. When the value is a tuple, the second element is interpreted as a weight.

Return type

`None`

`compute_mean()`

Creates a dictionary of mean values.

It returns a single dictionary that holds a mean value for each entry added to the summary.

Returns

Dictionary of mean values.

Return type
dict

load_state_dict(to_load)

Parameters
`to_load (Dict[str, Any]) –`

Return type
None

make_statistics()

Creates a dictionary of statistics.

It returns a single dictionary that holds mean and standard deviation values for every entry added to the summary. For an entry of name 'key', these values are added to the dictionary by names 'key' and 'key.std', respectively.

Returns
Dictionary of statistics of all entries.

Return type
dict

state_dict()

Return type
`Dict[str, Any]`

pytorch_pfn_extras.reporting.Reporter

class `pytorch_pfn_extras.reporting.Reporter`

Bases: `object`

Object to which observed values are reported.

Reporter is used to collect values that users want to watch. The reporter object holds a mapping from value names to the actually observed values. We call this mapping *observations*.

When a value is passed to the reporter, an object called *observer* can be optionally attached. In this case, the name of the observer is added as the prefix of the value name. The observer name should be registered beforehand.

See the following example:

```
>>> from pytorch_pfn_extras.reporting import Reporter, report, report_scope
>>>
>>> reporter = Reporter()
>>> observer = object() # it can be an arbitrary (reference) object
>>> reporter.add_observer('my_observer', observer)
>>> observation = {}
>>> with reporter.scope(observation):
...     reporter.report({'x': 1}, observer)
...
>>> observation
{'my_observer/x': 1}
```

There are also a global API to add values:

```
>>> reporter = Reporter()
>>> observation = {}
>>> with reporter:
...     with report_scope(observation):
...         report({'x': 1})
...
>>> observation
{'x': 1}
```

The most important application of Reporter is to report observed values from each link or chain in the training and validation procedures. and some extensions prepare their own Reporter object with the hierarchy of the target module registered as observers. We can use `report()` function inside any nn.Module to report the observed values (e.g., training loss, accuracy, activation statistics, etc.).

observation

Dictionary of observed values.

Methods

`__init__()`

<code>add_observer(name, observer)</code>	Registers an observer of values.
<code>add_observers(prefix, observers)</code>	Registers multiple observers at once.
<code>report(values[, observer])</code>	Reports observed values.
<code>scope(observation)</code>	Creates a scope to report observed values to <code>observation</code> .

`__init__()`

Return type

None

`add_observer(name, observer)`

Registers an observer of values.

Observer defines a scope of names for observed values. Values observed with the observer are registered with names prefixed by the observer name.

Parameters

- **name** (*str*) – Name of the observer.
- **observer** (*Module*) – The observer object. Note that the reporter distinguishes the observers by their object ids (i.e., `id(owner)`), rather than the object equality.

Return type

None

`add_observers(prefix, observers)`

Registers multiple observers at once.

This is a convenient method to register multiple objects at once.

Parameters

- **prefix** (*str*) – Prefix of each name of observers.
- **observers** (*Sequence[Tuple[str, Module]]*) – Iterator of name and observer pairs.

Return type

None

report(*values*, *observer*=*None*)

Reports observed values.

The values are written with the key, prefixed by the name of the observer object if given.

Note: If a value is of type Tensor, the variable is copied without preserving the computational graph and the new variable object purged from the graph is stored to the observer.

Parameters

- **values** (*dict*) – Dictionary of observed values.
- **observer** (*Optional[Module]*) – Observer object. Its object ID is used to retrieve the observer name, which is used as the prefix of the registration name of the observed value.

Return type

None

scope(*observation*)Creates a scope to report observed values to *observation*.This is a context manager to be passed to `with` statements. In this scope, the observation dictionary is changed to the given one.

It also makes this reporter object current.

Parameters

observation (*dict*) – Observation dictionary. All observations reported inside of the `with` statement are written to this dictionary.

Return type*Generator[None, None, None]*

[pytorch_pfn_extras.reporting.Summary](#)

class `pytorch_pfn_extras.reporting.Summary`Bases: `object`

Online summarization of a sequence of scalars.

Summary computes the statistics of given scalars online.

Methods

`__init__()`

<code>add(value[, weight])</code>	Adds a scalar value.
<code>compute_mean()</code>	Computes the mean.
<code>load_state_dict(to_load)</code>	
<code>make_statistics()</code>	Computes and returns the mean and standard deviation values.
<code>state_dict()</code>	

`__init__()`

Return type

None

`add(value, weight=1)`

Adds a scalar value.

Parameters

- **value** (*Union[Tensor, ndarray, floating, float, Callable[[], float]]*) – Scalar value to accumulate. It is either a NumPy scalar or a zero-dimensional array (on CPU or GPU).
- **weight** (*Union[Tensor, ndarray, floating, float]*) – An optional weight for the value. It is a NumPy scalar or a zero-dimensional array (on CPU or GPU). Default is 1 (integer).

Return type

None

`compute_mean()`

Computes the mean.

Return type

Union[Tensor, ndarray, floating, float]

`load_state_dict(to_load)`

Parameters

`to_load(Dict[str, Any])` –

Return type

None

`make_statistics()`

Computes and returns the mean and standard deviation values.

Returns

Mean and standard deviation values.

Return type

tuple

state_dict()**Return type***Dict[str, Any]***pytorch_pfn_extras.runtime****Classes**

<i>pytorch_pfn_extras.runtime.BaseRuntime(...)</i>	A base class for collections of device-specific callback functions.
<i>pytorch_pfn_extras.runtime.PyTorchRuntime(...)</i>	A collections of callback functions for the devices that PyTorch supports by default.

pytorch_pfn_extras.runtime.BaseRuntime**class** *pytorch_pfn_extras.runtime.BaseRuntime*(*device_spec, options*)Bases: *object*

A base class for collections of device-specific callback functions.

The function attributes of this class will be called from *ppe.to* or *ppe.handler.Handler*.*ppe.runtime.runtime_registry* stores the runtime classes and dispatches them by feeding the corresponding name string as an input.**Parameters**

- **device_spec** (*torch.device or str*) – The device that modules and tensors are transferred to.
- **options** (*dict*) – A configuration dictionary that can be used from runtime method.

Methods

`__init__(device_spec, options)`

<code>convert_batch(args)</code>	Transfers the given batch to the specific device.
<code>eval_post_step(evaluator, module, batch_idx, ...)</code>	The method called at the end of each evaluation.
<code>eval_pre_step(evaluator, module, batch_idx, ...)</code>	The method called at the beginning of each evaluation.
<code>execute(code_block, batch)</code>	Method called by the CodeBlocks API to do device dependent execution.
<code>initialize_module(module, loader_or_batch[, ...])</code>	Initializes the module at the beginning of training or inference.
<code>map(func, iterable[, out_keys, device])</code>	Method called by the user to apply function to iterable efficiently.
<code>move_module(module)</code>	Transfers the module to the specific device.
<code>move_tensor(tensor)</code>	Transfers the tensor to the specific device.
<code>trace(event_name, arg)</code>	Context manager for tracing PPE events in the custom device tools.
<code>train_cleanup(module)</code>	A method called only once when completing a training run.
<code>train_epoch_begin(module)</code>	Preprocess of each epoch.
<code>train_epoch_end(module)</code>	Completion of each epoch.
<code>train_post_step(trainer, module, batch_idx, ...)</code>	Postprocess of each step.
<code>train_pre_step(trainer, module, batch_idx, batch)</code>	Preprocess of each step.
<code>train_validation_begin(module)</code>	The method called before each evaluation.
<code>train_validation_end(module)</code>	The method called after each evaluation.

`__init__(device_spec, options)`

Parameters

- **device_spec** (*Union[str, device]*) –
- **options** (*Dict[str, Any]*) –

Return type

None

`convert_batch(args)`

Transfers the given batch to the specific device.

Parameters

args (*object*) – A batch data of any type.

Returns

A batch data transferred to the specific device of the same type as input.

Return type

Any

`eval_post_step(evaluator, module, batch_idx, batch, outs)`

The method called at the end of each evaluation.

Parameters

- **evaluator** (*Evaluator*) – An evaluator.
- **module** (*torch.nn.Module*) – A module.

- **batch_idx** (*int*) – The batch index.
- **batch** (*list of torch.Tensor*) – The list of input tensors of this batch.
- **outs** (*Any*) – (*list of torch.Tensor*): The list of output tensors of this batch.

Return type

None

Returns: None

eval_pre_step(*evaluator, module, batch_idx, batch*)

The method called at the beginning of each evaluation.

Parameters

- **evaluator** ([Evaluator](#)) – An evaluator.
- **module** ([torch.nn.Module](#)) – A module.
- **batch_idx** (*int*) – The batch index.
- **batch** (*list of torch.Tensor*) – The list of input tensors of this batch.

Return type

None

Returns: None

execute(*code_block, batch*)

Method called by the CodeBlocks API to do device dependent execution.

Parameters

- **code_block** ([CodeBlock](#)) – The codeblock requesting execution.
- **batch** (*dict of str, torch.Tensor*) – The input tensors of this batch.

Returns

The results of executing the codeblock on this runtime.

Return type

Any

initialize_module(*module, loader_or_batch, optimizer=None*)

Initializes the module at the beginning of training or inference.

Parameters

- **module** ([torch.nn.Module](#)) – A module.
- **loader_or_batch** ([DataLoader](#) or [torch.Tensor](#)) – A data loader or a tensor.
- **optimizer** (*Optimizer or None*) – An optimizer. This argument is sometimes used to copy LR from the original optimizer to the training model.

Return type

None

Returns: None

map(*func, iterable, out_keys=None, device='cpu'*)

Method called by the user to apply function to iterable efficiently.

Parameters

- **func** ([CodeBlock](#)) – The function to be executed

- **iterable** (*Iterable[Any]*) – The data
- **out_keys** (*Optional[Set[str]]*) – The output keys that to be moved to the host device
- **device** (*Any*) – The torch device that contains the final outputs

Returns

The result of *func*

Return type

Iterable[Any]

move_module(*module*)

Transfers the module to the specific device.

Before this method is called, `ppe.to` will add this class as an new attribute (“_ppe_runtime”) to the input module.

Parameters

module (`torch.nn.Module`) – A module.

Returns

A module transferred to the specific device.

Return type

Module

move_tensor(*tensor*)

Transfers the tensor to the specific device.

Parameters

tensor (`torch.Tensor`) – A tensor.

Returns

A tensor transferred to the specific device.

Return type

Tensor

classmethod trace(*event_name, arg*)

Context manager for tracing PPE events in the custom device tools.

Parameters

- **event_name** (*Optional[str]*) – The name of the event being traced
- **arg** (*Any*) – Custom argument for the tracer

Return type

Generator[None, None, None]

train_cleanup(*module*)

A method called only once when compleing a training run.

Parameters

module (`torch.nn.Module`) – A module.

Return type

None

Returns: None

train_epoch_begin(module)

Preprocess of each epoch.

Parameters

module (`torch.nn.Module`) – A module.

Return type

None

Returns: None

train_epoch_end(module)

Completion of each epoch.

Parameters

module (`torch.nn.Module`) – A module.

Return type

None

Returns: None

train_post_step(trainer, module, batch_idx, batch, outs)

Postprocess of each step.

This method is called at the end of every steps: the set of (typically one) iterations and an update.

Parameters

- **trainer** (`Trainer`) – A trainer.
- **module** (`torch.nn.Module`) – A module.
- **batch_idx** (`int`) – The batch index.
- **batch** (`list of torch.Tensor`) – The list of input tensors of this batch.
- **outs** (`Any`) – (`list of torch.Tensor`): The list of output tensors of this batch.

Return type

None

Returns: None

train_pre_step(trainer, module, batch_idx, batch)

Preprocess of each step.

This method is called at the beginning of every steps: the set of (typically one) iterations and an update.

Parameters

- **trainer** (`Trainer`) – A trainer.
- **module** (`torch.nn.Module`) – A module.
- **batch_idx** (`int`) – The batch index.
- **batch** (`list of torch.Tensor`) – The list of input tensors of this batch.

Return type

None

Returns: None

train_validation_begin(module)

The method called before each evaluation.

Parameters

module (`torch.nn.Module`) – A module.

Return type

None

Returns: None

train_validation_end(module)

The method called after each evaluation.

Parameters

module (`torch.nn.Module`) – A module.

Return type

None

Returns: None

pytorch_pfn_extras.runtime.PyTorchRuntime

class pytorch_pfn_extras.runtime.PyTorchRuntime(device_spec, options)

Bases: `BaseRuntime`

A collections of callback functions for the devices that PyTorch supports by default.

Parameters

- **device_spec** (`torch.device or str`) – The device.
- **options** (`dict, optional`) – The configuration options.
 - **'autocast'** (`bool or dict`):
If True, `torch.cuda.amp.autocast` is enabled. using `{"enabled": True, "device_type": "cuda"}` as autocast options. Default is False which corresponds to the following options `{"enabled": False, "device_type": "cuda"}`. If dict, Options to pass to `torch.autocast`. Includes `device_type`, `dtype` among others.
 - **'grad_scaler'** (`torch.cuda.amp.GradScaler`):
A gradient scaler that outputs are applied to.

Methods

`__init__(device_spec, options)`

<code>convert_batch(args)</code>	Transfers the given batch to the specific device.
<code>eval_post_step(evaluator, module, batch_idx, ...)</code>	The method called at the end of each evaluation.
<code>eval_pre_step(evaluator, module, batch_idx, ...)</code>	The method called at the beginning of each evaluation.
<code>execute(code_block, batch)</code>	Method called by the CodeBlocks API to do device dependent execution.
<code>initialize_module(module, loader_or_batch[, ...])</code>	Initializes the module at the beginning of training or inference.
<code>map(func, iterable[, out_keys, device])</code>	Method called by the user to apply function to iterable efficiently.
<code>move_module(module)</code>	Transfers the module to the specific device.
<code>move_tensor(tensor)</code>	Transfers the tensor to the specific device.
<code>trace(event_name, arg)</code>	Context manager for tracing PPE events in the custom device tools.
<code>train_cleanup(module)</code>	A method called only once when completing a training run.
<code>train_epoch_begin(module)</code>	Preprocess of each epoch.
<code>train_epoch_end(module)</code>	Completion of each epoch.
<code>train_post_step(trainer, module, batch_idx, ...)</code>	Postprocess of each step.
<code>train_pre_step(trainer, module, batch_idx, batch)</code>	Preprocess of each step.
<code>train_validation_begin(module)</code>	The method called before each evaluation.
<code>train_validation_end(module)</code>	The method called after each evaluation.

`__init__(device_spec, options)`

Parameters

- `device_spec (Union[str, device])` –
- `options (Dict[str, Any])` –

Return type

None

`eval_post_step(evaluator, module, batch_idx, batch, outs)`

The method called at the end of each evaluation.

Parameters

- `evaluator (Evaluator)` – An evaluator.
- `module (torch.nn.Module)` – A module.
- `batch_idx (int)` – The batch index.
- `batch (list of torch.Tensor)` – The list of input tensors of this batch.
- `outs (Any)` – (list of torch.Tensor): The list of output tensors of this batch.

Return type

None

Returns: None

eval_pre_step(*evaluator, module, batch_idx, batch*)

The method called at the beginning of each evaluation.

Parameters

- **evaluator** ([Evaluator](#)) – An evaluator.
- **module** ([torch.nn.Module](#)) – A module.
- **batch_idx** ([int](#)) – The batch index.
- **batch** ([list of torch.Tensor](#)) – The list of input tensors of this batch.

Return type

None

Returns: None

execute(*code_block, batch*)

Method called by the CodeBlocks API to do device dependent execution.

Parameters

- **code_block** ([CodeBlock](#)) – The codeblock requesting execution.
- **batch** ([dict of str, torch.Tensor](#)) – The input tensors of this batch.

Returns

The results of executing the codeblock on this runtime.

Return type

Any

initialize_module(*module, loader_or_batch, optimizer=None*)

Initializes the module at the beginning of training or inference.

Parameters

- **module** ([torch.nn.Module](#)) – A module.
- **loader_or_batch** ([DataLoader](#) or [torch.Tensor](#)) – A data loader or a tensor.
- **optimizer** ([Optimizer](#) or [None](#)) – An optimizer. This argument is sometimes used to copy LR from the original optimizer to the training model.

Return type

None

Returns: None

map(*func, iterable, out_keys=None, device='cpu'*)

Method called by the user to apply function to iterable efficiently.

Parameters

- **func** ([CodeBlock](#)) – The function to be executed
- **iterable** ([Iterable\[Any\]](#)) – The data
- **out_keys** ([Optional\[Set\[str\]\]](#)) – The output keys that to be moved to the host device
- **device** ([Any](#)) – The torch device that contains the final outputs

Returns

The result of *func*

Return type*Iterable[Any]***move_module(module)**

Transfers the module to the specific device.

Before this method is called, `ppe.to` will add this class as an new attribute (“`_ppe_runtime`”) to the input module.

Parameters`module (torch.nn.Module)` – A module.**Returns***A module transferred to the specific device.***Return type***Module***move_tensor(tensor)**

Transfers the tensor to the specific device.

Parameters`tensor (torch.Tensor)` – A tensor.**Returns***A tensor transferred to the specific device.***Return type***Tensor***classmethod trace(event_name, arg)**

Context manager for tracing PPE events in the custom device tools.

Parameters

- `event_name (Optional[str])` – The name of the event being traced
- `arg (Any)` – Custom argument for the tracer

Return type*Generator[None, None, None]***train_cleanup(module)**

A method called only once when compleing a training run.

Parameters`module (torch.nn.Module)` – A module.**Return type***None*

Returns: None

train_epoch_begin(module)

Preprocess of each epoch.

Parameters`module (torch.nn.Module)` – A module.**Return type***None*

Returns: None

train_epoch_end(*module*)

Completion of each epoch.

Parameters

module (`torch.nn.Module`) – A module.

Return type

None

Returns: None

train_post_step(*trainer*, *module*, *batch_idx*, *batch*, *outs*)

Postprocess of each step.

This method is called at the end of every steps: the set of (typically one) iterations and an update.

Parameters

- **trainer** (`Trainer`) – A trainer.
- **module** (`torch.nn.Module`) – A module.
- **batch_idx** (`int`) – The batch index.
- **batch** (`list of torch.Tensor`) – The list of input tensors of this batch.
- **outs** (`Any`) – (list of `torch.Tensor`): The list of output tensors of this batch.

Return type

None

Returns: None

train_pre_step(*trainer*, *module*, *batch_idx*, *batch*)

Preprocess of each step.

This method is called at the beginning of every steps: the set of (typically one) iterations and an update.

Parameters

- **trainer** (`Trainer`) – A trainer.
- **module** (`torch.nn.Module`) – A module.
- **batch_idx** (`int`) – The batch index.
- **batch** (`list of torch.Tensor`) – The list of input tensors of this batch.

Return type

None

Returns: None

train_validation_begin(*module*)

The method called before each evaluation.

Parameters

module (`torch.nn.Module`) – A module.

Return type

None

Returns: None

train_validation_end(*module*)

The method called after each evaluation.

Parameters

module (`torch.nn.Module`) – A module.

Return type

None

Returns: None

pytorch_pfn_extras.testing**pytorch_pfn_extras.torchscript****Functions**

`pytorch_pfn_extras.torchscript.`

`find_inplace(g)`

`pytorch_pfn_extras.torchscript.`

`run_jit_pass(p, ...)`

pytorch_pfn_extras.torchscript.find_inplace

`pytorch_pfn_extras.torchscript.find_inplace(g)`

Parameters

g (`Graph`) –

Return type

`Tuple[Graph, List[Node]]`

pytorch_pfn_extras.torchscript.run_jit_pass

`pytorch_pfn_extras.torchscript.run_jit_pass(p, g, *args, **kwargs)`

Parameters

- **p** (`Callable`) –

- **g** (`Graph`) –

- **args** (`Any`) –

- **kwargs** (`Any`) –

Return type

None

[pytorch_pfn_extras.training](#)

Functions

<code>pytorch_pfn_extras.training. make_extension(...)</code>	Decorator to make given function into an extension.
---	---

[pytorch_pfn_extras.training.make_extension](#)

`pytorch_pfn_extras.training.make_extension(trigger=(1, 'iteration'), default_name=None, priority=100,
finalizer=<function <lambda>>, initializer=<function
<lambda>>, on_error=<function <lambda>>)`

Decorator to make given function into an extension.

This decorator just adds some attributes to a given function. The value of the attributes are given by the arguments of this decorator.

See [Extension](#) for details of extensions. Most of the default values of arguments also follow those for this class.

Parameters

- **trigger** (`TriggerLike`) – Default trigger of the extension.
- **default_name** (`Optional[str]`) – Default name of the extension. The name of a given function is used by default.
- **priority** (`int`) – Default priority of the extension.
- **finalizer** (`ExtensionLike`) – Finalizer function of this extension. It is called at the end of the training loop.
- **initializer** (`ExtensionLike`) – Initializer function of this extension. It is called at the beginning of the training loop.
- **on_error** (`Callable[[ExtensionsManagerProtocol, Exception,
TracebackType], None]`) – Error handler callback function of this extension. It is called after an error is raised during the training loop.

Return type

`Callable[[ExtensionLike], ExtensionLike]`

Classes

<code>pytorch_pfn_extras.training.</code>	A metric for an evaluator to report accuracy.
<code>AccuracyMetric(...)</code>	
<code>pytorch_pfn_extras.training.</code>	
<code>DistributedEvaluator(...)</code>	
<code>pytorch_pfn_extras.training.Evaluator(...[, ...])</code>	
<code>pytorch_pfn_extras.training.Extension()</code>	Base class of extensions.
<code>pytorch_pfn_extras.training.</code>	
<code>ExtensionEntry(...)</code>	Extension and options.
<code>pytorch_pfn_extras.training.</code>	
<code>ExtensionsManager(...)</code>	Manages the extensions and the current status.
<code>pytorch_pfn_extras.training.</code>	
<code>ExtensionsManagerProtocol(...)</code>	
<code>pytorch_pfn_extras.training.</code>	
<code>IgniteExtensionsManager(...)</code>	Manages extensions and the current status in Ignite training loop.
<code>pytorch_pfn_extras.training.</code>	
<code>StateObjectProtocol(...)</code>	
<code>pytorch_pfn_extras.training.Trainer(handler, ...)</code>	

`pytorch_pfn_extras.training.AccuracyMetric`

```
class pytorch_pfn_extras.training.AccuracyMetric(label_key, output_key)
```

Bases: object

A metric for an evaluator to report accuracy.

Parameters

- **label_key (str)** – The key name of label.
- **output_key (str)** – The key name of prediction.

Methods

`__init__(label_key, output_key)`

`__call__(batch, out)`

Call self as a function.

Parameters

- **batch (Dict[str, Tensor])** –
- **out (Dict[str, Tensor])** –

Return type

`Dict[str, Any]`

`__init__(label_key, output_key)`

Parameters

- **label_key** (*str*) –
- **output_key** (*str*) –

Return type

`None`

[pytorch_pfn_extras.training.DistributedEvaluator](#)

```
class pytorch_pfn_extras.training.DistributedEvaluator(handler, models, *, progress_bar=False,  
metrics=None)
```

Bases: *Evaluator*

Methods

`__init__(handler, models, *[, progress_bar, ...])`

`run(loader, *[, eval_len])` Executes the evaluation loop.

Parameters

- **handler** (*BaseHandler*) –
- **models** (*Union[Module, Mapping[str, Module]]*) –
- **progress_bar** (*bool*) –
- **metrics** (*Optional[Sequence[MetricType]]*) –

`__init__(handler, models, *, progress_bar=False, metrics=None)`

Parameters

- **handler** (*BaseHandler*) –
- **models** (*Union[Module, Mapping[str, Module]]*) –
- **progress_bar** (*bool*) –
- **metrics** (*Optional[Sequence[MetricType]]*) –

[pytorch_pfn_extras.training.Evaluator](#)

```
class pytorch_pfn_extras.training.Evaluator(handler, models, *, progress_bar=False, metrics=None,  
profile=None)
```

Bases: *object*

Methods

`__init__(handler, models, *[, progress_bar, ...])`

`run(loader, *[, eval_len])` Executes the evaluation loop.

Parameters

- **handler** (`BaseHandler`) –
- **models** (`Union[Module, Mapping[str, Module]]`) –
- **progress_bar** (`bool`) –
- **metrics** (`Optional[Sequence[MetricType]]`) –
- **profile** (`Optional[profile]`) –

`__init__(handler, models, *, progress_bar=False, metrics=None, profile=None)`

Parameters

- **handler** (`BaseHandler`) –
- **models** (`Union[Module, Mapping[str, Module]]`) –
- **progress_bar** (`bool`) –
- **metrics** (`Optional[Sequence[MetricType]]`) –
- **profile** (`Optional[profile]`) –

`run(loader, *, eval_len=None)`

Executes the evaluation loop.

Parameters

- **loader** (`torch.utils.data.DataLoader`) – A data loader for evaluation.
- **eval_len** (`int, optional`) – The number of iterations per one evaluation epoch.

Return type

None

pytorch_pfn_extras.training.Extension

`class pytorch_pfn_extras.training.Extension`

Bases: `object`

Base class of extensions.

An extension is a callable object that takes the manager object as the argument. It also provides some default configurations as its attributes, e.g. the default trigger and the default priority. This class provides a set of typical default values for these attributes.

There are three ways to define users' own extensions: inheriting this class, decorating closures by `make_extension()`, or using any callable including lambda functions as extensions. Decorator can slightly reduce the overhead and is much easier to use, while this class provides more flexibility (for example, it can have methods to configure the behavior). Using a lambda function allows one-line coding for simple purposes, but users have to specify the configurations as arguments to `ExtensionsManager.extend()`. For a callable not

inheriting this class, the default configurations of this class are used unless the user explicitly specifies them in `ExtensionsManager.extend()` method.

trigger

Default value of trigger for this extension. It is set to (1, 'iteration') by default.

Type

TriggerLike

priority

Default priority of the extension. It is set to PRIORITY_READER by default.

Type

int

~Extension.name

Name of the extension. It is set to None by default. This value will be overwritten when registering an extension to a manager. See `pytorch_pfn_extras.ExtensionsManager.extend()` for details.

Methods

__init__()

<code>finalize(manager)</code>	Finalizes the extension.
<code>initialize(manager)</code>	Initializes up the manager state.
<code>load_state_dict(to_load)</code>	
<code>on_error(manager, exc, tb)</code>	Handles the error raised during training before finalization.
<code>state_dict()</code>	Serializes the extension state.

Attributes

<code>default_name</code>	Default name of the extension.
<code>is_async</code>	
<code>name</code>	
<code>needs_model_state</code>	
<code>priority</code>	
<code>trigger</code>	

__call__(manager)

Invokes the extension.

Implementations should override this operator. This method is called at iterations which the corresponding trigger accepts.

Parameters

`manager` (`ExtensionsManager`) – Manager object to call this operator.

Return type*Any***property default_name: str**

Default name of the extension.

It is the name of the class by default. Implementation can override this property, or provide a class attribute to hide it.

finalize(manager)

Finalizes the extension.

This method is called at the end of the training loop.

Parameters**manager** (`ExtensionsManagerProtocol`) –**Return type***None***initialize(manager)**

Initializes up the manager state.

This method is called before entering the training loop. An extension modifying the state of `ExtensionsManager` can override this method to initialize it.

When the manager has been restored from a snapshot, this method has to recover an appropriate part of the state of the manager.

Parameters**manager** (`ExtensionsManager`) – Manager object to call this extension.**Return type***None***is_async = False****load_state_dict(to_load)****Parameters****to_load** (`Dict[str, Any]`) –**Return type***None***name: Optional[str] = None****needs_model_state = False****on_error(manager, exc, tb)**

Handles the error raised during training before finalization.

This method is called when an exception is thrown during the training loop, before finalize. An extension that needs different error handling from finalize, can override this method to handle errors.

Parameters

- **manager** (`ExtensionsManager`) –
- **extension.** (*Manager object to call this*) –
- **exc** (`Exception`) – arbitrary exception thrown during update loop.
- **tb** (`traceback`) – traceback object of the exception

Return type

None

priority: `int = 100`

state_dict()

Serializes the extension state.

It is called when a manager that owns this extension is serialized. It serializes nothing by default.

Return type

`Dict[str, Any]`

trigger: `TriggerLike = (1, 'iteration')`

[pytorch_pfn_extras.training.ExtensionEntry](#)

```
class pytorch_pfn_extras.training.ExtensionEntry(extension, *, name=None, priority=None,
                                                trigger=None, call_before_training=False)
```

Bases: `object`

Extension and options. When name, priority, or trigger is not specified, it is copied from the attributes of the given extension.

Parameters

- **extension** (`ExtensionLike`) – An extension.
- **name** (`Optional[str]`) – Name of extension.
- **priority** (`Optional[int]`) – Invocation priority of the extension.
- **trigger** (`Optional[TriggerLike]`) – Trigger object that determines when to invoke the extension.
- **call_before_training** (`bool`) – Flag to call extension before training.

See also:

`pytorch_pfn_extras.training.ExtensionsManager.extend()`

Methods

`__init__(extension, *[name, priority, ...])`

`load_state_dict(to_load)`

`state_dict()`

`__init__(extension, *, name=None, priority=None, trigger=None, call_before_training=False)`

Parameters

- **extension** (`ExtensionLike`) –
- **name** (`Optional[str]`) –
- **priority** (`Optional[int]`) –

- **trigger** (*Optional[TriggerLike]*) –
- **call_before_training** (*bool*) –

Return type

None

load_state_dict(*to_load*)**Parameters**

- to_load** (*Dict[str, Any]*) –

Return type

None

state_dict()**Return type***Dict[str, Any]***pytorch_pfn_extras.training.ExtensionsManager**

```
class pytorch_pfn_extras.training.ExtensionsManager(models, optimizers, max_epochs, *,  
                                                 iters_per_epoch, extensions=None,  
                                                 out_dir='result', stop_trigger=None,  
                                                 writer=None, transform_model=<function  
                                                 ExtensionsManager.<lambda>>,  
                                                 enable_profile=False, state_objects={})
```

Bases: `_BaseExtensionsManager`

Manages the extensions and the current status.

Parameters

- **models** (dict or *torch.nn.Module*) – Map of string to Module or an actual Module
- **optimizers** (dict or *torch.Optimizer*) – Map of string to Optimizer or an actual Optimizer.
- **max_epochs** (*int*) – Number of epochs in the whole training loop. Ignored if *stop_trigger* is passed as a kwarg.
- **iters_per_epoch** (*int*) – Number of iterations in one epoch.
- **extensions** (*list or None*) – List of Extentions to be used.
- **out_dir** (*str*) – Output directory (default: `result`).
- **stop_trigger** (*trigger object, optional*) – to determine wether training has concluded. The default is an interval trigger set to *max_epochs*
- **writer** (*writing.Writer object*) – Writer that can be used by extensions to write data to custom filesystems.
- **enable_profile** (*bool*) – Flag to enable/disable profiling of iterations. Default is *False*.
- **transform_model** (*Callable[[str, Module], Module]*) –
- **state_objects** (*Dict[str, StateObjectProtocol]*) –

Methods

<code>__init__(models, optimizers, max_epochs, *, ...)</code>	
<code>extend(extension[, name, trigger, priority, ...])</code>	Registers an extension to the manager.
<code>finalize()</code>	
<code>get_extension(name)</code>	Returns the extension of a given name.
<code>load_state_dict(to_load)</code>	
<code>needs_model_state([iteration])</code>	
<code>needs_state_this_iteration()</code>	
<code>run_extensions()</code>	
<code>run_iteration(*[, step_optimizers])</code>	Context manager to run an iteration.
<code>start_extensions()</code>	
<code>state_dict()</code>	

Attributes

<code>elapsed_time</code>
<code>epoch</code>
<code>epoch_detail</code>
<code>is_before_training</code>
<code>iteration</code>
<code>models</code>
<code>optimizers</code>
<code>out</code>
<code>raw_models</code>
<code>stop_trigger</code>
<code>updater</code>
<code>__init__(models, optimizers, max_epochs, *, iters_per_epoch, extensions=None, out_dir='result', stop_trigger=None, writer=None, transform_model=<function ExtensionsManager.<lambda>>, enable_profile=False, state_objects={})</code>

Parameters

- **models** (*Union[Module, Dict[str, Module]]*) –
- **optimizers** (*Union[Optimizer, Dict[str, Optimizer]]*) –
- **max_epochs** (*int*) –
- **iters_per_epoch** (*int*) –
- **extensions** (*Optional[Sequence[extension_module.ExtensionLike]]*) –
- **out_dir** (*str*) –
- **stop_trigger** (*trigger_module.TriggerLike*) –
- **writer** (*Optional[Writer]*) –
- **transform_model** (*Callable[[str, Module], Module]*) –
- **enable_profile** (*bool*) –
- **state_objects** (*Dict[str, StateObjectProtocol]*) –

Return type

None

finalize()**Return type**

None

run_iteration(*, step_optimizers=None)

Context manager to run an iteration.

This manager can additionally run a step in the specified optimizers names.

Parameters

- **step_optimizers** (*list or None*) – names of the optimizers
- **step** (*to call zero_grad and*) –

Return type*Generator[None, None, None]***pytorch_pfn_extras.training.ExtensionsManagerProtocol****class pytorch_pfn_extras.training.ExtensionsManagerProtocol(*args, **kwargs)**

Bases: Protocol

Methods

__init__(*args, **kwargs)

get_extension(name)

Attributes

```
elapsed_time
epoch
epoch_detail
is_before_training
iteration
models
observation
optimizers
out
raw_models
reporter
stop_trigger
writer
```

```
__init__(*args, **kwargs)
property elapsed_time: float
property epoch: int
property epoch_detail: float
get_extension(name)

    Parameters
        name (str) ->

    Return type
        Extension

    property is_before_training: bool
    property iteration: int
    property models: Mapping[str, Module]
    property observation: reporting.Observation
    property optimizers: Mapping[str, Optimizer]
```

```
property out: str
property raw_models: Mapping[str, Module]
property reporter: reporting.Reporter
property stop_trigger: bool
property writer: Optional[writing.Writer]
```

pytorch_pfn_extras.training.IgniteExtensionsManager

```
class pytorch_pfn_extras.training.IgniteExtensionsManager(engine, models, optimizers, max_epochs,
*, extensions=None, out_dir='result',
writer=None, enable_profile=False,
state_objects={})
```

Bases: _BaseExtensionsManager

Manages extensions and the current status in Ignite training loop.

Parameters

- **engine** (*ignite.engine.Engine*) – Ignite trainer engine
- **models** (*dict or torch.nn.Module*) – Map of string to Module or an actual Module
- **optimizers** (*dict or torch.Optimizer*) – Map of string to Optimizer or an actual Optimizer.
- **max_epochs** (*int*) – Number of epochs in the whole training loop.
- **extensions** (*list or None*) – List of Extentions to be used.
- **out_dir** (*str*) – Output directory (default: `result`).
- **writer** (*writing.Writer object*) – Writer that can be used by extensions to write data to custom filesystems.
- **enable_profile** (*bool*) – Flag to enable/disable profiling of iterations. Default is *False*.
- **state_objects** (*Dict[str, StateObjectProtocol]*) –

Methods

```
__init__(engine, models, optimizers, ...[, ...])
```

```
extend(extension[, name, trigger, priority, ...]) Registers an extension to the manager.
```

```
get_extension(name) Returns the extension of a given name.
```

```
load_state_dict(to_load)
```

```
needs_model_state([iteration])
```

```
needs_state_this_iteration()
```

```
run_extensions()
```

```
set_ignite_handlers()
```

```
start_extensions()
```

```
state_dict()
```

Attributes

```
elapsed_time
```

```
epoch
```

```
epoch_detail
```

```
is_before_training
```

```
iteration
```

```
models
```

```
optimizers
```

```
out
```

```
raw_models
```

```
stop_trigger
```

```
updater
```

```
__init__(engine, models, optimizers, max_epochs, *, extensions=None, out_dir='result', writer=None,
        enable_profile=False, state_objects={})
```

Parameters

- **engine** (`ignite.engine.Engine`) –
- **models** (`Union[Module, Mapping[str, Module]]`) –
- **optimizers** (`Union[Optimizer, Mapping[str, Optimizer]]`) –
- **max_epochs** (`int`) –
- **extensions** (`Optional[Sequence[extension_module.ExtensionLike]]`) –
- **out_dir** (`str`) –
- **writer** (`Optional[Writer]`) –
- **enable_profile** (`bool`) –
- **state_objects** (`Dict[str, StateObjectProtocol]`) –

Return type

None

load_state_dict(`to_load`)**Parameters**`to_load` (`Dict[str, Any]`) –**Return type**

None

set_ignite_handlers()**Return type**

None

state_dict()**Return type**`Dict[str, Any]`**pytorch_pfn_extras.training.StateObjectProtocol****class** `pytorch_pfn_extras.training.StateObjectProtocol`(*args, **kwargs)Bases: `Protocol`**Methods**

`__init__`(*args, **kwargs)

`load_state_dict`(`state_dict`)

`state_dict`()

`__init__`(*args, **kwargs)

`load_state_dict(state_dict)`

Parameters

`state_dict (Dict[str, Any]) –`

Return type

`None`

`state_dict()`

Return type

`Dict[str, Any]`

[pytorch_pfn_extras.training.Trainer](#)

`class pytorch_pfn_extras.training.Trainer(handler, *, evaluator, models, profile=None, **kwargs)`

Bases: `object`

Methods

`__init__(handler, *, evaluator, models[, ...])`

`extend(extension[, name, trigger, priority, ...])`

`get_optimizer(name)`

`is_epoch_last_iter(idx)`

`load_state_dict(to_load)`

`run(train_loader[, val_loader, train_len, ...])` Executes the training loop.

`set_optimizer(name, optimizer)`

`state_dict()`

Attributes

`epoch`
`epoch_detail`
`evaluator`
`is_before_training`
`iteration`
`manager`
`models`
`optimizers`
`stop_trigger`

Parameters

- **handler** (`handler_module.BaseHandler`) –
- **evaluator** (`Optional[Union[Evaluator, Tuple[Evaluator, Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]]], Mapping[str, Union[Evaluator, Tuple[Evaluator, Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]]]]]]`) –
- **models** (`Union[Module, Mapping[str, Module]]`) –
- **profile** (`Optional[profile]`) –
- **kwargs** (`Any`) –

`__init__(handler, *, evaluator, models, profile=None, **kwargs)`

Parameters

- **handler** (`handler_module.BaseHandler`) –
- **evaluator** (`Optional[Union[Evaluator, Tuple[Evaluator, Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]]], Mapping[str, Union[Evaluator, Tuple[Evaluator, Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]]]]]]`) –
- **models** (`Union[Module, Mapping[str, Module]]`) –
- **profile** (`Optional[profile]`) –
- **kwargs** (`Any`) –

`property epoch: int`

```
property epoch_detail: float
property evaluator: Optional[Evaluator]
extend(extension, name=None, trigger=None, priority=None, *, call_before_training=False, **kwargs)

Parameters
    • extension (Union[extension.ExtensionLike, ExtensionEntry]) –
    • name (Optional[str]) –
    • trigger (TriggerLike) –
    • priority (Optional[int]) –
    • call_before_training (bool) –
    • kwargs (Any) –

Return type
None

get_optimizer(name)

Parameters
    name (str) –

Return type
Optimizer

property is_before_training: bool

is_epoch_last_iter(idx)

Parameters
    idx (int) –

Return type
bool

property iteration: int

load_state_dict(to_load)

Parameters
    to_load (Dict[str, Any]) –

Return type
None

property manager: ExtensionsManager

property models: Mapping[str, Module]

property optimizers: Mapping[str, Optimizer]

run(train_loader, val_loader=None, *, train_len=None, eval_len=None)
    Executes the training loop.

Parameters
    • train_loader (torch.utils.data.DataLoader) – A data loader for training.
```

- **val_loader** (`torch.utils.data.DataLoader`, *optional*) – A data loader passed to `Evaluator.run()`.
- **train_len** (`int`, *optional*) – The number of iterations per one training epoch. The default value is inferred from the size of training data loader.
- **eval_len** (`int`, *optional*) – The number of iterations per one evaluation epoch, passed to `Evaluator.run()`

Return type

None

See also:

- `pytorch_pfn_extras.training._evaluator.Evaluator()`

`set_optimizer(name, optimizer)`**Parameters**

- **name** (`str`) –
- **optimizer** (`Optimizer`) –

Return type

None

`state_dict()`**Return type***Dict[str, Any]*`property stop_trigger: Trigger`**Modules**

`pytorch_pfn_extras.training.extension`

`pytorch_pfn_extras.training.extensions`

`pytorch_pfn_extras.training.manager`

`pytorch_pfn_extras.training.metrics`

`pytorch_pfn_extras.training.trigger`

`pytorch_pfn_extras.training.triggers`

[pytorch_pfn_extras.training.extension](#)

Functions

<code>pytorch_pfn_extras.training.extension. make_extension(...)</code>	Decorator to make given function into an extension.
---	---

[pytorch_pfn_extras.training.extension.make_extension](#)

`pytorch_pfn_extras.training.extension.make_extension(trigger=(1, 'iteration'), default_name=None,
priority=100, finalizer=<function <lambda>>,
initializer=<function <lambda>>,
on_error=<function <lambda>>)`

Decorator to make given function into an extension.

This decorator just adds some attributes to a given function. The value of the attributes are given by the arguments of this decorator.

See [Extension](#) for details of extensions. Most of the default values of arguments also follow those for this class.

Parameters

- **trigger** (*TriggerLike*) – Default trigger of the extension.
- **default_name** (*Optional[str]*) – Default name of the extension. The name of a given function is used by default.
- **priority** (*int*) – Default priority of the extension.
- **finalizer** (*ExtensionLike*) – Finalizer function of this extension. It is called at the end of the training loop.
- **initializer** (*ExtensionLike*) – Initializer function of this extension. It is called at the beginning of the training loop.
- **on_error** (*Callable[[ExtensionsManagerProtocol, Exception,
TracebackType], None]*) – Error handler callback function of this extension. It is called after an error is raised during the training loop.

Return type

Callable[[ExtensionLike], ExtensionLike]

Classes

<code>pytorch_pfn_extras.training.extension. Extension()</code>	Base class of extensions.
---	---------------------------

<code>pytorch_pfn_extras.training.extension. ExtensionEntry(...)</code>	Extension and options.
---	------------------------

<code>pytorch_pfn_extras.training.extension. ExtensionsManagerProtocol(...)</code>
--

pytorch_pfn_extras.training.extension.Extension

```
class pytorch_pfn_extras.training.extension.Extension
```

Bases: object

Base class of extensions.

An extension is a callable object that takes the manager object as the argument. It also provides some default configurations as its attributes, e.g. the default trigger and the default priority. This class provides a set of typical default values for these attributes.

There are three ways to define users' own extensions: inheriting this class, decorating closures by [make_extension\(\)](#), or using any callable including lambda functions as extensions. Decorator can slightly reduce the overhead and is much easier to use, while this class provides more flexibility (for example, it can have methods to configure the behavior). Using a lambda function allows one-line coding for simple purposes, but users have to specify the configurations as arguments to `ExtensionsManager.extend()`. For a callable not inheriting this class, the default configurations of this class are used unless the user explicitly specifies them in `ExtensionsManager.extend()` method.

trigger

Default value of trigger for this extension. It is set to `(1, 'iteration')` by default.

Type

TriggerLike

priority

Default priority of the extension. It is set to `PRIORITY_READER` by default.

Type

int

~Extension.name

Name of the extension. It is set to `None` by default. This value will be overwritten when registering an extension to a manager. See `pytorch_pfn_extras.ExtensionsManager.extend()` for details.

Methods

__init__()

<code>finalize(manager)</code>	Finalizes the extension.
<code>initialize(manager)</code>	Initializes up the manager state.
<code>load_state_dict(to_load)</code>	
<code>on_error(manager, exc, tb)</code>	Handles the error raised during training before finalization.
<code>state_dict()</code>	Serializes the extension state.

Attributes

<code>default_name</code>	Default name of the extension.
<code>is_async</code>	
<code>name</code>	
<code>needs_model_state</code>	
<code>priority</code>	
<code>trigger</code>	

`__call__(manager)`

Invokes the extension.

Implementations should override this operator. This method is called at iterations which the corresponding trigger accepts.

Parameters

`manager` ([ExtensionsManager](#)) – Manager object to call this operator.

Return type

`Any`

`property default_name: str`

Default name of the extension.

It is the name of the class by default. Implementation can override this property, or provide a class attribute to hide it.

`finalize(manager)`

Finalizes the extension.

This method is called at the end of the training loop.

Parameters

`manager` ([ExtensionsManagerProtocol](#)) –

Return type

`None`

`initialize(manager)`

Initializes up the manager state.

This method is called before entering the training loop. An extension modifying the state of `ExtensionsManager` can override this method to initialize it.

When the manager has been restored from a snapshot, this method has to recover an appropriate part of the state of the manager.

Parameters

`manager` ([ExtensionsManager](#)) – Manager object to call this extension.

Return type

`None`

```
is_async = False
load_state_dict(to_load)

    Parameters
        to_load(Dict[str, Any]) –
    Return type
        None
name: Optional[str] = None
needs_model_state = False
on_error(manager, exc, tb)
    Handles the error raised during training before finalization.

    This method is called when an exception is thrown during the training loop, before finalize. An extension
    that needs different error handling from finalize, can override this method to handle errors.

    Parameters
        • manager(ExtensionsManager) –
        • extension.(Manager object to call this) –
        • exc(Exception) – arbitrary exception thrown during update loop.
        • tb(traceback) – traceback object of the exception

    Return type
        None
priority: int = 100
state_dict()
    Serializes the extension state.

    It is called when a manager that owns this extension is serialized. It serializes nothing by default.

    Return type
        Dict[str, Any]
trigger: TriggerLike = (1, 'iteration')
```

pytorch_pfn_extras.training.extension.ExtensionEntry

```
class pytorch_pfn_extras.training.extension.ExtensionEntry(extension, *, name=None,
                                                       priority=None, trigger=None,
                                                       call_before_training=False)
```

Bases: object

Extension and options. When name, priority, or trigger is not specified, it is copied from the attributes of the given extension.

Parameters

- **extension**(ExtensionLike) – An extension.
- **name**(Optional[str]) – Name of extension.
- **priority**(Optional[int]) – Invocation priority of the extension.

- **trigger** (*Optional[TriggerLike]*) – Trigger object that determines when to invoke the extension.
- **call_before_training** (*bool*) – Flag to call extension before training.

See also:

`pytorch_pfn_extras.training.ExtensionsManager.extend()`

Methods

`__init__(extension, *[name, priority, ...])`

`load_state_dict(to_load)`

`state_dict()`

`__init__(extension, *, name=None, priority=None, trigger=None, call_before_training=False)`

Parameters

- **extension** (*ExtensionLike*) –
- **name** (*Optional[str]*) –
- **priority** (*Optional[int]*) –
- **trigger** (*Optional[TriggerLike]*) –
- **call_before_training** (*bool*) –

Return type

None

`load_state_dict(to_load)`

Parameters

`to_load(Dict[str, Any])` –

Return type

None

`state_dict()`

Return type

`Dict[str, Any]`

`pytorch_pfn_extras.training.extension.ExtensionsManagerProtocol`

`class pytorch_pfn_extras.training.extension.ExtensionsManagerProtocol(*args, **kwargs)`
Bases: `Protocol`

Methods

```
__init__(*args, **kwargs)
```

```
get_extension(name)
```

Attributes

```
elapsed_time
```

```
epoch
```

```
epoch_detail
```

```
is_before_training
```

```
iteration
```

```
models
```

```
observation
```

```
optimizers
```

```
out
```

```
raw_models
```

```
reporter
```

```
stop_trigger
```

```
writer
```

```
__init__(*args, **kwargs)
```

```
property elapsed_time: float
```

```
property epoch: int
```

```
property epoch_detail: float
```

```
get_extension(name)
```

Parameters

name (*str*) –

Return type

Extension

```
property is_before_training: bool
property iteration: int
property models: Mapping[str, Module]
property observation: reporting.Observation
property optimizers: Mapping[str, Optimizer]
property out: str
property raw_models: Mapping[str, Module]
property reporter: reporting.Reporter
property stop_trigger: bool
property writer: Optional[writing.Writer]
```

pytorch_pfn_extras.training.extensions

Functions

<code>pytorch_pfn_extras.training.extensions.observe_lr(...)</code>	Returns an extension to record the learning rate.
<code>pytorch_pfn_extras.training.extensions.observe_value(...)</code>	Returns an extension to continuously record a value.
<code>pytorch_pfn_extras.training.extensions.snapshot([...])</code>	Returns a trainer extension to take snapshots of the trainer.
<code>pytorch_pfn_extras.training.extensions.snapshot_object(...)</code>	Returns an extension to take snapshots of a given object.

pytorch_pfn_extras.training.extensions.observe_lr

`pytorch_pfn_extras.training.extensions.observe_lr(optimizer, param_group=0, observation_key='lr')`

Returns an extension to record the learning rate.

Parameters

- **optimizer** (`Optimizer`) – Optimizer whose learning rate is recorded.
- **param_group** (`int`) – Param group of the optimizer to observe
- **observation_key** (`str`) – Key of observation to record.

Returns

The extension function.

Return type

`Any`

This extension is triggered each epoch by default. To change this, use the `trigger` argument with the `ExtensionsManager.extend()` method.

pytorch_pfn_extras.training.extensions.observe_value

`pytorch_pfn_extras.training.extensions.observe_value(observation_key, target_func)`

Returns an extension to continuously record a value.

Parameters

- **observation_key** (`str`) – Key of observation to record.
- **target_func** (`function`) – Function that returns the value to record. It must take one argument: :class:`~pytorch_pfn_extras.training.ExtensionsManager` object.

Returns

The extension function.

Return type

`Callable[[ExtensionsManagerProtocol], None]`

This extension is triggered each epoch by default. To change this, use the `trigger` argument with the `ExtensionsManager.extend()` method.

pytorch_pfn_extras.training.extensions.snapshot

`pytorch_pfn_extras.training.extensions.snapshot(savefun=None, filename='snapshot_iter_{.iteration}', *, target=None, condition=None, writer=None, snapshot_on_error=False, n_retains=-1, autoload=False, saver_rank=None)`

Returns a trainer extension to take snapshots of the trainer.

This extension serializes the manager object and saves it to the output directory. It is used to support resuming the training loop from the saved state.

This extension is called once per epoch by default. To take a snapshot at a different interval, a trigger object specifying the required interval can be passed along with this extension to the `extend()` method of the manager.

The default priority is -100, which is lower than that of most built-in extensions.

Parameters

- **savefun** (*Optional[Any]*) – Function to save the manager. It takes two arguments: the output file path and the manager object. It is `torch.save()` by default. If `writer` is specified, this argument must be `None`.
- **filename** (`str`) – Name of the file into which the manager is serialized. It can be a format string, where the manager object is passed to the `str.format()` method.
- **target** (*Optional[Any]*) – Object to serialize. If it is not specified, it will be the manager object.
- **condition** (*Optional[Any]*) – Condition object. It must be a callable object that returns boolean without any arguments. If it returns `True`, the snapshot will be done. If not, it will be skipped. The default is a function that always returns `True`.
- **writer** (*Optional[Writer]*) – Writer object. It must be a callable object. See below for the list of built-in writers. If `savefun` is other than `None`, this argument must be `None`. In that case, a `SimpleWriter` object instantiated with specified `savefun` argument will be used.
- **snapshot_on_error** (`bool`) – Whether to take a snapshot in case training loop has been failed.

- **n_retains** (*int*) – Number of snapshot files to retain through the cleanup. Must be a positive integer for any cleanup to take place. Automatic deletion of old snapshots only works when the filename is string.
- **autoload** (*bool*) – With this enabled, the extension automatically finds the latest snapshot and loads the data to the target. Automatic loading only works when the filename is a string. It is assumed that snapshots are generated by `torch.save()`.
- **saver_rank** (*int*) – If defined, the snapshot will be taken by only one rank when running in distributed mode and restored by all.

Returns

Snapshot extension object.

Return type

`_Snapshot`

Using asynchronous writers

By specifying `writer` argument, writing operations can be made asynchronous, hiding I/O overhead of snapshots.

```
>>> from pytorch_pfn_extras.training import extensions
>>> from pytorch_pfn_extras import writing
>>> writer = writing.ProcessWriter()
>>> manager.extend(extensions.snapshot(writer=writer), trigger=(1, 'epoch'))
```

To change the format, you can pass a saving function as `savefun` argument of the writer.

```
>>> from pytorch_pfn_extras.training import extensions
>>> from pytorch_pfn_extras import writing
>>> writer = writing.ProcessWriter(
...     savefun=torch.save)
>>> manager.extend(extensions.snapshot(writer=writer), trigger=(1, 'epoch'))
```

This is the list of built-in snapshot writers.

- `pytorch_pfn_extras.writing.SimpleWriter`
- `pytorch_pfn_extras.writing.ThreadWriter`
- `pytorch_pfn_extras.writing.ProcessWriter`
- `pytorch_pfn_extras.writing.ThreadQueueWriter`
- `pytorch_pfn_extras.writing.ProcessQueueWriter`

See also:

- `pytorch_pfn_extras.training.extensions.snapshot_object()`

pytorch_pfn_extras.training.extensions.snapshot_object

```
pytorch_pfn_extras.training.extensions.snapshot_object(target, filename, savefun=None, *,  
                                                       condition=None, writer=None,  
                                                       snapshot_on_error=False, n_retains=-1,  
                                                       autoload=False)
```

Returns an extension to take snapshots of a given object.

This extension serializes the given object and saves it to the output directory.

This extension is called once per epoch by default. To take a snapshot at a different interval, a trigger object specifying the required interval can be passed along with this extension to the `extend()` method of the manager.

The default priority is lower than that of most built-in extensions.

Parameters

- **target** (*Any*) – Object to serialize.
- **filename** (*str*) – Name of the file into which the object is serialized. It can be a format string, where the manager object is passed to the `str.format()` method. For example, '`'snapshot_{.iteration}'`' is converted to '`'snapshot_10000'`' at the 10,000th iteration.
- **savefun** (*Optional[Any]*) – Function to save the object. It takes two arguments: the output file path and the object to serialize.
- **condition** – Condition object. It must be a callable object that returns boolean without any arguments. If it returns True, the snapshot will be done. If not, it will be skipped. The default is a function that always returns True.
- **writer** – Writer object. It must be a callable object. See below for the list of built-in writers. If `savefun` is other than None, this argument must be None. In that case, a `SimpleWriter` object instantiated with specified `savefun` argument will be used.
- **snapshot_on_error** (*bool*) – Whether to take a snapshot in case training loop has failed.
- **n_retains** (*int*) – Number of snapshot files to retain through the cleanup. Must be a positive integer for any cleanup to take place. Automatic deletion of old snapshots only works when the filename is string.
- **autoload** (*bool*) – With this enabled, the extension automatically finds the latest snapshot and loads the data to the target. Automatic loading only works when the filename is a string.
- **saver_rank** (*int*) – If defined, the snapshot will be taken by only one rank when running in distributed mode and restored by all.
- **kwargs** (*Any*) –

Returns

Snapshot extension object.

Return type

`_Snapshot`

See also:

- [pytorch_pfn_extras.training.extensions.snapshot\(\)](#)

Classes

<code>pytorch_pfn_extras.training.extensions.BestValue(...)</code>	Extension traces the best value of a specific key in the observation.
<code>pytorch_pfn_extras.training.extensions.DistributedEvaluator(...)</code>	An extension to evaluate models on a validation set in a distributed training setup.
<code>pytorch_pfn_extras.training.extensions.Evaluator(...)</code>	An extension to evaluate models on a validation set.
<code>pytorch_pfn_extras.training.extensions.FailOnNonNumber(*)</code>	An extension to raise RuntimeError if parameters and its gradients contain NaN or Inf.
<code>pytorch_pfn_extras.training.extensions.IgniteEvaluator(...)</code>	
<code>pytorch_pfn_extras.training.extensions.LRScheduler(...)</code>	Trainer extension to adjust the learning rate using PyTorch's learning rate scheduler.
<code>pytorch_pfn_extras.training.extensions.LogReport([...])</code>	An extension to output the accumulated results to a log file.
<code>pytorch_pfn_extras.training.extensions.MaxValue(key)</code>	Extension traces the maximum value of a specific key in the observation.
<code>pytorch_pfn_extras.training.extensions.MicroAverage(...)</code>	Calculates micro-average ratio.
<code>pytorch_pfn_extras.training.extensions.MinValue(key)</code>	Extension traces the minimum value of a specific key in the observation.
<code>pytorch_pfn_extras.training.extensions.ParameterStatistics(links)</code>	An extension to report parameter statistics.
<code>pytorch_pfn_extras.training.extensions.PlotReport(y_keys)</code>	An extension to output plots.
<code>pytorch_pfn_extras.training.extensions.PrintReport([...])</code>	An extension to print the accumulated results.
<code>pytorch_pfn_extras.training.extensions.PrintReportCLI</code>	alias of <code>PrintReport</code>
<code>pytorch_pfn_extras.training.extensions.ProfileReport([...])</code>	Writes the profile results to a file.
<code>pytorch_pfn_extras.training.extensions.ProgressBar([...])</code>	An extension to print a progress bar and recent training status.
<code>pytorch_pfn_extras.training.extensions.ProgressBarCLI</code>	alias of <code>ProgressBar</code>
<code>pytorch_pfn_extras.training.extensions.Slack(channel)</code>	An extension to communicate with Slack.
<code>pytorch_pfn_extras.training.extensions.SlackWebhook(url)</code>	An extension to communicate with Slack using Incoming Webhook.
<code>pytorch_pfn_extras.training.extensions.VariableStatisticsPlot(targets)</code>	An extension to plot statistics for Tensors.

pytorch_pfn_extras.training.extensions.BestValue

```
class pytorch_pfn_extras.training.extensions.BestValue(key, compare, trigger=(1, 'epoch'))
```

Bases: *Extension*

Extension traces the best value of a specific key in the observation.

Parameters

- **key** (*str*) – Key of value.
- **compare** (*callable*) – Compare function which takes current best value and new value and returns whether new value is better than current best.
- **trigger** (*TriggerLike*) – Trigger that decides the comparison interval between current best value and new value. This must be a tuple in the form of <int>, 'epoch' or <int>, 'iteration' which is passed to `BestValueTrigger`.

Methods

```
__init__(key, compare[, trigger])
```

<code>finalize(manager)</code>	Finalizes the extension.
<code>initialize(manager)</code>	Initializes up the manager state.
<code>load_state_dict(to_load)</code>	
<code>on_error(manager, exc, tb)</code>	Handles the error raised during training before finalization.
<code>state_dict()</code>	Serializes the extension state.

Attributes

<code>best_epoch</code>	Returns the epoch count that the current best value is observed.
<code>best_iteration</code>	Returns the iteration count that the current best value is observed.
<code>best_value</code>	Returns the current best value.
<code>default_name</code>	
<code>is_async</code>	
<code>name</code>	
<code>needs_model_state</code>	
<code>priority</code>	
<code>trigger</code>	

`__call__(manager)`

Invokes the extension.

Implementations should override this operator. This method is called at iterations which the corresponding trigger accepts.

Parameters

manager ([ExtensionsManager](#)) – Manager object to call this operator.

Return type

None

`__init__(key, compare, trigger=(1, 'epoch'))`

Parameters

- **key** (*str*) –
- **compare** (*Callable[[float, float], bool]*) –
- **trigger** (*TriggerLike*) –

Return type

None

`property best_epoch: int`

Returns the epoch count that the current best value is observed.

If no value has been observed yet, it raises a RuntimeError.

`property best_iteration: int`

Returns the iteration count that the current best value is observed.

If no value has been observed yet, it raises a RuntimeError.

`property best_value: float`

Returns the current best value.

If no value has been observed yet, it raises a RuntimeError.

`default_name = 'best_value'`

`load_state_dict(to_load)`

Parameters

to_load (*Dict[str, Any]*) –

Return type

None

`state_dict()`

Serializes the extension state.

It is called when a manager that owns this extension is serialized. It serializes nothing by default.

Return type

Dict[str, Any]

pytorch_pfn_extras.training.extensions.DistributedEvaluator

```
class pytorch_pfn_extras.training.extensions.DistributedEvaluator(self, iterator, target,
                                                               eval_func=None, *,
                                                               progress_bar=False)
```

Bases: *Evaluator*

An extension to evaluate models on a validation set in a distributed training setup.

In case `torch.distributed` is used to parallelize training iterations, it is efficient to also run evaluation in parallel by splitting the validation set to each worker process and conduct evaluation separately followed by aggregation of results of each worker, which can be achieved by :class:`~``DistributedEvaluator```.

This extension basically behaves similarly to `Evaluator`, but adds an aggregation step in `Evaluator.evaluate()`. A summary of evaluation (`DictSummary`) in each worker process is collected in “all-gather” manner and then accumulated. Therefore all the worker processes must attend the evaluation, i.e., make sure all the processes have a `Evaluator` extension object configured in the `ExtensionManager` with the same trigger. All the worker process will get identical evaluation result returned by `Evaluator.evaluate()` and reported to an observation.

It is necessary to pass a `DataLoader` with an appropriate sampler which properly splits the validation dataset to each MPI worker process. PyTorch `DistributedSampler` implements this, but it allows sampler repetition in order to make the number of samples assigned to each process identical. For evaluation purpose it distorts the evaluation result, hence it is recommended to use `DistributedValidationSampler` instead.

Methods

<code>__init__(iterator, target[, eval_hook, ...])</code>	
<code>add_metric(metric_fn)</code>	Adds a custom metric to the evaluator.
<code>eval_func(*args, **kwargs)</code>	
<code>evaluate()</code>	Evaluates the model and returns a result dictionary.
<code>finalize(manager)</code>	Finalizes the extension.
<code>get_all_iterators()</code>	Returns a dictionary of all iterators.
<code>get_all_targets()</code>	Returns a dictionary of all target links.
<code>get_iterator(name)</code>	Returns the iterator of the given name.
<code>get_target(name)</code>	Returns the target link of the given name.
<code>initialize(manager)</code>	Initializes up the manager state.
<code>load_state_dict(to_load)</code>	
<code>on_error(manager, exc, tb)</code>	Handles the error raised during training before finalization.
<code>state_dict()</code>	Serializes the extension state.

Attributes

default_name

is_async

name

needs_model_state

priority

trigger

Parameters

- **iterator** (`Union[DataLoader[Any], Dict[str, DataLoader[Any]]]`) –
- **target** (`Union[Module, Dict[str, Module]]`) –
- **eval_hook** (`Optional[Callable[[Evaluator], None]]`) –
- **eval_func** (`Optional[Callable[..., Any]]`) –
- **kwargs** (`Any`) –

`__init__(iterator, target, eval_hook=None, eval_func=None, **kwargs)`

Parameters

- **iterator** (`Union[DataLoader[Any], Dict[str, DataLoader[Any]]]`) –
- **target** (`Union[Module, Dict[str, Module]]`) –
- **eval_hook** (`Optional[Callable[[Evaluator], None]]`) –
- **eval_func** (`Optional[Callable[..., Any]]`) –
- **kwargs** (`Any`) –

Return type

`None`

[pytorch_pfn_extras.training.extensions.Evaluator](#)

```
class pytorch_pfn_extras.training.extensions.Evaluator(self, iterator, target, eval_func=None, *,  
                                                    progress_bar=False)
```

Bases: `Extension`

An extension to evaluate models on a validation set.

This extension evaluates the current models by a given evaluation function. It creates a `Reporter` object to store values observed in the evaluation function on each iteration. The report for all iterations are aggregated to `DictSummary`. The collected mean values are further reported to the reporter object of the manager, where the name of each observation is prefixed by the evaluator name. See `Reporter` for details in naming rules of the reports.

Evaluator has a structure to customize similar to that of `StandardUpdater`. The main differences are:

- There are no optimizers in an evaluator. Instead, it holds links to evaluate.
- An evaluation loop function is used instead of an update function.
- Preparation routine can be customized, which is called before each evaluation. It can be used, e.g., to initialize the state of stateful recurrent networks.

There are two ways to modify the evaluation behavior besides setting a custom evaluation function. One is by setting a custom evaluation loop via the `eval_func` argument. The other is by inheriting this class and overriding the `evaluate()` method. In latter case, users have to create and handle a reporter object manually. Users also have to copy the iterators before using them, in order to reuse them at the next time of evaluation. In both cases, the functions are called in testing mode

This extension is called at the end of each epoch by default.

Parameters

- **iterator** (`Union[DataLoader[Any], Dict[str, DataLoader[Any]]]`) – Dataset iterator for the validation dataset. It can also be a dictionary of iterators. If this is just an iterator, the iterator is registered by the name 'main'.
- **target** (`Union[Module, Dict[str, Module]]`) – `torch.nn.Module` object or a dictionary of links to evaluate. If this is just a layer object, the link is registered by the name 'main'.
- **eval_func** (`Optional[Callable[..., Any]]`) – Evaluation function called at each iteration. The target link to evaluate as a callable is used by default.
- **progress_bar** – Boolean flag to show a progress bar while training, which is similar to `ProgressBar`. (default: `False`)
- **metrics** – List of callables that are called every batch to calculate metrics such as accuracy, roc_auc or others. The signature of the callable is: `def metric_fn(batch, output, last_iteration)` (default: `[]`)
- **eval_hook** (`Optional[Callable[[Evaluator], None]]`) –
- **kwargs** (`Any`) –

Warning: The argument `progress_bar` is experimental. The interface can change in the future.

eval_hook

Function to prepare for each evaluation process.

eval_func

Evaluation function called at each iteration.

Parameters

- **args** (`Any`) –
- **kwargs** (`Any`) –

Return type

`Any`

Methods

<code>__init__(iterator, target[, eval_hook, ...])</code>	
<code>add_metric(metric_fn)</code>	Adds a custom metric to the evaluator.
<code>eval_func(*args, **kwargs)</code>	
<code>evaluate()</code>	Evaluates the model and returns a result dictionary.
<code>finalize(manager)</code>	Finalizes the extension.
<code>get_all_iterators()</code>	Returns a dictionary of all iterators.
<code>get_all_targets()</code>	Returns a dictionary of all target links.
<code>get_iterator(name)</code>	Returns the iterator of the given name.
<code>get_target(name)</code>	Returns the target link of the given name.
<code>initialize(manager)</code>	Initializes up the manager state.
<code>load_state_dict(to_load)</code>	
<code>on_error(manager, exc, tb)</code>	Handles the error raised during training before finalization.
<code>state_dict()</code>	Serializes the extension state.

Attributes

<code>default_name</code>	
<code>is_async</code>	
<code>name</code>	
<code>needs_model_state</code>	
<code>priority</code>	
<code>trigger</code>	

`__call__(manager=None)`

Executes the evaluator extension.

Unlike usual extensions, this extension can be executed without passing a manager object. This extension reports the performance on validation dataset using the `report()` function. Thus, users can use this extension independently from any manager by manually configuring a `Reporter` object.

Parameters

`manager` (`ExtensionsManager`) – Manager object that invokes this extension.

Returns

Result dictionary that contains mean statistics of values reported by the evaluation function.

Return type

`dict`

`__init__(iterator, target, eval_hook=None, eval_func=None, **kwargs)`

Parameters

- **iterator** (`Union[DataLoader[Any], Dict[str, DataLoader[Any]]]`) –
- **target** (`Union[Module, Dict[str, Module]]`) –
- **eval_hook** (`Optional[Callable[[Evaluator], None]]`) –
- **eval_func** (`Optional[Callable[[], Any]]`) –
- **kwargs** (`Any`) –

Return type

`None`

add_metric(`metric_fn`)

Adds a custom metric to the evaluator.

The metric is a callable that is executed every batch with the following signature: `def metric_fn(batch, output, last_iteration)`

Batch is the input batch passed to the model. Output is the result of evaluating batch, last_iteration is a boolean flag that indicates if its the last batch in the evaluation.

Parameters

- **metric_fn** (`Callable[[Any, Any, Any], None]`) –

Return type

`None`

default_name = 'validation'**eval_func(*args, **kwargs)****Parameters**

- **args** (`Any`) –
- **kwargs** (`Any`) –

Return type

`Any`

evaluate()

Evaluates the model and returns a result dictionary.

This method runs the evaluation loop over the validation dataset. It accumulates the reported values to `DictSummary` and returns a dictionary whose values are means computed by the summary.

Users can override this method to customize the evaluation routine.

Returns

Result dictionary. This dictionary is further reported via `report()` without specifying any observer.

Return type

`dict`

get_all_iterators()

Returns a dictionary of all iterators.

Return type

`Dict[str, DataLoader[Any]]`

get_all_targets()

Returns a dictionary of all target links.

Return type

Dict[str, Module]

get_iterator(name)

Returns the iterator of the given name.

Parameters

name (*str*) –

Return type

DataLoader[Any]

get_target(name)

Returns the target link of the given name.

Parameters

name (*str*) –

Return type

Module

priority: *int* = 300

trigger: *TriggerLike* = (1, 'epoch')

pytorch_pfn_extras.training.extensions.FailOnNonNumber

class `pytorch_pfn_extras.training.extensions.FailOnNonNumber(*, check_grad=True)`

Bases: *Extension*

An extension to raise `RuntimeError` if parameters and its gradients contain NaN or Inf.

Although parameters including non-number such as NaN and Inf are unnecessary in most cases the training loop will continue to compute even if the parameters in a given optimizer diverge. This extension is aimed to reduce unnecessary computations by throwing `RuntimeError` if the parameters contain NaN or Inf.

Parameters

check_grad (*bool*) – Set to False to skip checking gradients.

Methods

__init__(*, check_grad)

finalize(manager)	Finalizes the extension.
initialize(manager)	Initializes up the manager state.
load_state_dict(to_load)	

on_error(manager, exc, tb)	Handles the error raised during training before finalization.
state_dict()	Serializes the extension state.

Attributes

<code>default_name</code>	Default name of the extension.
<code>is_async</code>	
<code>name</code>	
<code>needs_model_state</code>	
<code>priority</code>	
<code>trigger</code>	
<hr/>	
<code>__call__(manager)</code>	
	Invokes the extension.
	Implementations should override this operator. This method is called at iterations which the corresponding trigger accepts.
	Parameters
	<code>manager</code> (ExtensionsManager) – Manager object to call this operator.
	Return type
	None
<code>__init__(*, check_grad=True)</code>	
	Parameters
	<code>check_grad</code> (<code>bool</code>) –
	<code>needs_model_state = True</code>

[pytorch_pfn_extras.training.extensions.IgniteEvaluator](#)

```
class pytorch_pfn_extras.training.extensions.IgniteEvaluator(evaluator, iterator, target, **kwargs)
Bases: Evaluator
```

Methods

<code>__init__(evaluator, iterator, target, **kwargs)</code>	
<code>add_metric(metric_fn)</code>	Adds a custom metric to the evaluator.
<code>eval_func(*args, **kwargs)</code>	
<code>evaluate()</code>	Evaluates the model and returns a result dictionary.
<code>finalize(manager)</code>	Finalizes the extension.
<code>get_all_iterators()</code>	Returns a dictionary of all iterators.
<code>get_all_targets()</code>	Returns a dictionary of all target links.
<code>get_iterator(name)</code>	Returns the iterator of the given name.
<code>get_target(name)</code>	Returns the target link of the given name.
<code>initialize(manager)</code>	Initializes up the manager state.
<code>load_state_dict(to_load)</code>	
<code>on_error(manager, exc, tb)</code>	Handles the error raised during training before finalization.
<code>set_evaluator_handlers()</code>	
<code>state_dict()</code>	Serializes the extension state.

Attributes

<code>default_name</code>	
<code>is_async</code>	
<code>name</code>	
<code>needs_model_state</code>	
<code>priority</code>	
<code>trigger</code>	

Parameters

- **evaluator** (`Engine`) –
- **iterator** (`Union[DataLoader[Any], Dict[str, DataLoader[Any]]]`) –
- **target** (`Union[Module, Dict[str, Module]]`) –
- **kwargs** (`Any`) –

`__init__(evaluator, iterator, target, **kwargs)`

Parameters

- **evaluator** (`Engine`) –
- **iterator** (`Union[DataLoader[Any], Dict[str, DataLoader[Any]]]`) –

- **target** (*Union[Module, Dict[str, Module]]*) –
- **kwargs** (*Any*) –

evaluate()

Evaluates the model and returns a result dictionary.

This method runs the evaluation loop over the validation dataset. It accumulates the reported values to `DictSummary` and returns a dictionary whose values are means computed by the summary.

Users can override this method to customize the evaluation routine.

Returns

Result dictionary. This dictionary is further reported via `report()` without specifying any observer.

Return type

`dict`

set_evaluator_handlers()**Return type**

`None`

pytorch_pfn_extras.training.extensions.LRScheduler

```
class pytorch_pfn_extras.training.extensions.LRScheduler(scheduler, *, stepper=<function  
_default_stepper>, trigger=(1, 'epoch'),  
wait_for_first_optimizer_step=False,  
is_async=True)
```

Bases: *Extension*

Trainer extension to adjust the learning rate using PyTorch’s learning rate scheduler.

This extension calls `step()` method of the given LR scheduler. (`torch.option.lr_scheduler.*`). When using `ReduceLROnPlateau`, the latest reported `val/loss` value will be used. This behavior can be customized by passing a custom `stepper` function.

Parameters

- **scheduler** (`_LRScheduler` or `ReduceLROnPlateau`) – Any instance of `torch.optim.lr_scheduler.*`.
- **stepper** (`callable`) – Function that performs the step on the scheduler.
- **trigger** (*Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]]*) – Frequency to call this extension.
- **wait_for_first_optimizer_step** (`bool`) – Wait until `optimizer.step()` is called before invoking `scheduler.step()`. This can address the issue where `optimizer.step()` is not called from the first iteration when using GradScaler.
- **is_async** (`bool`) –

Methods

<code>__init__(scheduler, *[stepper, trigger, ...])</code>	
<code>finalize(manager)</code>	Finalizes the extension.
<code>initialize(manager)</code>	Initializes up the manager state.
<code>load_state_dict(state)</code>	
<code>on_error(manager, exc, tb)</code>	Handles the error raised during training before finalization.
<code>state_dict()</code>	Serializes the extension state.
<code>step_by_value(key)</code>	

Attributes

<code>default_name</code>	Default name of the extension.
<code>is_async</code>	
<code>name</code>	
<code>needs_model_state</code>	
<code>priority</code>	
<code>trigger</code>	

`__call__(manager)`

Invokes the extension.

Implementations should override this operator. This method is called at iterations which the corresponding trigger accepts.

Parameters

`manager` ([ExtensionsManager](#)) – Manager object to call this operator.

Return type

None

`__init__(scheduler, *, stepper=<function _default_stepper>, trigger=(1, 'epoch'), wait_for_first_optimizer_step=False, is_async=True)`

Parameters

- `scheduler` (`Any`) –
- `stepper` (`Any`) –
- `trigger` (`Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]]`) –
- `wait_for_first_optimizer_step` (`bool`) –
- `is_async` (`bool`) –

Return type
None

load_state_dict(state)

Parameters
`state (Dict[str, Any]) –`

Return type
None

state_dict()

Serializes the extension state.

It is called when a manager that owns this extension is serialized. It serializes nothing by default.

Return type
`Dict[str, Any]`

static step_by_value(key)

Parameters
`key (Optional[str]) –`

Return type
`Any`

pytorch_pfn_extras.training.extensions.LogReport

```
class pytorch_pfn_extras.training.extensions.LogReport(keys=None, trigger=(1, 'epoch'),
                                                       postprocess=None, filename=None,
                                                       append=False, format=None, **kwargs)
```

Bases: *Extension*

An extension to output the accumulated results to a log file.

This extension accumulates the observations of the manager to `DictSummary` at a regular interval specified by a supplied trigger, and writes them into a log file in JSON format.

There are two triggers to handle this extension. One is the trigger to invoke this extension, which is used to handle the timing of accumulating the results. It is set to 1, 'iteration' by default. The other is the trigger to determine when to emit the result. When this trigger returns True, this extension appends the summary of accumulated values to the list of past summaries, and writes the list to the log file. Then, this extension makes a new fresh summary object which is used until the next time that the trigger fires.

It also adds some entries to each result dictionary.

- 'epoch' and 'iteration' are the epoch and iteration counts at the output, respectively.
- 'elapsed_time' is the elapsed time in seconds since the training begins. The value is taken from `ExtensionsManager.elapsed_time`.

Parameters

- `keys (iterable of strs)` – Keys of values to accumulate. If this is None, all the values are accumulated and output to the log file.
- `trigger (Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]])` – Trigger that decides when to aggregate the result and output the values. This is distinct from the trigger of this extension itself. If it

is a tuple in the form <int>, 'epoch' or <int>, 'iteration', it is passed to IntervalTrigger.

- **postprocess** (*Optional[Callable[[Mapping[str, Any]], None]]*) – Callback to postprocess the result dictionaries. Each result dictionary is passed to this callback on the output. This callback can modify the result dictionaries, which are used to output to the log file.
- **filename** (*str*) – Name of the log file under the output directory. It can be a format string: the last result dictionary is passed for the formatting. For example, users can use '{iteration}' to separate the log files for different iterations. (default: 'log')
- **append** (*bool, optional*) – If the file is JSON Lines or YAML, contents will be appended instead of rewriting the file every call.
- **format** (*str, optional*) – accepted values are 'json', 'json-lines' and 'yaml'.
- **writer** (*writer object, optional*) – must be callable. object to dump the log to. If specified, it needs to have a correct *savefun* defined. The writer can override the save location in the [*pytorch_pfn_extras.training.ExtensionsManager*](#) object
- **kwargs** (*Any*) –

Note: Enabling *append=True* reduces size of snapshots (and thus reduces the time needed to take snapshots). Note that extensions relying on the logs from past iterations may behave differently; for example, when resuming from a snapshot, PrintReport will not show logs of iterations already done.

Methods

`__init__([keys, trigger, postprocess, ...])`

<code>finalize(manager)</code>	Finalizes the extension.
<code>initialize(manager)</code>	Initializes up the manager state.
<code>load_state_dict(to_load)</code>	
<code>on_error(manager, exc, tb)</code>	Handles the error raised during training before finalization.
<code>state_dict()</code>	Serializes the extension state.
<code>to_dataframe()</code>	

Attributes

<code>default_name</code>	Default name of the extension.
<code>is_async</code>	
<code>log</code>	The current list of observation dictionaries.
<code>name</code>	
<code>needs_model_state</code>	
<code>priority</code>	
<code>trigger</code>	

`__call__(manager)`

Invokes the extension.

Implementations should override this operator. This method is called at iterations which the corresponding trigger accepts.

Parameters

`manager` ([ExtensionsManager](#)) – Manager object to call this operator.

Return type

None

`__init__(keys=None, trigger=(1, 'epoch'), postprocess=None, filename=None, append=False, format=None, **kwargs)`

Parameters

- `keys` (*Optional[Iterable[str]]*) –
- `trigger` (*Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]]*) –
- `postprocess` (*Optional[Callable[[Mapping[str, Any]], None]]*) –
- `filename` (*Optional[str]*) –
- `append` (*bool*) –
- `format` (*Optional[str]*) –
- `kwargs` (*Any*) –

`finalize(manager)`

Finalizes the extension.

This method is called at the end of the training loop.

Parameters

`manager` ([ExtensionsManagerProtocol](#)) –

Return type

None

`load_state_dict(to_load)`

Parameters

`to_load(Dict[str, Any]) –`

Return type

None

`property log: List[Mapping[str, Any]]`

The current list of observation dictionaries.

`state_dict()`

Serializes the extension state.

It is called when a manager that owns this extension is serialized. It serializes nothing by default.

Return type

`Dict[str, Any]`

`to_dataframe()`

Return type

`pandas.DataFrame`

[pytorch_pfn_extras.training.extensions.MaxValue](#)

`class pytorch_pfn_extras.training.extensions.MaxValue(key, trigger=(1, 'epoch'))`

Bases: `BestValue`

Extension traces the maximum value of a specific key in the observation.

Parameters

- `key (str) – Key of value.`
- `trigger (TriggerLike) – Trigger that decides the comparison interval between current maximum value and new value. This must be a tuple in the form of <int>, 'epoch' or <int>, 'iteration' which is passed to BestValueTrigger.`

Methods

`__init__(key[, trigger])`

`finalize(manager)` Finalizes the extension.

`initialize(manager)` Initializes up the manager state.

`load_state_dict(to_load)`

`on_error(manager, exc, tb)` Handles the error raised during training before finalization.

`state_dict()` Serializes the extension state.

Attributes

<code>best_epoch</code>	Returns the epoch count that the current best value is observed.
<code>best_iteration</code>	Returns the iteration count that the current best value is observed.
<code>best_value</code>	Returns the current best value.
<code>default_name</code>	
<code>is_async</code>	
<code>name</code>	
<code>needs_model_state</code>	
<code>priority</code>	
<code>trigger</code>	

`__init__(key, trigger=(1, 'epoch'))`

Parameters

- `key (str)` –
- `trigger (TriggerLike)` –

`default_name = 'max_value'`

pytorch_pfn_extras.training.extensions.MicroAverage

```
class pytorch_pfn_extras.training.extensions.MicroAverage(numerator_key, denominator_key,
                                                       result_key, trigger=(1, 'epoch'))
```

Bases: `Extension`

Calculates micro-average ratio.

Give N batches and values $\{n_1, \dots, n_N\}$ and $\{d_1, \dots, d_N\}$, this extension calculates micro-average of these ratio defined as:

$$\frac{\sum_i^N n_i}{\sum_i^N d_i}.$$

A user usually uses the number of examples which a system correctly predict as n_i and the number of total examples in i -th batch as d_i . This value is called macro-average of precision.

Note that macro-average is defined as:

$$\frac{1}{N} \sum_i^N (n_i/d_i),$$

It is same to the micro-average when each mini-batch has the same d_i .

You need to report numerator value (the number of correct examples) and denominator value (the number of examples) in your model.

```
>>> class MyModel(torch.nn.Module):
...     def __call__(self, x, y):
...         loss = torch.nn.CrossEntropyLoss(x, y)
...         correct = (x.data.argmax(axis=1) == y.data).sum()
...         total = len(y.data)
...         reporting.report({'correct': correct, 'total': total}, self)
...     return loss
```

And then, make an extension with corresponding reporting keys and register it.

```
>>> ext = extensions.MicroAverage(
...     'main/correct', 'main/total', 'main/accuracy')
```

Parameters

- **numerator_key** (*str*) – Key string of obserbation storing a numerator value.
- **denominator_key** (*str*) – Key string of obserbation storing a denominator value.
- **result_key** (*str*) – Key string of obserbation to store a result.
- **trigger** (*Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]]*) – Trigger that decides when to calcurate average. This is distinct from the trigger of this extension itself. If it is a tuple in the form <int>, 'epoch' or <int>, 'iteration', it is passed to IntervalTrigger.

Methods

```
__init__(numerator_key, denominator_key, ...)
```

<code>finalize(manager)</code>	Finalizes the extension.
<code>initialize(manager)</code>	Initializes up the manager state.
<code>load_state_dict(to_load)</code>	
<code>on_error(manager, exc, tb)</code>	Handles the error raised during training before finalization.
<code>state_dict()</code>	Serializes the extension state.

Attributes

<code>default_name</code>	Default name of the extension.
<code>is_async</code>	
<code>name</code>	
<code>needs_model_state</code>	
<code>priority</code>	
<code>trigger</code>	

`__call__(manager)`

Invokes the extension.

Implementations should override this operator. This method is called at iterations which the corresponding trigger accepts.

Parameters

`manager` (`ExtensionsManager`) – Manager object to call this operator.

Return type

None

`__init__(numerator_key, denominator_key, result_key, trigger=(1, 'epoch'))`**Parameters**

- `numerator_key` (`str`) –
- `denominator_key` (`str`) –
- `result_key` (`str`) –
- `trigger` (`Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]]`) –

Return type

None

`load_state_dict(to_load)`**Parameters**

`to_load` (`Dict[str, Any]`) –

Return type

None

priority: `int = 200`

`state_dict()`

Serializes the extension state.

It is called when a manager that owns this extension is serialized. It serializes nothing by default.

Return type

`Dict[str, Any]`

`pytorch_pfn_extras.training.extensions.MinValue`

class `pytorch_pfn_extras.training.extensions.MinValue(key, trigger=(1, 'epoch'))`

Bases: `BestValue`

Extension traces the maximum value of a specific key in the observation.

Parameters

- `key` (`str`) – Key of value.
- `trigger` (`TriggerLike`) – Trigger that decides the comparison interval between current maximum value and new value. This must be a tuple in the form of `<int>, 'epoch'` or `<int>, 'iteration'` which is passed to `BestValueTrigger`.

Methods

<code>__init__(key[, trigger])</code>	
<code>finalize(manager)</code>	Finalizes the extension.
<code>initialize(manager)</code>	Initializes up the manager state.
<code>load_state_dict(to_load)</code>	
<code>on_error(manager, exc, tb)</code>	Handles the error raised during training before finalization.
<code>state_dict()</code>	Serializes the extension state.

Attributes

<code>best_epoch</code>	Returns the epoch count that the current best value is observed.
<code>best_iteration</code>	Returns the iteration count that the current best value is observed.
<code>best_value</code>	Returns the current best value.
<code>default_name</code>	
<code>is_async</code>	
<code>name</code>	
<code>needs_model_state</code>	
<code>priority</code>	
<code>trigger</code>	
<code>__init__(key, trigger=(1, 'epoch'))</code>	

Parameters

- `key (str) –`
- `trigger (TriggerLike) –`

`default_name = 'min_value'`

pytorch_pfn_extras.training.extensions.ParameterStatistics

```
class pytorch_pfn_extras.training.extensions.ParameterStatistics(links, statistics='default',
                                                               report_params=True,
                                                               report_grads=True,
                                                               prefix=None, trigger=(1,
                                                               'epoch'),
                                                               skip_nan_params=False)
```

Bases: *Extension*

An extension to report parameter statistics.

Statistics are collected and reported for a given `Module` or an iterable of `Modules`. If a link contains child modules, the statistics are reported separately for each child.

Any function that takes a one-dimensional `torch.Tensor` and outputs a single or multiple real numbers can be registered to handle the collection of statistics, e.g. `numpy.ndarray.mean()`.

The keys of reported statistics follow the convention of link name followed by parameter name, attribute name and function name, e.g. `VGG16Layers/conv1_1/W/data/mean`. They are prepended with an optional prefix and appended with integer indices if the statistics generating function return multiple values.

Parameters

- **links** (*instance or iterable of Module*) – Module(s) containing the parameters to observe. The link is expected to have a `name` attribute which is used as a part of the report key.
- **statistics** (*dict or 'default'*) – Dictionary with function name to function mappings. The name is a string and is used as a part of the report key. The function is responsible for generating the statistics. If the special value '`default`' is specified, the default statistics functions will be used.
- **report_params** (*bool*) – If `True`, report statistics for parameter values such as weights and biases.
- **report_grads** (*bool*) – If `True`, report statistics for parameter gradients.
- **prefix** (*str*) – Optional prefix to prepend to the report keys.
- **trigger** (*Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]]*) – Trigger that decides when to aggregate the results and report the values.
- **skip_nan_params** (*bool*) – If `True`, statistics are not computed for parameters including NaNs and a single NaN value is immediately reported instead. Otherwise, this extension will simply try to compute the statistics without performing any checks for NaNs.

Note: The default statistic functions are as follows:

- '`mean`' (`xp.mean(x)`)
 - '`std`' (`xp.std(x)`)
 - '`min`' (`xp.min(x)`)
 - '`max`' (`xp.max(x)`)
 - '`zeros`' (`xp.count_nonzero(x == 0)`)
 - '`percentile`' (`xp.percentile(x, (0.13, 2.28, 15.87, 50, 84.13, 97.72, 99.87))`)
-

Methods

<code>__init__(links[, statistics, report_params, ...])</code>	
<code>finalize(manager)</code>	Finalizes the extension.
<code>initialize(manager)</code>	Initializes up the manager state.
<code>load_state_dict(to_load)</code>	
<code>on_error(manager, exc, tb)</code>	Handles the error raised during training before finalization.
<code>register_statistics(name, function)</code>	Register a function to compute a certain statistic.
<code>state_dict()</code>	Serializes the extension state.

Attributes

<code>default_name</code>	
<code>default_statistics</code>	
<code>is_async</code>	
<code>name</code>	
<code>needs_model_state</code>	
<code>priority</code>	
<code>report_key_template</code>	
<code>trigger</code>	

`__call__(manager)`

Execute the statistics extension.

Collect statistics for the current state of parameters.

Note that this method will merely update its statistic summary, unless the internal trigger is fired. If the trigger is fired, the summary will also be reported and then reset for the next accumulation.

Parameters

`manager` (`ExtensionsManager`) – Associated manager that invoked this extension.

Return type

None

`__init__(links, statistics='default', report_params=True, report_grads=True, prefix=None, trigger=(1, 'epoch'), skip_nan_params=False)`

Parameters

- `links` (`Any`) –
- `statistics` (`Any`) –

```
    • report_params (bool) –
    • report_grads (bool) –
    • prefix (Optional[str]) –
    • trigger (Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]]) –
    • skip_nan_params (bool) –

default_name = 'parameter_statistics'

default_statistics = {'max': <function <lambd>>, 'mean': <function <lambd>>,
'min': <function <lambd>>, 'std': <function <lambd>>, 'zeros': <function
<lambd>>}

priority: int = 300

register_statistics(name, function)
    Register a function to compute a certain statistic.
```

The registered function will be called each time the extension runs and the results will be included in the report.

Parameters

- **name** (*str*) – Name of the statistic.
- **function** (*Any*) – Function to generate the statistic. Any function that takes a one-dimensional numpy.ndarray or a cupy.ndarray and outputs a single or multiple real numbers is allowed.

Return type

None

```
report_key_template = '{prefix}{param_name}/{attr_name}/{function_name}'
```

pytorch_pfn_extras.training.extensions.PlotReport

```
class pytorch_pfn_extras.training.extensions.PlotReport(y_keys, x_key='iteration', trigger=(1,
'epoch'), postprocess=None,
filename='plot.png', marker='x',
grid=True)
```

Bases: *Extension*

An extension to output plots.

This extension accumulates the observations of the manager to *DictSummary* at a regular interval specified by a supplied trigger, and plot a graph with using them.

There are two triggers to handle this extension. One is the trigger to invoke this extension, which is used to handle the timing of accumulating the results. It is set to 1, 'iteration' by default. The other is the trigger to determine when to emit the result. When this trigger returns True, this extension appends the summary of accumulated values to the list of past summaries, and writes the list to the log file. Then, this extension makes a new fresh summary object which is used until the next time that the trigger fires.

It also adds 'epoch' and 'iteration' entries to each result dictionary, which are the epoch and iteration counts at the output.

Warning: If your environment needs to specify a backend of matplotlib explicitly, please call `matplotlib.use` before calling `manager.run_iteration`. For example:

```
import matplotlib
matplotlib.use('Agg')

manager.extend(
    extensions.PlotReport(['main/loss', 'validation/main/loss'],
                          'epoch', filename='loss.png'))
with manager.run_iteration():
    pass
```

Then, once one of instances of this extension is called, `matplotlib.use` will have no effect.

For the details, please see here: https://matplotlib.org/faq/usage_faq.html#what-is-a-backend

Parameters

- **y_keys** (*iterable of str*) – Keys of values regarded as y. If this is None, nothing is output to the graph.
- **x_key** (*str*) – Keys of values regarded as x. The default value is ‘iteration’.
- **trigger** (*Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]]*) – Trigger that decides when to aggregate the result and output the values. This is distinct from the trigger of this extension itself. If it is a tuple in the form <int>, ‘epoch’ or <int>, ‘iteration’, it is passed to `IntervalTrigger`.
- **postprocess** (*Any*) – Callback to postprocess the result dictionaries. Figure object, Axes object, and all plot data are passed to this callback in this order. This callback can modify the figure.
- **filename** (*str*) – Name of the figure file under the output directory. It can be a format string. For historical reasons `file_name` is also accepted as an alias of this argument.
- **marker** (*str*) – The marker used to plot the graph. Default is ‘x’. If None is given, it draws with no markers.
- **grid** (*bool*) – If True, set the axis grid on. The default value is True.
- **writer** (*writer object, optional*) – must be callable. object to dump the log to. If specified, it needs to have a correct `savefun` defined. The writer can override the save location in the `pytorch_pfn_extras.training.ExtensionsManager` object
- **kwargs** (*Any*) –

Methods

`__init__(y_keys[, x_key, trigger, ...])`

`available()`

<code>finalize(manager)</code>	Finalizes the extension.
<code>initialize(manager)</code>	Initializes up the manager state.

`load_state_dict(to_load)`

`on_error(manager, exc, tb)` Handles the error raised during training before finalization.

`state_dict()` Serializes the extension state.

Attributes

`default_name` Default name of the extension.

`is_async`

`name`

`needs_model_state`

`priority`

`trigger`

`__call__(manager)`

Invokes the extension.

Implementations should override this operator. This method is called at iterations which the corresponding trigger accepts.

Parameters

`manager` (`ExtensionsManager`) – Manager object to call this operator.

Return type

`None`

`__init__(y_keys, x_key='iteration', trigger=(1, 'epoch'), postprocess=None, filename=None, marker='x', grid=True, **kwargs)`

Parameters

- `y_keys` (`Union[Iterable[str], str]`) –
- `x_key` (`str`) –
- `trigger` (`Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]]`) –
- `postprocess` (`Optional[Any]`) –
- `filename` (`Optional[str]`) –

- **marker** (*str*) –
- **grid** (*bool*) –
- **kwargs** (*Any*) –

static available()

Return type
bool

finalize(manager)

Finalizes the extension.

This method is called at the end of the training loop.

Parameters
manager ([ExtensionsManagerProtocol](#)) –

Return type
None

load_state_dict(to_load)

Parameters
to_load (*Dict*[*str*, *Any*]) –

Return type
None

state_dict()

Serializes the extension state.

It is called when a manager that owns this extension is serialized. It serializes nothing by default.

Return type
Dict[*str*, *Any*]

[pytorch_pfn_extras.training.extensions.PrintReport](#)

```
class pytorch_pfn_extras.training.extensions.PrintReport(entries=None, log_report='LogReport',
                                                       out=<_io.TextIOWrapper
                                                       name='<stdout>' mode='w'
                                                       encoding='utf-8'>)
```

Bases: [Extension](#)

An extension to print the accumulated results.

This extension uses the log accumulated by a [LogReport](#) extension to print specified entries of the log in a human-readable format.

Parameters

- **entries** (*list of str or None*) – List of keys of observations to print. If *None* is passed, automatically infer keys from reported dict.
- **log_report** (*str or LogReport*) – Log report to accumulate the observations. This is either the name of a LogReport extensions registered to the manager, or a LogReport instance to use internally.
- **out** ([IO](#)[*Any*]) – Stream to print the bar. Standard output is used by default.

Methods

<code>__init__([entries, log_report, out])</code>	
<code>finalize(manager)</code>	Finalizes the extension.
<code>get_log_report(manager)</code>	
<code>initialize(manager)</code>	Initializes up the manager state.
<code>load_state_dict(to_load)</code>	
<code>on_error(manager, exc, tb)</code>	Handles the error raised during training before finalization.
<code>state_dict()</code>	Serializes the extension state.

Attributes

<code>default_name</code>	Default name of the extension.
<code>is_async</code>	
<code>name</code>	
<code>needs_model_state</code>	
<code>priority</code>	
<code>trigger</code>	

`__call__(manager)`
Invokes the extension.
Implementations should override this operator. This method is called at iterations which the corresponding trigger accepts.

Parameters

`manager` ([ExtensionsManager](#)) – Manager object to call this operator.

Return type

None

`__init__(entries=None, log_report='LogReport', out=<_io.TextIOWrapper name='<stdout>' mode='w' encoding='utf-8'>)`

Parameters

- `entries` (*Optional[Sequence[str]]*) –
- `log_report` (*Union[str, LogReport]*) –
- `out` ([IO\[Any\]](#)) –

Return type

None

`get_log_report(manager)`

Parameters

`manager (ExtensionsManagerProtocol) –`

Return type

`LogReport`

`initialize(manager)`

Initializes up the manager state.

This method is called before entering the training loop. An extension modifying the state of `ExtensionsManager` can override this method to initialize it.

When the manager has been restored from a snapshot, this method has to recover an appropriate part of the state of the manager.

Parameters

`manager (ExtensionsManager) – Manager object to call this extension.`

Return type

`None`

`load_state_dict(to_load)`

Parameters

`to_load (Dict[str, Any]) –`

Return type

`None`

`state_dict()`

Serializes the extension state.

It is called when a manager that owns this extension is serialized. It serializes nothing by default.

Return type

`Dict[str, Any]`

[`pytorch_pfn_extras.training.extensions.PrintReportCLI`](#)

`pytorch_pfn_extras.training.extensions.PrintReportCLI`

alias of `PrintReport`

[`pytorch_pfn_extras.training.extensions.ProfileReport`](#)

`class pytorch_pfn_extras.training.extensions.ProfileReport(store_keys=None, report_keys=None, trigger=(1, 'epoch'), filename=None, append=False, format=None, **kwargs)`

Bases: `Extension`

Writes the profile results to a file.

Times are reported by using the `pytorch_pfn_extras.profiler.TimeSummary.report()` context manager.

Parameters

- **store_keys** (*iterable of strs*) – Keys of values to write to the profiler report file.
- **report_keys** (*iterable of strs*) – Keys of values that will be reported.
- **trigger** (*Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]]*) – Trigger that decides when to aggregate the result and output the values. This is distinct from the trigger of this extension itself. If it is a tuple in the form <int>, 'epoch' or <int>, 'iteration', it is passed to IntervalTrigger.
- **filename** (*str*) – Name of the log file under the output directory. It can be a format string: the last result dictionary is passed for the formatting. For example, users can use '{iteration}' to separate the log files for different iterations. If the log name is None, it does not output the log to any file.
- **append** (*bool, options1*) – If the file is JSON Lines or YAML, contents will be appended instead of rewriting the file every call.
- **format** (*str, optional*) – accepted values are 'json', 'json-lines' and 'yaml'.
- **writer** (*writer object, optional*) – must be callable. object to dump the log to. If specified, it needs to have a correct *savefun* defined. The writer can override the save location in the *pytorch_pfn_extras.training.ExtensionsManager* object
- **entries** (*list*) – list of str
- **kwarg**s (*Any*) –

Returns

header string templates (str): template string for print values.

Return type

header (str)

Methods

__init__([store_keys, report_keys, trigger, ...])

<i>finalize</i> (manager)	Finalizes the extension.
<i>initialize</i> (manager)	Initializes up the manager state.
<i>load_state_dict</i> (to_load)	
<i>on_error</i> (manager, exc, tb)	Handles the error raised during training before finalization.
<i>state_dict</i> ()	Serializes the extension state.

Attributes

<code>default_name</code>	Default name of the extension.
<code>is_async</code>	
<code>name</code>	
<code>needs_model_state</code>	
<code>priority</code>	
<code>trigger</code>	

`__call__(manager)`

Invokes the extension.

Implementations should override this operator. This method is called at iterations which the corresponding trigger accepts.

Parameters

`manager` ([ExtensionsManager](#)) – Manager object to call this operator.

Return type

None

`__init__(store_keys=None, report_keys=None, trigger=(1, 'epoch'), filename=None, append=False, format=None, **kwargs)`

Parameters

- `store_keys` (*Optional[Iterable[str]]*) –
- `report_keys` (*Optional[Iterable[str]]*) –
- `trigger` (*Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]]*) –
- `filename` (*Optional[str]*) –
- `append` (*bool*) –
- `format` (*Optional[str]*) –
- `kwargs` (*Any*) –

`finalize(manager)`

Finalizes the extension.

This method is called at the end of the training loop.

Parameters

`manager` ([ExtensionsManagerProtocol](#)) –

Return type

None

`load_state_dict(to_load)`

Parameters

`to_load` (*Dict[str, Any]*) –

Return type

None

state_dict()

Serializes the extension state.

It is called when a manager that owns this extension is serialized. It serializes nothing by default.

Return type*Dict[str, Any]***pytorch_pfn_extras.training.extensions.ProgressBar**

```
class pytorch_pfn_extras.training.extensions.ProgressBar(training_length=None,
                                                       update_interval=100, bar_length=50,
                                                       out=<_io.TextIOWrapper
                                                       name='<stdout>' mode='w'
                                                       encoding='utf-8'>)
```

Bases: *Extension*

An extension to print a progress bar and recent training status.

This extension prints a progress bar at every call. It watches the current iteration and epoch to print the bar.

Parameters

- **training_length** (*tuple or None*) – Length of whole training. It consists of an integer and either 'epoch' or 'iteration'. If this value is omitted and the stop trigger of the manager is `IntervalTrigger`, this extension uses its attributes to determine the length of the training.
- **update_interval** (*int*) – Number of iterations to skip printing the progress bar.
- **bar_length** (*int*) – Length of the progress bar in characters.
- **out** (*Any*) – Stream to print the bar. Standard output is used by default.

Methods**__init__**([training_length, update_interval, ...])

finalize (manager)	Finalizes the extension.
initialize (manager)	Initializes up the manager state.
load_state_dict (to_load)	
on_error (manager, exc, tb)	Handles the error raised during training before finalization.
state_dict ()	Serializes the extension state.

Attributes

<code>default_name</code>	Default name of the extension.
<code>is_async</code>	
<code>name</code>	
<code>needs_model_state</code>	
<code>priority</code>	
<code>trigger</code>	

`__call__(manager)`

Invokes the extension.

Implementations should override this operator. This method is called at iterations which the corresponding trigger accepts.

Parameters

`manager` ([ExtensionsManager](#)) – Manager object to call this operator.

Return type

None

`__init__(training_length=None, update_interval=100, bar_length=50, out=<_io.TextIOWrapper name='<stdout>' mode='w' encoding='utf-8'>)`

Parameters

- `training_length` (*Optional[Any]*) –
- `update_interval` (*int*) –
- `bar_length` (*int*) –
- `out` (*Any*) –

`finalize(manager)`

Finalizes the extension.

This method is called at the end of the training loop.

Parameters

`manager` ([ExtensionsManagerProtocol](#)) –

Return type

None

pytorch_pfn_extras.training.extensions.ProgressBarCLI

pytorch_pfn_extras.training.extensions.ProgressBarCLI

alias of *ProgressBar*

pytorch_pfn_extras.training.extensions.Slack

```
class pytorch_pfn_extras.training.extensions.Slack(channel, msg=None, *, start_msg='{default}',  
                                                end_msg='{default}', error_msg='{default}',  
                                                thread=True, filenames=None,  
                                                upload_trigger=None, context=None,  
                                                token=None)
```

Bases: _SlackBase

An extension to communicate with Slack.

Example

```
>>> ppe.training.extensions.Slack(  
...     channel="experiment-progress",  
...     msg="Epoch #{{manager.epoch}}: loss = {{val/loss}}",  
...     end_msg="{{default}} \n <@username> Check out the result!",  
...  
...     # Upload files at the end of the experiment.  
...     filenames=["result/statistics.png"],  
...     upload_trigger=(max_epoch, 'epoch'),  
... )
```

This extension posts a message when:

- `start_msg`: The training has started
- `msg`: The extension is triggered, usually at the end of each epoch
- `end_msg`: The training has finished
- `error_msg`: An exception has raised during the training

These messages can be specified as a format string, a callable that returns a string, or None to disable posting on that event.

When using a format string, the following variables are available for use:

- `manager`: an ExtensionsManager object
- `default`: the default message string
- `context`: an arbitrary object passed to this extension
- `error`: an Exception object (for `error_msg` only)
- All reported values (`manager.observations`)

When using a callable, it should take (`ExtensionsManager, context`) or (`ExtensionsManager, Exception, context`) (for `error_msg`) and return a string.

This extension can upload files along with the message when triggered. `filenames` can be a list of filenames (the same formatting rule as `msg` apply), or a callable taking (`ExtensionsManager`, `context`) and returning a list of filenames.

To use this extension, you must create a Slack app, then specify the token via an environment variable `SLACK_BOT_TOKEN` or `token` option.

Parameters

- **`channel` (str)** – The channel where messages and files will be sent. This can be a channel name or a channel ID.
- **`msg` (str, callable, or None)** – A message to be sent when triggered. It can be a string to be formatted using `.format` or a callable that returns a string.
- **`start_msg` (str, callable, or None)** – A message to be sent at the beginning of the experiment.
- **`end_msg` (str, callable, or None)** – A message to be sent at the completion of the experiment.
- **`error_msg` (str, callable, or None)** – A message to be sent when an exception is raised during the experiment.
- **`thread` (bool)** – When True, subsequent messages will be posted as a thread of the original message. Default is True.
- **`filenames` (list of str or callable)** – A list of files that will be uploaded. These are string templates that can take values in the same way as `msg`, or a callable that returns a list of filenames.
- **`upload_trigger` (trigger or None)** – Used to upload files at certain events. If not specified, files will be uploaded in every call.
- **`context` (Any)** – Any arbitrary user object you will need when generating a message.
- **`token` (str)** – Slack bot token. If None, the environment variable `SLACK_BOT_TOKEN` will be used. Optional, default is None.

Methods

`__init__(channel[, msg, start_msg, end_msg, ...])`

`default_end_msg(context)`

`default_error_msg(exc, context)`

`default_msg(context)`

`default_start_msg(context)`

`finalize(manager)` Finalizes the extension.

`initialize(manager)` Initializes up the manager state.

`load_state_dict(to_load)`

`on_error(manager, exc, tb)` Handles the error raised during training before finalization.

`state_dict()` Serializes the extension state.

Attributes

<code>default_name</code>	Default name of the extension.
<code>is_async</code>	
<code>name</code>	
<code>needs_model_state</code>	
<code>priority</code>	
<code>trigger</code>	

```
__init__(channel, msg=None, *, start_msg='{default}', end_msg='{default}', error_msg='{default}',
        thread=True, filenames=None, upload_trigger=None, context=None, token=None)
```

Parameters

- **channel** (`str`) –
- **msg** (`Optional[Union[str, Callable[[ExtensionsManagerProtocol, Any], str]]]`) –
- **start_msg** (`Optional[Union[str, Callable[[ExtensionsManagerProtocol, Any], str]]]`) –
- **end_msg** (`Optional[Union[str, Callable[[ExtensionsManagerProtocol, Any], str]]]`) –
- **error_msg** (`Optional[Union[str, Callable[[ExtensionsManagerProtocol, Any, Exception], str]]]`) –
- **thread** (`bool`) –
- **filenames** (`Optional[Union[Sequence[str], Callable[[ExtensionsManagerProtocol, Any], Sequence[str]]]]`) –
- **upload_trigger** (`Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]]`) –
- **context** (`Optional[Any]`) –
- **token** (`Optional[str]`) –

Return type

`None`

```
trigger: Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]] = (1, 'epoch')
```

`pytorch_pfn_extras.training.extensions.SlackWebhook`

```
class pytorch_pfn_extras.training.extensions.SlackWebhook(url, msg=None, *, start_msg='{default}',  
                                                       end_msg='{default}',  
                                                       error_msg='{default}', context=None)
```

Bases: `_SlackBase`

An extension to communicate with Slack using Incoming Webhook.

Example

```
>>> ppe.training.extensions.SlackWebhook(  
...     url="https://hooks.slack.com/services/Txxxxx.....",  
...     msg="Epoch # {manager.epoch}: loss = {val/loss}",  
...     end_msg="{default} \n <@username> Check out the result!",  
... )
```

This extension posts a message when:

- `start_msg`: The training has started
- `msg`: The extension is triggered, usually at the end of each epoch
- `end_msg`: The training has finished
- `error_msg`: An exception has raised during the training

These messages can be specified as a format string, a callable that returns a string, or `None` to disable posting on that event.

When using a format string, the following variables are available for use:

- `manager`: an `ExtensionsManager` object
- `default`: the default message string
- `context`: an arbitrary object passed to this extension
- `error`: an `Exception` object (for `error_msg` only)
- All reported values (`manager.observations`)

When using a callable, it should take (`ExtensionsManager, context`) or (`ExtensionsManager, Exception, context`) (for `error_msg`) and return a string.

Parameters

- `url (str)` – Incoming webhook URL to send messages.
- `msg (str, callable, or None)` – A message to be sent when triggered. It can be a string to be formatted using `.format` or a callable that returns a string.
- `start_msg (str, callable, or None)` – A message to be sent at the beginning of the experiment.
- `end_msg (str, callable, or None)` – A message to be sent at the completion of the experiment.
- `error_msg (str, callable, or None)` – A message to be sent when an exception is raised during the experiment.
- `context (object)` – Any arbitrary user object you will need when generating a message.

Methods

<code>__init__(url[, msg, start_msg, end_msg, ...])</code>	
<code>default_end_msg(context)</code>	
<code>default_error_msg(exc, context)</code>	
<code>default_msg(context)</code>	
<code>default_start_msg(context)</code>	
<code>finalize(manager)</code>	Finalizes the extension.
<code>initialize(manager)</code>	Initializes up the manager state.
<code>load_state_dict(to_load)</code>	
<code>on_error(manager, exc, tb)</code>	Handles the error raised during training before finalization.
<code>state_dict()</code>	Serializes the extension state.

Attributes

<code>default_name</code>	Default name of the extension.
<code>is_async</code>	
<code>name</code>	
<code>needs_model_state</code>	
<code>priority</code>	
<code>trigger</code>	

`__init__(url, msg=None, *, start_msg='{default}', end_msg='{default}', error_msg='{default}', context=None)`

Parameters

- `url (str) –`
- `msg (Optional[Union[str, Callable[[ExtensionsManagerProtocol, Any], str]]) –`
- `start_msg(Optional[Union[str, Callable[[ExtensionsManagerProtocol, Any], str]]) –`
- `end_msg(Optional[Union[str, Callable[[ExtensionsManagerProtocol, Any], str]]) –`
- `error_msg(Optional[Union[str, Callable[[ExtensionsManagerProtocol, Any, Exception], str]]) –`
- `context (Optional[Any]) –`

Return type

None

[pytorch_pfn_extras.training.extensions.VariableStatisticsPlot](#)

```
class pytorch_pfn_extras.training.extensions.VariableStatisticsPlot(targets,
                     max_sample_size=1000,
                     report_data=True,
                     report_grad=True,
                     plot_mean=True,
                     plot_std=True,
                     percentile_sigmas=(0, 0.13,
                     2.28, 15.87, 50, 84.13,
                     97.72, 99.87, 100),
                     trigger=(1, 'epoch'),
                     filename='statistics.png',
                     figsize=None,
                     marker=None, grid=True)
```

Bases: [Extension](#)

An extension to plot statistics for Tensors.

This extension collects statistics for a single `torch.Tensor`, a list of `torch.Tensors` or similarly a single or a list of `torch.nn.Modules` containing one or more `torch.Tensors`. In case multiple `torch.Tensors` are found, the means are computed. The collected statistics are plotted and saved as an image in the directory specified by the Manager.

Statistics include mean, standard deviation and percentiles.

This extension uses reservoir sampling to preserve memory, using a fixed size running sample. This means that collected items in the sample are discarded uniformly at random when the number of items becomes larger than the maximum sample size, but each item is expected to occur in the sample with equal probability.

:param targets (`torch.Tensor`: or list of either): Parameters for which statistics are collected. :param `torch.nn.Module`: or list of either): Parameters for which statistics are collected. :param max_sample_size: Maximum number of running samples. :type max_sample_size: int :param report_data: If True, data (e.g. weights) statistics are plotted. If False, they are neither computed nor plotted.

If False, they are neither computed nor plotted.

Parameters

- **report_grad** (`bool`) – If True, gradient statistics are plotted. If False, they are neither computed nor plotted.
- **plot_mean** (`bool`) – If True, means are plotted. If False, they are neither computed nor plotted.
- **plot_std** (`bool`) – If True, standard deviations are plotted. If False, they are neither computed nor plotted.
- **percentile_sigmas** (`float or tuple of floats`) – Percentiles to plot in the range [0, 100].
- **trigger** (`Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]]`) – Trigger that decides when to save the plots as an image. This is distinct from the trigger of this extension itself. If it is a tuple in the form <int>, 'epoch' or <int>, 'iteration', it is passed to `IntervalTrigger`.

- **filename** (*str*) – Name of the output image file under the output directory. For historical reasons `file_name` is also accepted as an alias of this argument.
- **figsize** (*tuple of int*) – Matplotlib `figsize` argument that specifies the size of the output image.
- **marker** (*str*) – Matplotlib `marker` argument that specified the marker style of the plots.
- **grid** (*bool*) – Matplotlib `grid` argument that specifies whether grids are rendered in in the plots or not.
- **writer** (*writer object, optional*) – must be callable. object to dump the log to. If specified, it needs to have a correct `savefun` defined. The writer can override the save location in the `pytorch_pfn_extras.training.ExtensionsManager` object
- **targets** (*Any*) –
- **max_sample_size** (*int*) –
- **report_data** (*bool*) –
- **kwargs** (*Any*) –

Methods

`__init__(targets[, max_sample_size, ...])`

`available()`

<code>finalize(manager)</code>	Finalizes the extension.
<code>initialize(manager)</code>	Initializes up the manager state.
<code>load_state_dict(to_load)</code>	
<code>on_error(manager, exc, tb)</code>	Handles the error raised during training before finalization.
<code>save_plot_using_module(plt, manager)</code>	
<code>state_dict()</code>	Serializes the extension state.

Attributes

<code>default_name</code>	Default name of the extension.
<code>is_async</code>	
<code>name</code>	
<code>needs_model_state</code>	
<code>priority</code>	
<code>trigger</code>	

```
__call__(manager)
    Invokes the extension.

    Implementations should override this operator. This method is called at iterations which the corresponding trigger accepts.

Parameters
    manager (ExtensionsManager) – Manager object to call this operator.

Return type
    None

__init__(targets, max_sample_size=1000, report_data=True, report_grad=True, plot_mean=True, plot_std=True, percentile_sigmas=(0, 0.13, 2.28, 15.87, 50, 84.13, 97.72, 99.87, 100), trigger=(1, 'epoch'), filename=None, figsize=None, marker=None, grid=True, **kwargs)

Parameters
    • targets (Any) –
    • max_sample_size (int) –
    • report_data (bool) –
    • report_grad (bool) –
    • plot_mean (bool) –
    • plot_std (bool) –
    • percentile_sigmas (Union[float, Tuple[float, ...]]) –
    • trigger (Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]]) –
    • filename (Optional[str]) –
    • figsize (Optional[Tuple[int, ...]]) –
    • marker (Optional[str]) –
    • grid (bool) –
    • kwargs (Any) –

static available()

Return type
    bool

finalize(manager)
    Finalizes the extension.

    This method is called at the end of the training loop.

Parameters
    manager (ExtensionsManagerProtocol) –

Return type
    None

save_plot_using_module(plt, manager)

Parameters
    • plt (Any) –
```

- **manager** (`ExtensionsManagerProtocol`) –

Return type

None

Modules

`pytorch_pfn_extras.training.extensions.
best_value`

`pytorch_pfn_extras.training.extensions.
evaluator`

`pytorch_pfn_extras.training.extensions.
fail_on_non_number`

`pytorch_pfn_extras.training.extensions.
log_report`

`pytorch_pfn_extras.training.extensions.
lr_scheduler`

`pytorch_pfn_extras.training.extensions.
micro_average`

`pytorch_pfn_extras.training.extensions.
parameter_statistics`

`pytorch_pfn_extras.training.extensions.
plot_report`

`pytorch_pfn_extras.training.extensions.
print_report`

`pytorch_pfn_extras.training.extensions.
profile_report`

`pytorch_pfn_extras.training.extensions.
progress_bar`

`pytorch_pfn_extras.training.extensions.
slack`

`pytorch_pfn_extras.training.extensions.
snapshot_writers`

`pytorch_pfn_extras.training.extensions.
util`

`pytorch_pfn_extras.training.extensions.
value_observation`

`pytorch_pfn_extras.training.extensions.
variable_statistics_plot`

[pytorch_pfn_extras.training.extensions.best_value](#)

Classes

pytorch_pfn_extras.training.extensions.best_value.BestValue(...)	Extension traces the best value of a specific key in the observation.
pytorch_pfn_extras.training.extensions.best_value.ExtensionsManagerProtocol(...)	
pytorch_pfn_extras.training.extensions.best_value.MaxValue(key)	Extension traces the maximum value of a specific key in the observation.
pytorch_pfn_extras.training.extensions.best_value.MinValue(key)	Extension traces the minimum value of a specific key in the observation.

[pytorch_pfn_extras.training.extensions.best_value.BestValue](#)

```
class pytorch_pfn_extras.training.extensions.best_value.BestValue(key, compare, trigger=(1, 'epoch'))
```

Bases: *Extension*

Extension traces the best value of a specific key in the observation.

Parameters

- **key** (*str*) – Key of value.
- **compare** (*callable*) – Compare function which takes current best value and new value and returns whether new value is better than current best.
- **trigger** (*TriggerLike*) – Trigger that decides the comparison interval between current best value and new value. This must be a tuple in the form of <int>, 'epoch' or <int>, 'iteration' which is passed to `BestValueTrigger`.

Methods

[__init__\(key, compare\[, trigger\]\)](#)

finalize(manager)	Finalizes the extension.
initialize(manager)	Initializes up the manager state.
load_state_dict(to_load)	
on_error(manager, exc, tb)	Handles the error raised during training before finalization.
state_dict()	Serializes the extension state.

Attributes

<code>best_epoch</code>	Returns the epoch count that the current best value is observed.
<code>best_iteration</code>	Returns the iteration count that the current best value is observed.
<code>best_value</code>	Returns the current best value.
<code>default_name</code>	
<code>is_async</code>	
<code>name</code>	
<code>needs_model_state</code>	
<code>priority</code>	
<code>trigger</code>	

`__call__(manager)`

Invokes the extension.

Implementations should override this operator. This method is called at iterations which the corresponding trigger accepts.

Parameters

`manager` (`ExtensionsManager`) – Manager object to call this operator.

Return type

None

`__init__(key, compare, trigger=(1, 'epoch'))`

Parameters

- `key` (`str`) –
- `compare` (`Callable[[float, float], bool]`) –
- `trigger` (`TriggerLike`) –

Return type

None

`property best_epoch: int`

Returns the epoch count that the current best value is observed.

If no value has been observed yet, it raises a `RuntimError`.

`property best_iteration: int`

Returns the iteration count that the current best value is observed.

If no value has been observed yet, it raises a `RuntimError`.

`property best_value: float`

Returns the current best value.

If no value has been observed yet, it raises a `RuntimError`.

```
default_name = 'best_value'  
load_state_dict(to_load)
```

Parameters

`to_load(Dict[str, Any]) –`

Return type

`None`

state_dict()

Serializes the extension state.

It is called when a manager that owns this extension is serialized. It serializes nothing by default.

Return type

`Dict[str, Any]`

[pytorch_pfn_extras.training.extensions.best_value.ExtensionsManagerProtocol](#)

```
class pytorch_pfn_extras.training.extensions.best_value.ExtensionsManagerProtocol(*args,  
                                **kwargs)
```

Bases: `Protocol`

Methods

```
__init__(*args, **kwargs)
```

```
get_extension(name)
```

Attributes

elapsed_time

epoch

epoch_detail

is_before_training

iteration

models

observation

optimizers

out

raw_models

reporter

stop_trigger

writer

`__init__(*args, **kwargs)`

`property elapsed_time: float`

`property epoch: int`

`property epoch_detail: float`

`get_extension(name)`

Parameters

`name (str) –`

Return type

Extension

`property is_before_training: bool`

`property iteration: int`

`property models: Mapping[str, Module]`

`property observation: reporting.Observation`

`property optimizers: Mapping[str, Optimizer]`

```
property out: str
property raw_models: Mapping[str, Module]
property reporter: reporting.Reporter
property stop_trigger: bool
property writer: Optional[writing.Writer]
```

pytorch_pfn_extras.training.extensions.best_value.MaxValue

class pytorch_pfn_extras.training.extensions.best_value.MaxValue(key, trigger=(1, 'epoch'))

Bases: BestValue

Extension traces the maximum value of a specific key in the observation.

Parameters

- **key** (str) – Key of value.
- **trigger** (TriggerLike) – Trigger that decides the comparison interval between current maximum value and new value. This must be a tuple in the form of <int>, 'epoch' or <int>, 'iteration' which is passed to BestValueTrigger.

Methods

__init__(key[, trigger])

finalize(manager)	Finalizes the extension.
initialize(manager)	Initializes up the manager state.
load_state_dict(to_load)	
on_error(manager, exc, tb)	Handles the error raised during training before finalization.
state_dict()	Serializes the extension state.

Attributes

<code>best_epoch</code>	Returns the epoch count that the current best value is observed.
<code>best_iteration</code>	Returns the iteration count that the current best value is observed.
<code>best_value</code>	Returns the current best value.
<code>default_name</code>	
<code>is_async</code>	
<code>name</code>	
<code>needs_model_state</code>	
<code>priority</code>	
<code>trigger</code>	

`__init__(key, trigger=(1, 'epoch'))`

Parameters

- **key** (*str*) –
- **trigger** (*TriggerLike*) –

`default_name = 'max_value'`

`pytorch_pfn_extras.training.extensions.best_value.MinValue`

`class pytorch_pfn_extras.training.extensions.best_value.MinValue(key, trigger=(1, 'epoch'))`

Bases: `BestValue`

Extension traces the maximum value of a specific key in the observation.

Parameters

- **key** (*str*) – Key of value.
- **trigger** (*TriggerLike*) – Trigger that decides the comparison interval between current maximum value and new value. This must be a tuple in the form of `<int>, 'epoch'` or `<int>, 'iteration'` which is passed to `BestValueTrigger`.

Methods

<code>__init__(key[, trigger])</code>	
<code>finalize(manager)</code>	Finalizes the extension.
<code>initialize(manager)</code>	Initializes up the manager state.
<code>load_state_dict(to_load)</code>	
<code>on_error(manager, exc, tb)</code>	Handles the error raised during training before finalization.
<code>state_dict()</code>	Serializes the extension state.

Attributes

<code>best_epoch</code>	Returns the epoch count that the current best value is observed.
<code>best_iteration</code>	Returns the iteration count that the current best value is observed.
<code>best_value</code>	Returns the current best value.
<code>default_name</code>	
<code>is_async</code>	
<code>name</code>	
<code>needs_model_state</code>	
<code>priority</code>	
<code>trigger</code>	
<code>__init__(key, trigger=(1, 'epoch'))</code>	

Parameters

- `key (str) –`
- `trigger (TriggerLike) –`

`default_name = 'min_value'`

pytorch_pfn_extras.training.extensions.evaluator

Classes

<code>pytorch_pfn_extras.training.extensions.evaluator.DistributedEvaluator(...)</code>	An extension to evaluate models on a validation set in a distributed training setup.
<code>pytorch_pfn_extras.training.extensions.evaluator.Evaluator(...)</code>	An extension to evaluate models on a validation set.
<code>pytorch_pfn_extras.training.extensions.evaluator.ExtensionsManagerProtocol(...)</code>	
<code>pytorch_pfn_extras.training.extensions.evaluator.IgniteEvaluator(...)</code>	
<code>pytorch_pfn_extras.training.extensions.evaluator.IterationStatus(size)</code>	
<code>pytorch_pfn_extras.training.extensions.evaluator.TextIO(...)</code>	Typed version of the return of open() in text mode.

pytorch_pfn_extras.training.extensions.evaluator.DistributedEvaluator

```
class pytorch_pfn_extras.training.extensions.evaluator.DistributedEvaluator(self, iterator,
                           target,
                           eval_func=None,
                           *,
                           progress_bar=False)
```

Bases: `Evaluator`

An extension to evaluate models on a validation set in a distributed training setup.

In case `torch.distributed` is used to parallelize training iterations, it is efficient to also run evaluation in parallel by splitting the validation set to each worker process and conduct evaluation separately followed by aggregation of results of each worker, which can be achieved by :class:`~`DistributedEvaluator`~`.

This extension basically behaves similarly to `Evaluator`, but adds an aggregation step in `Evaluator.evaluate()`. A summary of evaluation (`DictSummary`) in each worker process is collected in “all-gather” manner and then accumulated. Therefore all the worker processes must attend the evaluation, i.e., make sure all the processes have a `Evaluator` extension object configured in the `ExtensionManager` with the same trigger. All the worker process will get identical evaluation result returned by `Evaluator.evaluate()` and reported to an observation.

It is necessary to pass a `DataLoader` with an appropriate sampler which properly splits the validation dataset to each MPI worker process. PyTorch `DistributedSampler` implements this, but it allows sampler repetition in order to make the number of samples assigned to each process identical. For evaluation purpose it distorts the evaluation result, hence it is recommended to use `DistributedValidationSampler` instead.

Methods

<code>__init__(iterator, target[, eval_hook, ...])</code>	
<code>add_metric(metric_fn)</code>	Adds a custom metric to the evaluator.
<code>eval_func(*args, **kwargs)</code>	
<code>evaluate()</code>	Evaluates the model and returns a result dictionary.
<code>finalize(manager)</code>	Finalizes the extension.
<code>get_all_iterators()</code>	Returns a dictionary of all iterators.
<code>get_all_targets()</code>	Returns a dictionary of all target links.
<code>get_iterator(name)</code>	Returns the iterator of the given name.
<code>get_target(name)</code>	Returns the target link of the given name.
<code>initialize(manager)</code>	Initializes up the manager state.
<code>load_state_dict(to_load)</code>	
<code>on_error(manager, exc, tb)</code>	Handles the error raised during training before finalization.
<code>state_dict()</code>	Serializes the extension state.

Attributes

<code>default_name</code>	
<code>is_async</code>	
<code>name</code>	
<code>needs_model_state</code>	
<code>priority</code>	
<code>trigger</code>	

Parameters

- `iterator (Union[DataLoader[Any], Dict[str, DataLoader[Any]]]) –`
- `target (Union[Module, Dict[str, Module]]) –`
- `eval_hook (Optional[Callable[[Evaluator], None]]) –`
- `eval_func (Optional[Callable[..., Any]]) –`
- `kwargs (Any) –`

`__init__(iterator, target, eval_hook=None, eval_func=None, **kwargs)`

Parameters

- `iterator (Union[DataLoader[Any], Dict[str, DataLoader[Any]]]) –`
- `target (Union[Module, Dict[str, Module]]) –`

- **eval_hook** (*Optional[Callable[[Evaluator], None]]*) –
- **eval_func** (*Optional[Callable[..., Any]]*) –
- **kwargs** (*Any*) –

Return type

None

pytorch_pfn_extras.training.extensions.evaluator.Evaluator

```
class pytorch_pfn_extras.training.extensions.evaluator.Evaluator(self, iterator, target,
                                                               eval_func=None, *,
                                                               progress_bar=False)
```

Bases: *Extension*

An extension to evaluate models on a validation set.

This extension evaluates the current models by a given evaluation function. It creates a **Reporter** object to store values observed in the evaluation function on each iteration. The report for all iterations are aggregated to **DictSummary**. The collected mean values are further reported to the reporter object of the manager, where the name of each observation is prefixed by the evaluator name. See **Reporter** for details in naming rules of the reports.

Evaluator has a structure to customize similar to that of **StandardUpdater**. The main differences are:

- There are no optimizers in an evaluator. Instead, it holds links to evaluate.
- An evaluation loop function is used instead of an update function.
- Preparation routine can be customized, which is called before each evaluation. It can be used, e.g., to initialize the state of stateful recurrent networks.

There are two ways to modify the evaluation behavior besides setting a custom evaluation function. One is by setting a custom evaluation loop via the **eval_func** argument. The other is by inheriting this class and overriding the **evaluate()** method. In latter case, users have to create and handle a reporter object manually. Users also have to copy the iterators before using them, in order to reuse them at the next time of evaluation. In both cases, the functions are called in testing mode

This extension is called at the end of each epoch by default.

Parameters

- **iterator** (*Union[DataLoader[Any], Dict[str, DataLoader[Any]]]*) – Dataset iterator for the validation dataset. It can also be a dictionary of iterators. If this is just an iterator, the iterator is registered by the name 'main'.
- **target** (*Union[Module, Dict[str, Module]]*) – torch.nn.Module object or a dictionary of links to evaluate. If this is just a layer object, the link is registered by the name 'main'.
- **eval_func** (*Optional[Callable[..., Any]]*) – Evaluation function called at each iteration. The target link to evaluate as a callable is used by default.
- **progress_bar** – Boolean flag to show a progress bar while training, which is similar to **ProgressBar**. (default: `False`)
- **metrics** – List of callables that are called every batch to calculate metrics such as accuracy, roc_auc or others. The signature of the callable is: `def metric_fn(batch, output, last_iteration)` (default: `[]`)
- **eval_hook** (*Optional[Callable[[Evaluator], None]]*) –

- **kwargs** (*Any*) –

Warning: The argument `progress_bar` is experimental. The interface can change in the future.

eval_hook

Function to prepare for each evaluation process.

eval_func

Evaluation function called at each iteration.

Parameters

- **args** (*Any*) –
- **kwargs** (*Any*) –

Return type

Any

Methods

`__init__(iterator, target[, eval_hook, ...])`

`add_metric(metric_fn)` Adds a custom metric to the evaluator.

`eval_func(*args, **kwargs)`

`evaluate()` Evaluates the model and returns a result dictionary.

`finalize(manager)` Finalizes the extension.

`get_all_iterators()` Returns a dictionary of all iterators.

`get_all_targets()` Returns a dictionary of all target links.

`get_iterator(name)` Returns the iterator of the given name.

`get_target(name)` Returns the target link of the given name.

`initialize(manager)` Initializes up the manager state.

`load_state_dict(to_load)`

`on_error(manager, exc, tb)` Handles the error raised during training before finalization.

`state_dict()` Serializes the extension state.

Attributes

`default_name`

`is_async`

`name`

`needs_model_state`

`priority`

`trigger`

`__call__(manager=None)`

Executes the evaluator extension.

Unlike usual extensions, this extension can be executed without passing a manager object. This extension reports the performance on validation dataset using the `report()` function. Thus, users can use this extension independently from any manager by manually configuring a `Reporter` object.

Parameters

`manager` (`ExtensionsManager`) – Manager object that invokes this extension.

Returns

Result dictionary that contains mean statistics of values reported by the evaluation function.

Return type

`dict`

`__init__(iterator, target, eval_hook=None, eval_func=None, **kwargs)`

Parameters

- `iterator` (`Union[DataLoader[Any], Dict[str, DataLoader[Any]]]`) –
- `target` (`Union[Module, Dict[str, Module]]`) –
- `eval_hook` (`Optional[Callable[[Evaluator], None]]`) –
- `eval_func` (`Optional[Callable[[], Any]]`) –
- `kwargs` (`Any`) –

Return type

`None`

`add_metric(metric_fn)`

Adds a custom metric to the evaluator.

The metric is a callable that is executed every batch with the following signature: `def metric_fn(batch, output, last_iteration)`

Batch is the input batch passed to the model. Output is the result of evaluating batch, last_iteration is a boolean flag that indicates if its the last batch in the evaluation.

Parameters

`metric_fn` (`Callable[[Any, Any, Any], None]`) –

Return type

None

default_name = 'validation'

eval_func(*args, **kwargs)

Parameters

- **args** (*Any*) –

- **kwargs** (*Any*) –

Return type

Any

evaluate()

Evaluates the model and returns a result dictionary.

This method runs the evaluation loop over the validation dataset. It accumulates the reported values to `DictSummary` and returns a dictionary whose values are means computed by the summary.

Users can override this method to customize the evaluation routine.

Returns

Result dictionary. This dictionary is further reported via `report()` without specifying any observer.

Return type

dict

get_all_iterators()

Returns a dictionary of all iterators.

Return type

Dict[str, `DataLoader[Any]`]

get_all_targets()

Returns a dictionary of all target links.

Return type

Dict[str, `Module`]

get_iterator(*name*)

Returns the iterator of the given name.

Parameters

- **name** (str) –

Return type

`DataLoader[Any]`

get_target(*name*)

Returns the target link of the given name.

Parameters

- **name** (str) –

Return type

`Module`

priority: int = 300

trigger: TriggerLike = (1, 'epoch')

pytorch_pfn_extras.training.extensions.evaluator.ExtensionsManagerProtocol

```
class pytorch_pfn_extras.training.extensions.evaluator.ExtensionsManagerProtocol(*args,  
                                **kwargs)
```

Bases: Protocol

Methods

```
__init__(*args, **kwargs)
```

```
get_extension(name)
```

Attributes

```
elapsed_time
```

```
epoch
```

```
epoch_detail
```

```
is_before_training
```

```
iteration
```

```
models
```

```
observation
```

```
optimizers
```

```
out
```

```
raw_models
```

```
reporter
```

```
stop_trigger
```

```
writer
```

```
__init__(*args, **kwargs)
```

```
property elapsed_time: float
```

```
property epoch: int
```

```
property epoch_detail: float
```

```
get_extension(name)

    Parameters
        name (str) –

    Return type
        Extension

property is_before_training: bool
property iteration: int
property models: Mapping[str, Module]
property observation: reporting.Observation
property optimizers: Mapping[str, Optimizer]
property out: str
property raw_models: Mapping[str, Module]
property reporter: reporting.Reporter
property stop_trigger: bool
property writer: Optional[writing.Writer]
```

pytorch_pfn_extras.training.extensions.evaluator.IgniteEvaluator

```
class pytorch_pfn_extras.training.extensions.evaluator.IgniteEvaluator(evaluator, iterator,
target, **kwargs)
```

Bases: *Evaluator*

Methods

<code>__init__(evaluator, iterator, target, **kwargs)</code>	
<code>add_metric(metric_fn)</code>	Adds a custom metric to the evaluator.
<code>eval_func(*args, **kwargs)</code>	
<code>evaluate()</code>	Evaluates the model and returns a result dictionary.
<code>finalize(manager)</code>	Finalizes the extension.
<code>get_all_iterators()</code>	Returns a dictionary of all iterators.
<code>get_all_targets()</code>	Returns a dictionary of all target links.
<code>get_iterator(name)</code>	Returns the iterator of the given name.
<code>get_target(name)</code>	Returns the target link of the given name.
<code>initialize(manager)</code>	Initializes up the manager state.
<code>load_state_dict(to_load)</code>	
<code>on_error(manager, exc, tb)</code>	Handles the error raised during training before finalization.
<code>set_evaluator_handlers()</code>	
<code>state_dict()</code>	Serializes the extension state.

Attributes

`default_name`

`is_async`

`name`

`needs_model_state`

`priority`

`trigger`

Parameters

- **evaluator** (*Engine*) –
- **iterator** (*Union[DataLoader[Any], Dict[str, DataLoader[Any]]]*) –
- **target** (*Union[Module, Dict[str, Module]]*) –
- **kwargs** (*Any*) –

`__init__(evaluator, iterator, target, **kwargs)`

Parameters

- **evaluator** (*Engine*) –
- **iterator** (*Union[DataLoader[Any], Dict[str, DataLoader[Any]]]*) –
- **target** (*Union[Module, Dict[str, Module]]*) –
- **kwargs** (*Any*) –

`evaluate()`

Evaluates the model and returns a result dictionary.

This method runs the evaluation loop over the validation dataset. It accumulates the reported values to `DictSummary` and returns a dictionary whose values are means computed by the summary.

Users can override this method to customize the evaluation routine.

Returns

Result dictionary. This dictionary is further reported via `report()` without specifying any observer.

Return type

`dict`

`set_evaluator_handlers()`

Return type

`None`

[pytorch_pfn_extras.training.extensions.evaluator.IterationStatus](#)

```
class pytorch_pfn_extras.training.extensions.evaluator.IterationStatus(size)
Bases: object
```

Methods

[__init__\(size\)](#)

Attributes

[epoch_detail](#)

Parameters

size (int) –

[__init__\(size\)](#)

Parameters

size (int) –

Return type

None

property epoch_detail: float

[pytorch_pfn_extras.training.extensions.evaluator.TextIO](#)

```
class pytorch_pfn_extras.training.extensions.evaluator.TextIO(*args, **kwds)
Bases: IO\[str\]
```

Typed version of the return of open() in text mode.

Methods

`__init__()`

`close()`

`fileno()`

`flush()`

`isatty()`

`read([n])`

`readable()`

`readline([limit])`

`readlines([hint])`

`seek(offset[, whence])`

`seekable()`

`tell()`

`truncate([size])`

`writable()`

`write(s)`

`writelines(lines)`

Attributes

buffer

closed

encoding

errors

line_buffering

mode

name

newlines

abstract property buffer: BinaryIO

abstract property encoding: str

abstract property errors: Optional[str]

abstract property line_buffering: bool

abstract property newlines: Any

[pytorch_pfn_extras.training.extensions.fail_on_non_number](#)

Classes

pytorch_pfn_extras.training.
extensions.fail_on_non_number.
ExtensionsManagerProtocol(...)

pytorch_pfn_extras.training.extensions.
fail_on_non_number.FailOnNonNumber()*

An extension to raise RuntimeError if parameters and its
gradients contain NaN or Inf.

[pytorch_pfn_extras.training.extensions.fail_on_non_number.ExtensionsManagerProtocol](#)

class *pytorch_pfn_extras.training.extensions.fail_on_non_number.ExtensionsManagerProtocol(*args,
**kwargs)*

Bases: Protocol

Methods

```
__init__(*args, **kwargs)
```

```
get_extension(name)
```

Attributes

```
elapsed_time
```

```
epoch
```

```
epoch_detail
```

```
is_before_training
```

```
iteration
```

```
models
```

```
observation
```

```
optimizers
```

```
out
```

```
raw_models
```

```
reporter
```

```
stop_trigger
```

```
writer
```

```
__init__(*args, **kwargs)
```

```
property elapsed_time: float
```

```
property epoch: int
```

```
property epoch_detail: float
```

```
get_extension(name)
```

Parameters

name (str) –

Return type

Extension

```
property is_before_training: bool
property iteration: int
property models: Mapping[str, Module]
property observation: reporting.Observation
property optimizers: Mapping[str, Optimizer]
property out: str
property raw_models: Mapping[str, Module]
property reporter: reporting.Reporter
property stop_trigger: bool
property writer: Optional[writing.Writer]
```

[pytorch_pfn_extras.training.extensions.fail_on_non_number.FailOnNonNumber](#)

```
class pytorch_pfn_extras.training.extensions.fail_on_non_number.FailOnNonNumber(*,
    check_grad=True)
```

Bases: *Extension*

An extension to raise `RuntimeError` if parameters and its gradients contain `NaN` or `Inf`.

Although parameters including non-number such as `NaN` and `Inf` are unnecessary in most cases the training loop will continue to compute even if the parameters in a given optimizer diverge. This extension is aimed to reduce unnecessary computations by throwing `RuntimeError` if the parameters contain `NaN` or `Inf`.

Parameters

`check_grad (bool)` – Set to False to skip checking gradients.

Methods

`__init__(*, check_grad)`

<code>finalize(manager)</code>	Finalizes the extension.
<code>initialize(manager)</code>	Initializes up the manager state.
<code>load_state_dict(to_load)</code>	
<code>on_error(manager, exc, tb)</code>	Handles the error raised during training before finalization.
<code>state_dict()</code>	Serializes the extension state.

Attributes

<code>default_name</code>	Default name of the extension.
<code>is_async</code>	
<code>name</code>	
<code>needs_model_state</code>	
<code>priority</code>	
<code>trigger</code>	
<hr/>	
<code>__call__(manager)</code>	
	Invokes the extension.
	Implementations should override this operator. This method is called at iterations which the corresponding trigger accepts.
	Parameters
	<code>manager</code> (ExtensionsManager) – Manager object to call this operator.
	Return type
	None
<code>__init__(*, check_grad=True)</code>	
	Parameters
	<code>check_grad</code> (<code>bool</code>) –
	<code>needs_model_state = True</code>

[pytorch_pfn_extras.training.extensions.log_report](#)

Classes

<code>pytorch_pfn_extras.training.extensions.log_report.ExtensionsManagerProtocol(...)</code>	
<code>pytorch_pfn_extras.training.extensions.log_report.LogReport([...])</code>	An extension to output the accumulated results to a log file.
<code>pytorch_pfn_extras.training.extensions.log_report.LogWriterSaveFunc(...)</code>	

[pytorch_pfn_extras.training.extensions.log_report.ExtensionsManagerProtocol](#)

```
class pytorch_pfn_extras.training.extensions.log_report.ExtensionsManagerProtocol(*args,  
                                **kwargs)
```

Bases: Protocol

Methods

```
__init__(*args, **kwargs)
```

```
get_extension(name)
```

Attributes

```
elapsed_time
```

```
epoch
```

```
epoch_detail
```

```
is_before_training
```

```
iteration
```

```
models
```

```
observation
```

```
optimizers
```

```
out
```

```
raw_models
```

```
reporter
```

```
stop_trigger
```

```
writer
```

```
__init__(*args, **kwargs)
```

```
property elapsed_time: float
```

```
property epoch: int
```

```
property epoch_detail: float
```

```
get_extension(name)

Parameters
    name (str) –

Return type
    Extension

property is_before_training: bool

property iteration: int

property models: Mapping[str, Module]

property observation: reporting.Observation

property optimizers: Mapping[str, Optimizer]

property out: str

property raw_models: Mapping[str, Module]

property reporter: reporting.Reporter

property stop_trigger: bool

property writer: Optional[writing.Writer]
```

pytorch_pfn_extras.training.extensions.log_report.LogReport

```
class pytorch_pfn_extras.training.extensions.log_report.LogReport(keys=None, trigger=(1,
    'epoch'), postprocess=None,
    filename=None,
    append=False, format=None,
    **kwargs)
```

Bases: *Extension*

An extension to output the accumulated results to a log file.

This extension accumulates the observations of the manager to `DictSummary` at a regular interval specified by a supplied trigger, and writes them into a log file in JSON format.

There are two triggers to handle this extension. One is the trigger to invoke this extension, which is used to handle the timing of accumulating the results. It is set to 1, 'iteration' by default. The other is the trigger to determine when to emit the result. When this trigger returns True, this extension appends the summary of accumulated values to the list of past summaries, and writes the list to the log file. Then, this extension makes a new fresh summary object which is used until the next time that the trigger fires.

It also adds some entries to each result dictionary.

- 'epoch' and 'iteration' are the epoch and iteration counts at the output, respectively.
- 'elapsed_time' is the elapsed time in seconds since the training begins. The value is taken from `ExtensionsManager.elapsed_time`.

Parameters

- **keys** (*iterable of strs*) – Keys of values to accumulate. If this is None, all the values are accumulated and output to the log file.

- **trigger** (*Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]]*) – Trigger that decides when to aggregate the result and output the values. This is distinct from the trigger of this extension itself. If it is a tuple in the form <int>, 'epoch' or <int>, 'iteration', it is passed to IntervalTrigger.
- **postprocess** (*Optional[Callable[[Mapping[str, Any]], None]]*) – Callback to postprocess the result dictionaries. Each result dictionary is passed to this callback on the output. This callback can modify the result dictionaries, which are used to output to the log file.
- **filename** (*str*) – Name of the log file under the output directory. It can be a format string: the last result dictionary is passed for the formatting. For example, users can use '{iteration}' to separate the log files for different iterations. (default: 'log')
- **append** (*bool, optional*) – If the file is JSON Lines or YAML, contents will be appended instead of rewriting the file every call.
- **format** (*str, optional*) – accepted values are 'json', 'json-lines' and 'yaml'.
- **writer** (*writer object, optional*) – must be callable. object to dump the log to. If specified, it needs to have a correct *savefun* defined. The writer can override the save location in the *pytorch_pfn_extras.training.ExtensionsManager* object
- **kwarg**s (*Any*) –

Note: Enabling *append=True* reduces size of snapshots (and thus reduces the time needed to take snapshots). Note that extensions relying on the logs from past iterations may behave differently; for example, when resuming from a snapshot, PrintReport will not show logs of iterations already done.

Methods

`__init__([keys, trigger, postprocess, ...])`

<code>finalize(manager)</code>	Finalizes the extension.
<code>initialize(manager)</code>	Initializes up the manager state.
<code>load_state_dict(to_load)</code>	
<code>on_error(manager, exc, tb)</code>	Handles the error raised during training before finalization.
<code>state_dict()</code>	Serializes the extension state.
<code>to_dataframe()</code>	

Attributes

<code>default_name</code>	Default name of the extension.
<code>is_async</code>	
<code>log</code>	The current list of observation dictionaries.
<code>name</code>	
<code>needs_model_state</code>	
<code>priority</code>	
<code>trigger</code>	

`__call__(manager)`

Invokes the extension.

Implementations should override this operator. This method is called at iterations which the corresponding trigger accepts.

Parameters

`manager` ([ExtensionsManager](#)) – Manager object to call this operator.

Return type

None

`__init__(keys=None, trigger=(1, 'epoch'), postprocess=None, filename=None, append=False, format=None, **kwargs)`

Parameters

- `keys` (*Optional[Iterable[str]]*) –
- `trigger` (*Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]]*) –
- `postprocess` (*Optional[Callable[[Mapping[str, Any]], None]]*) –
- `filename` (*Optional[str]*) –
- `append` (*bool*) –
- `format` (*Optional[str]*) –
- `kwargs` (*Any*) –

`finalize(manager)`

Finalizes the extension.

This method is called at the end of the training loop.

Parameters

`manager` ([ExtensionsManagerProtocol](#)) –

Return type

None

load_state_dict(*to_load*)

Parameters

to_load (*Dict[str, Any]*) –

Return type

None

property log: List[Mapping[str, Any]]

The current list of observation dictionaries.

state_dict()

Serializes the extension state.

It is called when a manager that owns this extension is serialized. It serializes nothing by default.

Return type

Dict[str, Any]

to_dataframe()

Return type

pandas.DataFrame

[pytorch_pfn_extras.training.extensions.log_report.LogWriterSaveFunc](#)

class [pytorch_pfn_extras.training.extensions.log_report.LogWriterSaveFunc](#)(*format, append*)

Bases: object

Methods

__init__(*format, append*)

Parameters

- **format** (*str*) –
- **append** (*bool*) –

__call__(*target, file_o*)

Call self as a function.

Parameters

- **target** (*Dict[str, Any]*) –
- **file_o** (*Any*) –

Return type

None

__init__(*format, append*)

Parameters

- **format** (*str*) –
- **append** (*bool*) –

Return type

None

pytorch_pfn_extras.training.extensions.lr_scheduler**Classes**

<i>pytorch_pfn_extras.training.extensions.</i>	
<i>lr_scheduler.ExtensionsManagerProtocol(...)</i>	
<i>pytorch_pfn_extras.training.extensions.</i>	Trainer extension to adjust the learning rate using Py-
<i>lr_scheduler.LRScheduler(...)</i>	Torch's learning rate scheduler.
<i>pytorch_pfn_extras.training.extensions.</i>	Reduce learning rate when a metric has stopped improv-
<i>lr_scheduler.ReduceLROnPlateau(...)</i>	ing.

pytorch_pfn_extras.training.extensions.lr_scheduler.ExtensionsManagerProtocol

```
class pytorch_pfn_extras.training.extensions.lr_scheduler.ExtensionsManagerProtocol(*args,  
                                    **kwargs)
```

Bases: Protocol

Methods

```
__init__(*args, **kwargs)
```

```
get_extension(name)
```

Attributes

```
elapsed_time
epoch
epoch_detail
is_before_training
iteration
models
observation
optimizers
out
raw_models
reporter
stop_trigger
writer
```

```
__init__(*args, **kwargs)
property elapsed_time: float
property epoch: int
property epoch_detail: float
get_extension(name)

    Parameters
        name (str) ->

    Return type
        Extension

    property is_before_training: bool
    property iteration: int
    property models: Mapping[str, Module]
    property observation: reporting.Observation
    property optimizers: Mapping[str, Optimizer]
```

```

property out: str
property raw_models: Mapping[str, Module]
property reporter: reporting.Reporter
property stop_trigger: bool
property writer: Optional[writing.Writer]

```

pytorch_pfn_extras.training.extensions.lr_scheduler.LRScheduler

```

class pytorch_pfn_extras.training.extensions.lr_scheduler.LRScheduler(scheduler, *,  

    stepper=<function  

    _default_stepper>,  

    trigger=(1, 'epoch'),  

    wait_for_first_optimizer_step=False,  

    is_async=True)

```

Bases: *Extension*

Trainer extension to adjust the learning rate using PyTorch's learning rate scheduler.

This extension calls `step()` method of the given LR scheduler. (`torch.option.lr_scheduler.*`). When using `ReduceLROnPlateau`, the latest reported `val/loss` value will be used. This behavior can be customized by passing a custom `stepper` function.

Parameters

- **scheduler** (`_LRScheduler` or `ReduceLROnPlateau`) – Any instance of `torch.optim.lr_scheduler.*`.
- **stepper** (`callable`) – Function that performs the step on the scheduler.
- **trigger** (`Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]]`) – Frequency to call this extension.
- **wait_for_first_optimizer_step** (`bool`) – Wait until `optimizer.step()` is called before invoking `scheduler.step()`. This can address the issue where `optimizer.step()` is not called from the first iteration when using GradScaler.
- **is_async** (`bool`) –

Methods

`__init__(scheduler, *[stepper, trigger, ...])`

<code>finalize(manager)</code>	Finalizes the extension.
<code>initialize(manager)</code>	Initializes up the manager state.
<code>load_state_dict(state)</code>	
<code>on_error(manager, exc, tb)</code>	Handles the error raised during training before finalization.
<code>state_dict()</code>	Serializes the extension state.
<code>step_by_value(key)</code>	

Attributes

<code>default_name</code>	Default name of the extension.
<code>is_async</code>	
<code>name</code>	
<code>needs_model_state</code>	
<code>priority</code>	
<code>trigger</code>	

`__call__(manager)`

Invokes the extension.

Implementations should override this operator. This method is called at iterations which the corresponding trigger accepts.

Parameters

`manager` ([ExtensionsManager](#)) – Manager object to call this operator.

Return type

None

`__init__(scheduler, *, stepper=<function _default_stepper>, trigger=(1, 'epoch'), wait_for_first_optimizer_step=False, is_async=True)`

Parameters

- `scheduler` (*Any*) –
- `stepper` (*Any*) –
- `trigger` (*Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]]*) –
- `wait_for_first_optimizer_step` (*bool*) –
- `is_async` (*bool*) –

Return type

None

`load_state_dict(state)`

Parameters

`state` (*Dict[str, Any]*) –

Return type

None

`state_dict()`

Serializes the extension state.

It is called when a manager that owns this extension is serialized. It serializes nothing by default.

Return type

Dict[str, Any]

```
static step_by_value(key)

Parameters
key (Optional[str]) –
```

Return type
Any

[pytorch_pfn_extras.training.extensions.lr_scheduler.ReduceLROnPlateau](#)

```
class pytorch_pfn_extras.training.extensions.lr_scheduler.ReduceLROnPlateau(optimizer,
mode='min',
factor=0.1,
patience=10,
thresh-
old=0.0001,
thresh-
old_mode='rel',
cooldown=0,
min_lr=0,
eps=1e-08,
verbose=False)
```

Bases: `object`

Reduce learning rate when a metric has stopped improving. Models often benefit from reducing the learning rate by a factor of 2-10 once learning stagnates. This scheduler reads a metrics quantity and if no improvement is seen for a ‘patience’ number of epochs, the learning rate is reduced.

Parameters

- **optimizer** (`Optimizer`) – Wrapped optimizer.
- **mode** (`str`) – One of *min*, *max*. In *min* mode, lr will be reduced when the quantity monitored has stopped decreasing; in *max* mode it will be reduced when the quantity monitored has stopped increasing. Default: ‘min’.
- **factor** (`float`) – Factor by which the learning rate will be reduced. `new_lr = lr * factor`. Default: 0.1.
- **patience** (`int`) – Number of epochs with no improvement after which learning rate will be reduced. For example, if *patience* = 2, then we will ignore the first 2 epochs with no improvement, and will only decrease the LR after the 3rd epoch if the loss still hasn’t improved then. Default: 10.
- **threshold** (`float`) – Threshold for measuring the new optimum, to only focus on significant changes. Default: 1e-4.
- **threshold_mode** (`str`) – One of *rel*, *abs*. In *rel* mode, `dynamic_threshold = best * (1 + threshold)` in ‘max’ mode or `best * (1 - threshold)` in *min* mode. In *abs* mode, `dynamic_threshold = best + threshold` in *max* mode or `best - threshold` in *min* mode. Default: ‘rel’.
- **cooldown** (`int`) – Number of epochs to wait before resuming normal operation after lr has been reduced. Default: 0.
- **min_lr** (`float or list`) – A scalar or a list of scalars. A lower bound on the learning rate of all param groups or each group respectively. Default: 0.

- **eps** (*float*) – Minimal decay applied to lr. If the difference between new and old lr is smaller than eps, the update is ignored. Default: 1e-8.
- **verbose** (*bool*) – If True, prints a message to stdout for each update. Default: False.

Example

```
>>> # xdoctest: +SKIP
>>> optimizer = torch.optim.SGD(model.parameters(), lr=0.1, momentum=0.9)
>>> scheduler = ReduceLROnPlateau(optimizer, 'min')
>>> for epoch in range(10):
>>>     train(...)
>>>     val_loss = validate(...)
>>>     # Note that step should be called after validate()
>>>     scheduler.step(val_loss)
```

Methods

```
__init__(optimizer[, mode, factor, ...])
```

```
is_better(a, best)
```

```
load_state_dict(state_dict)
```

```
state_dict()
```

```
step(metrics[, epoch])
```

Attributes

```
in_cooldown
```

```
__init__(optimizer, mode='min', factor=0.1, patience=10, threshold=0.0001, threshold_mode='rel',
        cooldown=0, min_lr=0, eps=1e-08, verbose=False)

property in_cooldown

is_better(a, best)

load_state_dict(state_dict)

state_dict()

step(metrics, epoch=None)
```

pytorch_pfn_extras.training.extensions.micro_average**Classes**

<i>pytorch_pfn_extras.training.extensions.</i>	
<i>micro_average.ExtensionsManagerProtocol(...)</i>	
<i>pytorch_pfn_extras.training.extensions.</i>	Calculates micro-average ratio.
<i>micro_average.MicroAverage(...)</i>	

pytorch_pfn_extras.training.extensions.micro_average.ExtensionsManagerProtocol

```
class pytorch_pfn_extras.training.extensions.micro_average.ExtensionsManagerProtocol(*args,  
                                    **kwargs)
```

Bases: Protocol

Methods

```
__init__(*args, **kwargs)
```

```
get_extension(name)
```

Attributes

`elapsed_time`

`epoch`

`epoch_detail`

`is_before_training`

`iteration`

`models`

`observation`

`optimizers`

`out`

`raw_models`

`reporter`

`stop_trigger`

`writer`

`__init__(*args, **kwargs)`

`property elapsed_time: float`

`property epoch: int`

`property epoch_detail: float`

`get_extension(name)`

Parameters

`name (str) –`

Return type

`Extension`

`property is_before_training: bool`

`property iteration: int`

`property models: Mapping[str, Module]`

`property observation: reporting.Observation`

`property optimizers: Mapping[str, Optimizer]`

```

property out: str
property raw_models: Mapping[str, Module]
property reporter: reporting.Reporter
property stop_trigger: bool
property writer: Optional[writing.Writer]

```

`pytorch_pfn_extras.training.extensions.micro_average.MicroAverage`

```

class pytorch_pfn_extras.training.extensions.micro_average.MicroAverage(numerator_key,
denominator_key,
result_key, trigger=(1,
'epoch'))

```

Bases: *Extension*

Calculates micro-average ratio.

Give N batches and values $\{n_1, \dots, n_N\}$ and $\{d_1, \dots, d_N\}$, this extension calculates micro-average of these ratio defined as:

$$\frac{\sum_i^N n_i}{\sum_i^N d_i}.$$

A user usually uses the number of examples which a system correctly predict as n_i and the number of total examples in i -th batch as d_i . This value is called macro-average of precision.

Note that macro-average is defined as:

$$\frac{1}{N} \sum_i^N (n_i/d_i),$$

It is same to the micro-average when each mini-batch has the same d_i .

You need to report numerator value (the number of correct examples) and denominator value (the number of examples) in your model.

```

>>> class MyModel(torch.nn.Module):
...     def __call__(self, x, y):
...         loss = torch.nn.CrossEntropyLoss(x, y)
...         correct = (x.data.argmax(axis=1) == y.data).sum()
...         total = len(y.data)
...         reporting.report({'correct': correct, 'total': total}, self)
...         return loss

```

And then, make an extension with corresponding reporting keys and register it.

```

>>> ext = extensions.MicroAverage(
...     'main/correct', 'main/total', 'main/accuracy')

```

Parameters

- **numerator_key** (str) – Key string of obserbation storing a numerator value.
- **denominator_key** (str) – Key string of obserbation storing a denominator value.

- **result_key (str)** – Key string of observation to store a result.
- **trigger (Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]])** – Trigger that decides when to calculate average. This is distinct from the trigger of this extension itself. If it is a tuple in the form <int>, 'epoch' or <int>, 'iteration', it is passed to IntervalTrigger.

Methods

<code>__init__(numerator_key, denominator_key, ...)</code>	
<code>finalize(manager)</code>	Finalizes the extension.
<code>initialize(manager)</code>	Initializes up the manager state.
<code>load_state_dict(to_load)</code>	
<code>on_error(manager, exc, tb)</code>	Handles the error raised during training before finalization.
<code>state_dict()</code>	Serializes the extension state.

Attributes

<code>default_name</code>	Default name of the extension.
<code>is_async</code>	
<code>name</code>	
<code>needs_model_state</code>	
<code>priority</code>	
<code>trigger</code>	

`__call__(manager)`

Invokes the extension.

Implementations should override this operator. This method is called at iterations which the corresponding trigger accepts.

Parameters

`manager` (`ExtensionsManager`) – Manager object to call this operator.

Return type

None

`__init__(numerator_key, denominator_key, result_key, trigger=(1, 'epoch'))`

Parameters

- **numerator_key (str)** –
- **denominator_key (str)** –
- **result_key (str)** –

- **trigger**(*Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]]*) –

Return type
None

load_state_dict(*to_load*)

Parameters
to_load(*Dict[str, Any]*) –

Return type
None

priority: *int* = 200

state_dict()

Serializes the extension state.

It is called when a manager that owns this extension is serialized. It serializes nothing by default.

Return type
Dict[str, Any]

pytorch_pfn_extras.training.extensions.parameter_statistics

Classes

<i>pytorch_pfn_extras.training.extensions.parameter_statistics.ExtensionsManagerProtocol(...)</i>	An extension to report parameter statistics.
<i>pytorch_pfn_extras.training.extensions.parameter_statistics.ParameterStatistics(links)</i>	

pytorch_pfn_extras.training.extensions.parameter_statistics.ExtensionsManagerProtocol

class *pytorch_pfn_extras.training.extensions.parameter_statistics.ExtensionsManagerProtocol(*args, **kwargs)*

Bases: Protocol

Methods

__init__(*args, **kwargs)

get_extension(*name*)

Attributes

`elapsed_time`

`epoch`

`epoch_detail`

`is_before_training`

`iteration`

`models`

`observation`

`optimizers`

`out`

`raw_models`

`reporter`

`stop_trigger`

`writer`

`__init__(*args, **kwargs)`

`property elapsed_time: float`

`property epoch: int`

`property epoch_detail: float`

`get_extension(name)`

Parameters

`name (str) –`

Return type

`Extension`

`property is_before_training: bool`

`property iteration: int`

`property models: Mapping[str, Module]`

`property observation: reporting.Observation`

`property optimizers: Mapping[str, Optimizer]`

```
property out: str
property raw_models: Mapping[str, Module]
property reporter: reporting.Reporter
property stop_trigger: bool
property writer: Optional[writing.Writer]
```

pytorch_pfn_extras.training.extensions.parameter_statistics.ParameterStatistics

```
class pytorch_pfn_extras.training.extensions.parameter_statistics.ParameterStatistics(links,
                                         statistics='default',
                                         report_params=True,
                                         report_grads=True,
                                         prefix=None,
                                         trigger=(I,
                                         'epoch'),
                                         skip_nan_params=False)
```

Bases: *Extension*

An extension to report parameter statistics.

Statistics are collected and reported for a given `Module` or an iterable of `Modules`. If a link contains child modules, the statistics are reported separately for each child.

Any function that takes a one-dimensional `torch.Tensor` and outputs a single or multiple real numbers can be registered to handle the collection of statistics, e.g. `numpy.ndarray.mean()`.

The keys of reported statistics follow the convention of link name followed by parameter name, attribute name and function name, e.g. `VGG16Layers/conv1_1/W/data/mean`. They are prepended with an optional prefix and appended with integer indices if the statistics generating function return multiple values.

Parameters

- **links** (*instance or iterable of Module*) – `Module`(s) containing the parameters to observe. The link is expected to have a `name` attribute which is used as a part of the report key.
- **statistics** (*dict or 'default'*) – Dictionary with function name to function mappings. The name is a string and is used as a part of the report key. The function is responsible for generating the statistics. If the special value '`default`' is specified, the default statistics functions will be used.
- **report_params** (*bool*) – If `True`, report statistics for parameter values such as weights and biases.
- **report_grads** (*bool*) – If `True`, report statistics for parameter gradients.
- **prefix** (*str*) – Optional prefix to prepend to the report keys.

- **trigger**(*Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]]*) – Trigger that decides when to aggregate the results and report the values.
 - **skip_nan_params**(*bool*) – If True, statistics are not computed for parameters including NaNs and a single NaN value is immediately reported instead. Otherwise, this extension will simply try to compute the statistics without performing any checks for NaNs.
-

Note: The default statistic functions are as follows:

- 'mean' (`xp.mean(x)`)
 - 'std' (`xp.std(x)`)
 - 'min' (`xp.min(x)`)
 - 'max' (`xp.max(x)`)
 - 'zeros' (`xp.count_nonzero(x == 0)`)
 - 'percentile' (`xp.percentile(x, (0.13, 2.28, 15.87, 50, 84.13, 97.72, 99.87))`)
-

Methods

`__init__(links[, statistics, report_params, ...])`

<code>finalize(manager)</code>	Finalizes the extension.
<code>initialize(manager)</code>	Initializes up the manager state.
<code>load_state_dict(to_load)</code>	
<code>on_error(manager, exc, tb)</code>	Handles the error raised during training before finalization.
<code>register_statistics(name, function)</code>	Register a function to compute a certain statistic.
<code>state_dict()</code>	Serializes the extension state.

Attributes

`default_name`

`default_statistics`

`is_async`

`name`

`needs_model_state`

`priority`

`report_key_template`

`trigger`

__call__(manager)

Execute the statistics extension.

Collect statistics for the current state of parameters.

Note that this method will merely update its statistic summary, unless the internal trigger is fired. If the trigger is fired, the summary will also be reported and then reset for the next accumulation.

Parameters

manager ([ExtensionsManager](#)) – Associated manager that invoked this extension.

Return type

None

__init__(links, statistics='default', report_params=True, report_grads=True, prefix=None, trigger=(1, 'epoch'), skip_nan_params=False)**Parameters**

- **links** (*Any*) –
- **statistics** (*Any*) –
- **report_params** (*bool*) –
- **report_grads** (*bool*) –
- **prefix** (*Optional[str]*) –
- **trigger** (*Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]]*) –
- **skip_nan_params** (*bool*) –

default_name = 'parameter_statistics'

default_statistics = {'max': <function <lambda>>, 'mean': <function <lambda>>, 'min': <function <lambda>>, 'std': <function <lambda>>, 'zeros': <function <lambda>>}'

priority: int = 300

register_statistics(name, function)

Register a function to compute a certain statistic.

The registered function will be called each time the extension runs and the results will be included in the report.

Parameters

- **name** (*str*) – Name of the statistic.
- **function** (*Any*) – Function to generate the statistic. Any function that takes a one-dimensional `numpy.ndarray` or a `cupy.ndarray` and outputs a single or multiple real numbers is allowed.

Return type

None

report_key_template = '{prefix}{param_name}/{attr_name}/{function_name}'

[pytorch_pfn_extras.training.extensions.plot_report](#)

Functions

`pytorch_pfn_extras.training.extensions.
plot_report.matplotlib_savefun(...)`

[pytorch_pfn_extras.training.extensions.plot_report.matplotlib_savefun](#)

`pytorch_pfn_extras.training.extensions.plot_report.matplotlib_savefun(target, file_o)`

Parameters

- **target** (*Tuple[Any, Any, Any]*) –
- **file_o** (*Any*) –

Return type

`None`

Classes

`pytorch_pfn_extras.training.extensions.
plot_report.ExtensionsManagerProtocol(...)`

`pytorch_pfn_extras.training.extensions.
plot_report.PlotReport(y_keys)`

[pytorch_pfn_extras.training.extensions.plot_report.ExtensionsManagerProtocol](#)

`class pytorch_pfn_extras.training.extensions.plot_report.ExtensionsManagerProtocol(*args,
**kwargs)`

Bases: `Protocol`

Methods

`__init__(*args, **kwargs)`

`get_extension(name)`

Attributes

elapsed_time

epoch

epoch_detail

is_before_training

iteration

models

observation

optimizers

out

raw_models

reporter

stop_trigger

writer

`__init__(*args, **kwargs)`

`property elapsed_time: float`

`property epoch: int`

`property epoch_detail: float`

`get_extension(name)`

Parameters

`name (str) –`

Return type

Extension

`property is_before_training: bool`

`property iteration: int`

`property models: Mapping[str, Module]`

`property observation: reporting.Observation`

`property optimizers: Mapping[str, Optimizer]`

```
property out: str
property raw_models: Mapping[str, Module]
property reporter: reporting.Reporter
property stop_trigger: bool
property writer: Optional[writing.Writer]
```

pytorch_pfn_extras.training.extensions.plot_report.PlotReport

```
class pytorch_pfn_extras.training.extensions.plot_report.PlotReport(y_keys, x_key='iteration',
                                                                    trigger=(1, 'epoch'),
                                                                    postprocess=None,
                                                                    filename='plot.png',
                                                                    marker='x', grid=True)
```

Bases: *Extension*

An extension to output plots.

This extension accumulates the observations of the manager to *DictSummary* at a regular interval specified by a supplied trigger, and plot a graph with using them.

There are two triggers to handle this extension. One is the trigger to invoke this extension, which is used to handle the timing of accumulating the results. It is set to 1, 'iteration' by default. The other is the trigger to determine when to emit the result. When this trigger returns True, this extension appends the summary of accumulated values to the list of past summaries, and writes the list to the log file. Then, this extension makes a new fresh summary object which is used until the next time that the trigger fires.

It also adds 'epoch' and 'iteration' entries to each result dictionary, which are the epoch and iteration counts at the output.

Warning: If your environment needs to specify a backend of matplotlib explicitly, please call `matplotlib.use` before calling `manager.run_iteration`. For example:

```
import matplotlib
matplotlib.use('Agg')

manager.extend(
    extensions.PlotReport(['main/loss', 'validation/main/loss'],
                          'epoch', filename='loss.png'))
with manager.run_iteration():
    pass
```

Then, once one of instances of this extension is called, `matplotlib.use` will have no effect.

For the details, please see here: https://matplotlib.org/faq/usage_faq.html#what-is-a-backend

Parameters

- **y_keys** (*iterable of strs*) – Keys of values regarded as y. If this is None, nothing is output to the graph.
- **x_key** (*str*) – Keys of values regarded as x. The default value is ‘iteration’.

- **trigger** (*Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]]*) – Trigger that decides when to aggregate the result and output the values. This is distinct from the trigger of this extension itself. If it is a tuple in the form <int>, 'epoch' or <int>, 'iteration', it is passed to IntervalTrigger.
- **postprocess** (*Any*) – Callback to postprocess the result dictionaries. Figure object, Axes object, and all plot data are passed to this callback in this order. This callback can modify the figure.
- **filename** (*str*) – Name of the figure file under the output directory. It can be a format string. For historical reasons `file_name` is also accepted as an alias of this argument.
- **marker** (*str*) – The marker used to plot the graph. Default is 'x'. If `None` is given, it draws with no markers.
- **grid** (*bool*) – If True, set the axis grid on. The default value is True.
- **writer** (*writer object, optional*) – must be callable. object to dump the log to. If specified, it needs to have a correct `savefun` defined. The writer can override the save location in the `pytorch_pfn_extras.training.ExtensionsManager` object
- **kwarg** (*Any*) –

Methods

<code>__init__(y_keys[, x_key, trigger, ...])</code>	
<code>available()</code>	
<code>finalize(manager)</code>	Finalizes the extension.
<code>initialize(manager)</code>	Initializes up the manager state.
<code>load_state_dict(to_load)</code>	
<code>on_error(manager, exc, tb)</code>	Handles the error raised during training before finalization.
<code>state_dict()</code>	Serializes the extension state.

Attributes

<code>default_name</code>	Default name of the extension.
<code>is_async</code>	
<code>name</code>	
<code>needs_model_state</code>	
<code>priority</code>	
<code>trigger</code>	

```
__call__(manager)
    Invokes the extension.

    Implementations should override this operator. This method is called at iterations which the corresponding trigger accepts.

Parameters
    manager (ExtensionsManager) – Manager object to call this operator.

Return type
    None

_init_(y_keys, x_key='iteration', trigger=(1, 'epoch'), postprocess=None, filename=None, marker='x', grid=True, **kwargs)

Parameters
    • y_keys (Union\[Iterable\[str\], str\]) –
    • x_key (str) –
    • trigger (Optional\[Union\[Trigger, Callable\[\[ExtensionsManagerProtocol\], bool\], Tuple\[float, str\]\]\]) –
    • postprocess (Optional\[Any\]) –
    • filename (Optional\[str\]) –
    • marker (str) –
    • grid (bool) –
    • kwargs (Any) –

static available()

Return type
    bool

finalize(manager)
    Finalizes the extension.

    This method is called at the end of the training loop.

Parameters
    manager (ExtensionsManagerProtocol) –

Return type
    None

load_state_dict(to_load)

Parameters
    to_load (Dict\[str, Any\]) –

Return type
    None

state_dict()
    Serializes the extension state.

    It is called when a manager that owns this extension is serialized. It serializes nothing by default.

Return type
    Dict\[str, Any\]
```

pytorch_pfn_extras.training.extensions.print_report

Functions

<code>pytorch_pfn_extras.training.extensions.print_report.create_header_and_templates(entries)</code>	Construct header and templates from <i>entries</i>
<code>pytorch_pfn_extras.training.extensions.print_report.deepcopy(x)</code>	Deep copy operation on arbitrary Python objects.
<code>pytorch_pfn_extras.training.extensions.print_report.filter_and_sort_entries(...)</code>	

pytorch_pfn_extras.training.extensions.print_report.create_header_and_templates

`pytorch_pfn_extras.training.extensions.print_report.create_header_and_templates(entries)`
Construct header and templates from *entries*

Parameters

`entries (list) – list of str`

Returns

`header string templates (str): template string for print values.`

Return type

`header (str)`

pytorch_pfn_extras.training.extensions.print_report.deepcopy

`pytorch_pfn_extras.training.extensions.print_report.deepcopy(x, memo=None, _nil=[])`
Deep copy operation on arbitrary Python objects.

See the module's `__doc__` string for more info.

pytorch_pfn_extras.training.extensions.print_report.filter_and_sort_entries

`pytorch_pfn_extras.training.extensions.print_report.filter_and_sort_entries(all_entries, unit='epoch')`

Parameters

- `all_entries (List[str]) –`
- `unit (str) –`

Return type

`List[str]`

Classes

<code>pytorch_pfn_extras.training.extensions. print_report.ExtensionsManagerProtocol(...)</code>	
<code>pytorch_pfn_extras.training.extensions. print_report.IO(...)</code>	Generic base class for TextIO and BinaryIO.
<code>pytorch_pfn_extras.training.extensions. print_report.PrintReport([...])</code>	An extension to print the accumulated results.

`pytorch_pfn_extras.training.extensions.print_report.ExtensionsManagerProtocol`

```
class pytorch_pfn_extras.training.extensions.print_report.ExtensionsManagerProtocol(*args,  
                                    **kwargs)
```

Bases: Protocol

Methods

```
__init__(*args, **kwargs)
```

```
get_extension(name)
```

Attributes

```
elapsed_time
epoch
epoch_detail
is_before_training
iteration
models
observation
optimizers
out
raw_models
reporter
stop_trigger
writer
```

```
__init__(*args, **kwargs)
property elapsed_time: float
property epoch: int
property epoch_detail: float
get_extension(name)

    Parameters
        name (str) ->

    Return type
        Extension

    property is_before_training: bool
    property iteration: int
    property models: Mapping[str, Module]
    property observation: reporting.Observation
    property optimizers: Mapping[str, Optimizer]
```

```
property out: str
property raw_models: Mapping[str, Module]
property reporter: reporting.Reporter
property stop_trigger: bool
property writer: Optional[writing.Writer]
```

[pytorch_pfn_extras.training.extensions.print_report.IO](#)

```
class pytorch_pfn_extras.training.extensions.print_report.IO(*args, **kwds)
```

Bases: Generic

Generic base class for TextIO and BinaryIO.

This is an abstract, generic version of the return of open().

NOTE: This does not distinguish between the different possible classes (text vs. binary, read vs. write vs. read/write, append-only, unbuffered). The TextIO and BinaryIO subclasses below capture the distinctions between text vs. binary, which is pervasive in the interface; however we currently do not offer a way to track the other distinctions in the type system.

Methods

`__init__()`

`close()`

`fileno()`

`flush()`

`isatty()`

`read([n])`

`readable()`

`readline([limit])`

`readlines([hint])`

`seek(offset[, whence])`

`seekable()`

`tell()`

`truncate([size])`

`writable()`

`write(s)`

`writelines(lines)`

Attributes

`closed`

`mode`

`name`

`abstract close()`

Return type

None

abstract property closed: bool

```
abstract fileno()

    Return type
        int

abstract flush()

    Return type
        None

abstract isatty()

    Return type
        bool

abstract property mode: str

abstract property name: str

abstract read(n=-1)

    Parameters
        n (int) –
    Return type
        AnyStr

abstract readable()

    Return type
        bool

abstract readline(limit=-1)

    Parameters
        limit (int) –
    Return type
        AnyStr

abstract readlines(hint=-1)

    Parameters
        hint (int) –
    Return type
        List

abstract seek(offset, whence=0)

    Parameters
        • offset (int) –
        • whence (int) –
    Return type
        int

abstract seekable()

    Return type
        bool
```

```
abstract tell()

    Return type
        int

abstract truncate(size=None)

    Parameters
        size (Optional[int]) –

    Return type
        int

abstract writable()

    Return type
        bool

abstract write(s)

    Parameters
        s (AnyStr) –

    Return type
        int

abstract writelines(lines)

    Parameters
        lines (List) –

    Return type
        None
```

[pytorch_pfn_extras.training.extensions.print_report.PrintReport](#)

```
class pytorch_pfn_extras.training.extensions.print_report.PrintReport(entries=None,
                                                                    log_report='LogReport',
                                                                    out=<_io.TextIOWrapper
                                                                    name='<stdout>''
                                                                    mode='w'
                                                                    encoding='utf-8'')
```

Bases: *Extension*

An extension to print the accumulated results.

This extension uses the log accumulated by a `LogReport` extension to print specified entries of the log in a human-readable format.

Parameters

- **entries** (`list of str or None`) – List of keys of observations to print. If `None` is passed, automatically infer keys from reported dict.
- **log_report** (`str or LogReport`) – Log report to accumulate the observations. This is either the name of a `LogReport` extensions registered to the manager, or a `LogReport` instance to use internally.
- **out** (`IIO[Any]`) – Stream to print the bar. Standard output is used by default.

Methods

<code>__init__([entries, log_report, out])</code>	
<code>finalize(manager)</code>	Finalizes the extension.
<code>get_log_report(manager)</code>	
<code>initialize(manager)</code>	Initializes up the manager state.
<code>load_state_dict(to_load)</code>	
<code>on_error(manager, exc, tb)</code>	Handles the error raised during training before finalization.
<code>state_dict()</code>	Serializes the extension state.

Attributes

<code>default_name</code>	Default name of the extension.
<code>is_async</code>	
<code>name</code>	
<code>needs_model_state</code>	
<code>priority</code>	
<code>trigger</code>	

`__call__(manager)`
Invokes the extension.
Implementations should override this operator. This method is called at iterations which the corresponding trigger accepts.

Parameters

`manager` ([ExtensionsManager](#)) – Manager object to call this operator.

Return type

None

`__init__(entries=None, log_report='LogReport', out=<_io.TextIOWrapper name='<stdout>' mode='w' encoding='utf-8'>)`

Parameters

- `entries` (*Optional[Sequence[str]]*) –
- `log_report` (*Union[str, LogReport]*) –
- `out` ([IO\[Any\]](#)) –

Return type

None

`get_log_report(manager)`

Parameters

`manager (ExtensionsManagerProtocol) –`

Return type

`LogReport`

`initialize(manager)`

Initializes up the manager state.

This method is called before entering the training loop. An extension modifying the state of `ExtensionsManager` can override this method to initialize it.

When the manager has been restored from a snapshot, this method has to recover an appropriate part of the state of the manager.

Parameters

`manager (ExtensionsManager) – Manager object to call this extension.`

Return type

`None`

`load_state_dict(to_load)`

Parameters

`to_load (Dict[str, Any]) –`

Return type

`None`

`state_dict()`

Serializes the extension state.

It is called when a manager that owns this extension is serialized. It serializes nothing by default.

Return type

`Dict[str, Any]`

`pytorch_pfn_extras.training.extensions.profile_report`

Functions

`pytorch_pfn_extras.training.extensions.
profile_report.get_time_summary()`

`pytorch_pfn_extras.training.extensions.profile_report.get_time_summary`

`pytorch_pfn_extras.training.extensions.profile_report.get_time_summary()`

Return type

`TimeSummary`

Classes

<code>pytorch_pfn_extras.training. extensions.profile_report. ExtensionsManagerProtocol(...)</code>	
<code>pytorch_pfn_extras.training.extensions. profile_report.OrderedDict</code>	Dictionary that remembers insertion order
<code>pytorch_pfn_extras.training.extensions. profile_report.ProfileReport([...])</code>	Writes the profile results to a file.

`pytorch_pfn_extras.training.extensions.profile_report.ExtensionsManagerProtocol`

```
class pytorch_pfn_extras.training.extensions.profile_report.ExtensionsManagerProtocol(*args,  
                                     **kwargs)
```

Bases: Protocol

Methods

```
__init__(*args, **kwargs)
```

```
get_extension(name)
```

Attributes

elapsed_time

epoch

epoch_detail

is_before_training

iteration

models

observation

optimizers

out

raw_models

reporter

stop_trigger

writer

`__init__(*args, **kwargs)`

`property elapsed_time: float`

`property epoch: int`

`property epoch_detail: float`

`get_extension(name)`

Parameters

`name (str) –`

Return type

Extension

`property is_before_training: bool`

`property iteration: int`

`property models: Mapping[str, Module]`

`property observation: reporting.Observation`

`property optimizers: Mapping[str, Optimizer]`

```
property out: str
property raw_models: Mapping[str, Module]
property reporter: reporting.Reporter
property stop_trigger: bool
property writer: Optional[writing.Writer]
```

`pytorch_pfn_extras.training.extensions.profile_report.OrderedDict`

`class pytorch_pfn_extras.training.extensions.profile_report.OrderedDict`

Bases: dict

Dictionary that remembers insertion order

Methods

`__init__(*args, **kwargs)`

`clear()`

`copy()`

`fromkeys([value])` Create a new ordered dictionary with keys from iterable and values set to value.

`get(key[, default])` Return the value for key if key is in the dictionary, else default.

`items()`

`keys()`

`move_to_end(key[, last])` Move an existing element to the end (or beginning if last is false).

`pop(k[,d])` value.

`popitem([last])` Remove and return a (key, value) pair from the dictionary.

`setdefault(key[, default])` Insert key with a value of default if key is not in the dictionary.

`update([E,]**F)` If E is present and has a .keys() method, then does: for k in E: D[k] = E[k] If E is present and lacks a .keys() method, then does: for k, v in E: D[k] = v In either case, this is followed by: for k in F: D[k] = F[k]

`values()`

`__init__(*args, **kwargs)`

`clear()` → None. Remove all items from od.

`copy()` → a shallow copy of od

fromkeys(*value=None*)

Create a new ordered dictionary with keys from iterable and values set to value.

items() → a set-like object providing a view on D's items**keys**() → a set-like object providing a view on D's keys**move_to_end**(*key, last=True*)

Move an existing element to the end (or beginning if last is false).

Raise KeyError if the element does not exist.

pop(*k[, d]*) → *v*, remove specified key and return the corresponding

value. If key is not found, *d* is returned if given, otherwise KeyError is raised.

popitem(*last=True*)

Remove and return a (key, value) pair from the dictionary.

Pairs are returned in LIFO order if last is true or FIFO order if false.

setdefault(*key, default=None*)

Insert key with a value of default if key is not in the dictionary.

Return the value for key if key is in the dictionary, else default.

update([*E*], ***F*) → None. Update D from dict/iterable E and F.

If E is present and has a .keys() method, then does: for k in E: D[k] = E[k] If E is present and lacks a .keys() method, then does: for k, v in E: D[k] = v In either case, this is followed by: for k in F: D[k] = F[k]

values() → an object providing a view on D's values**pytorch_pfn_extras.training.extensions.profile_report.ProfileReport**

```
class pytorch_pfn_extras.training.extensions.profile_report.ProfileReport(store_keys=None,
                                                               report_keys=None,
                                                               trigger=(1, 'epoch'),
                                                               filename=None,
                                                               append=False,
                                                               format=None,
                                                               **kwargs)
```

Bases: *Extension*

Writes the profile results to a file.

Times are reported by using the [pytorch_pfn_extras.profiler.TimeSummary.report\(\)](#) context manager.

Parameters

- **store_keys** (*iterable of strs*) – Keys of values to write to the profiler report file.
- **report_keys** (*iterable of strs*) – Keys of values that will be reported.
- **trigger** (*Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]]*) – Trigger that decides when to aggregate the result and output the values. This is distinct from the trigger of this extension itself. If it is a tuple in the form <int>, 'epoch' or <int>, 'iteration', it is passed to IntervalTrigger.

- **filename** (*str*) – Name of the log file under the output directory. It can be a format string: the last result dictionary is passed for the formatting. For example, users can use '{iteration}' to separate the log files for different iterations. If the log name is None, it does not output the log to any file.
- **append** (*bool, options1*) – If the file is JSON Lines or YAML, contents will be appended instead of rewriting the file every call.
- **format** (*str, optional*) – accepted values are 'json', 'json-lines' and 'yaml'.
- **writer** (*writer object, optional*) – must be callable. object to dump the log to. If specified, it needs to have a correct *savefun* defined. The writer can override the save location in the `pytorch_pfn_extras.training.ExtensionsManager` object
- **entries** (*list*) – list of str
- **kwargs** (*Any*) –

Returns

header string templates (*str*): template string for print values.

Return type

header (*str*)

Methods

`__init__([store_keys, report_keys, trigger, ...])`

<code>finalize(manager)</code>	Finalizes the extension.
<code>initialize(manager)</code>	Initializes up the manager state.
<code>load_state_dict(to_load)</code>	
<code>on_error(manager, exc, tb)</code>	Handles the error raised during training before finalization.
<code>state_dict()</code>	Serializes the extension state.

Attributes

<code>default_name</code>	Default name of the extension.
<code>is_async</code>	
<code>name</code>	
<code>needs_model_state</code>	
<code>priority</code>	
<code>trigger</code>	
<code>__call__(manager)</code>	
	Invokes the extension.

Implementations should override this operator. This method is called at iterations which the corresponding trigger accepts.

Parameters

manager ([ExtensionsManager](#)) – Manager object to call this operator.

Return type

None

__init__(*store_keys*=None, *report_keys*=None, *trigger*=(1, 'epoch'), *filename*=None, *append*=False, *format*=None, ***kwargs*)

Parameters

- **store_keys** (*Optional[Iterable[str]]*) –
- **report_keys** (*Optional[Iterable[str]]*) –
- **trigger** (*Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]]*) –
- **filename** (*Optional[str]*) –
- **append** (*bool*) –
- **format** (*Optional[str]*) –
- **kwargs** (*Any*) –

finalize(*manager*)

Finalizes the extension.

This method is called at the end of the training loop.

Parameters

manager ([ExtensionsManagerProtocol](#)) –

Return type

None

load_state_dict(*to_load*)

Parameters

to_load (*Dict[str, Any]*) –

Return type

None

state_dict()

Serializes the extension state.

It is called when a manager that owns this extension is serialized. It serializes nothing by default.

Return type

Dict[str, Any]

[pytorch_pfn_extras.training.extensions.progress_bar](#)

Classes

<i>pytorch_pfn_extras.training.extensions.progress_bar.ExtensionsManagerProtocol(...)</i>	
<i>pytorch_pfn_extras.training.extensions.progress_bar.ProgressBar([...])</i>	An extension to print a progress bar and recent training status.

[pytorch_pfn_extras.training.extensions.progress_bar.ExtensionsManagerProtocol](#)

```
class pytorch_pfn_extras.training.extensions.progress_bar.ExtensionsManagerProtocol(*args,  
                                **kwargs)
```

Bases: Protocol

Methods

```
__init__(*args, **kwargs)
```

```
get_extension(name)
```

Attributes

elapsed_time

epoch

epoch_detail

is_before_training

iteration

models

observation

optimizers

out

raw_models

reporter

stop_trigger

writer

`__init__(*args, **kwargs)`

`property elapsed_time: float`

`property epoch: int`

`property epoch_detail: float`

`get_extension(name)`

Parameters

`name (str) –`

Return type

Extension

`property is_before_training: bool`

`property iteration: int`

`property models: Mapping[str, Module]`

`property observation: reporting.Observation`

`property optimizers: Mapping[str, Optimizer]`

```
property out: str
property raw_models: Mapping[str, Module]
property reporter: reporting.Reporter
property stop_trigger: bool
property writer: Optional[writing.Writer]
```

[pytorch_pfn_extras.training.extensions.progress_bar.ProgressBar](#)

```
class pytorch_pfn_extras.training.extensions.progress_bar.ProgressBar(training_length=None,
                                                                    update_interval=100,
                                                                    bar_length=50,
                                                                    out=<_io.TextIOWrapper
                                                                    name='<stdout>'
                                                                    mode='w'
                                                                    encoding='utf-8'>)
```

Bases: [Extension](#)

An extension to print a progress bar and recent training status.

This extension prints a progress bar at every call. It watches the current iteration and epoch to print the bar.

Parameters

- **training_length** (*tuple or None*) – Length of whole training. It consists of an integer and either 'epoch' or 'iteration'. If this value is omitted and the stop trigger of the manager is `IntervalTrigger`, this extension uses its attributes to determine the length of the training.
- **update_interval** (*int*) – Number of iterations to skip printing the progress bar.
- **bar_length** (*int*) – Length of the progress bar in characters.
- **out** (*Any*) – Stream to print the bar. Standard output is used by default.

Methods

```
__init__([training_length, update_interval, ...])
```

<code>finalize(manager)</code>	Finalizes the extension.
<code>initialize(manager)</code>	Initializes up the manager state.
<code>load_state_dict(to_load)</code>	
<code>on_error(manager, exc, tb)</code>	Handles the error raised during training before finalization.
<code>state_dict()</code>	Serializes the extension state.

Attributes

<code>default_name</code>	Default name of the extension.
<code>is_async</code>	
<code>name</code>	
<code>needs_model_state</code>	
<code>priority</code>	
<code>trigger</code>	

`__call__(manager)`

Invokes the extension.

Implementations should override this operator. This method is called at iterations which the corresponding trigger accepts.

Parameters

`manager` ([ExtensionsManager](#)) – Manager object to call this operator.

Return type

None

`__init__(training_length=None, update_interval=100, bar_length=50, out=<_io.TextIOWrapper name='<stdout>' mode='w' encoding='utf-8'>)`

Parameters

- `training_length` (*Optional[Any]*) –
- `update_interval` (*int*) –
- `bar_length` (*int*) –
- `out` (*Any*) –

`finalize(manager)`

Finalizes the extension.

This method is called at the end of the training loop.

Parameters

`manager` ([ExtensionsManagerProtocol](#)) –

Return type

None

[pytorch_pfn_extras.training.extensions.slack](#)

Classes

<code>pytorch_pfn_extras.training.extensions. slack.ExtensionsManagerProtocol(...)</code>	
<code>pytorch_pfn_extras.training.extensions. slack.Slack(channel)</code>	An extension to communicate with Slack.
<code>pytorch_pfn_extras.training.extensions. slack.SlackWebhook(url)</code>	An extension to communicate with Slack using Incoming Webhook.

[pytorch_pfn_extras.training.extensions.slack.ExtensionsManagerProtocol](#)

```
class pytorch_pfn_extras.training.extensions.slack.ExtensionsManagerProtocol(*args,  
                           **kwargs)
```

Bases: `Protocol`

Methods

```
__init__(*args, **kwargs)
```

```
get_extension(name)
```

Attributes

elapsed_time

epoch

epoch_detail

is_before_training

iteration

models

observation

optimizers

out

raw_models

reporter

stop_trigger

writer

`__init__(*args, **kwargs)`

`property elapsed_time: float`

`property epoch: int`

`property epoch_detail: float`

`get_extension(name)`

Parameters

`name (str) –`

Return type

Extension

`property is_before_training: bool`

`property iteration: int`

`property models: Mapping[str, Module]`

`property observation: reporting.Observation`

`property optimizers: Mapping[str, Optimizer]`

```
property out: str
property raw_models: Mapping[str, Module]
property reporter: reporting.Reporter
property stop_trigger: bool
property writer: Optional[writing.Writer]
```

pytorch_pfn_extras.training.extensions.slack.Slack

```
class pytorch_pfn_extras.training.extensions.slack.Slack(channel, msg=None, *,
                                                       start_msg='{default}',
                                                       end_msg='{default}',
                                                       error_msg='{default}', thread=True,
                                                       filenames=None, upload_trigger=None,
                                                       context=None, token=None)
```

Bases: _SlackBase

An extension to communicate with Slack.

Example

```
>>> ppe.training.extensions.Slack(
...     channel="experiment-progress",
...     msg="Epoch #{manager.epoch}: loss = {val/loss}",
...     end_msg="{default} \n <@username> Check out the result!",
...
...     # Upload files at the end of the experiment.
...     filenames=["result/statistics.png"],
...     upload_trigger=(max_epoch, 'epoch'),
... )
```

This extension posts a message when:

- `start_msg`: The training has started
- `msg`: The extension is triggered, usually at the end of each epoch
- `end_msg`: The training has finished
- `error_msg`: An exception has raised during the training

These messages can be specified as a format string, a callable that returns a string, or None to disable posting on that event.

When using a format string, the following variables are available for use:

- `manager`: an ExtensionsManager object
- `default`: the default message string
- `context`: an arbitrary object passed to this extension
- `error`: an Exception object (for `error_msg` only)
- All reported values (`manager.observations`)

When using a callable, it should take (*ExtensionsManager, context*) or (*ExtensionsManager, Exception, context*) (for `error_msg`) and return a string.

This extension can upload files along with the message when triggered. `filenames` can be a list of filenames (the same formatting rule as `msg` apply), or a callable taking (*ExtensionsManager, context*) and returning a list of filenames.

To use this extension, you must create a Slack app, then specify the token via an environment variable `SLACK_BOT_TOKEN` or `token` option.

Parameters

- **channel** (*str*) – The channel where messages and files will be sent. This can be a channel name or a channel ID.
- **msg** (*str, callable, or None*) – A message to be sent when triggered. It can be a string to be formatted using `.format` or a callable that returns a string.
- **start_msg** (*str, callable, or None*) – A message to be sent at the beginning of the experiment.
- **end_msg** (*str, callable, or None*) – A message to be sent at the completion of the experiment.
- **error_msg** (*str, callable, or None*) – A message to be sent when an exception is raised during the experiment.
- **thread** (*bool*) – When True, subsequent messages will be posted as a thread of the original message. Default is True.
- **filenames** (*list of str or callable*) – A list of files that will be uploaded. These are string templates that can take values in the same way as `msg`, or a callable that returns a list of filenames.
- **upload_trigger** (*trigger or None*) – Used to upload files at certain events. If not specified, files will be uploaded in every call.
- **context** (*Any*) – Any arbitrary user object you will need when generating a message.
- **token** (*str*) – Slack bot token. If None, the environment variable `SLACK_BOT_TOKEN` will be used. Optional, default is None.

Methods

<code>__init__(channel[, msg, start_msg, end_msg, ...])</code>	
<code>default_end_msg(context)</code>	
<code>default_error_msg(exc, context)</code>	
<code>default_msg(context)</code>	
<code>default_start_msg(context)</code>	
<code>finalize(manager)</code>	Finalizes the extension.
<code>initialize(manager)</code>	Initializes up the manager state.
<code>load_state_dict(to_load)</code>	
<code>on_error(manager, exc, tb)</code>	Handles the error raised during training before finalization.
<code>state_dict()</code>	Serializes the extension state.

Attributes

<code>default_name</code>	Default name of the extension.
<code>is_async</code>	
<code>name</code>	
<code>needs_model_state</code>	
<code>priority</code>	
<code>trigger</code>	

`__init__(channel, msg=None, *, start_msg='{default}', end_msg='{default}', error_msg='{default}', thread=True, filenames=None, upload_trigger=None, context=None, token=None)`

Parameters

- **channel (str) –**
- **msg (Optional[Union[str, Callable[[ExtensionsManagerProtocol, Any], str]]]) –**
- **start_msg(Optional[Union[str, Callable[[ExtensionsManagerProtocol, Any], str]]) –**
- **end_msg(Optional[Union[str, Callable[[ExtensionsManagerProtocol, Any], str]]) –**
- **error_msg(Optional[Union[str, Callable[[ExtensionsManagerProtocol, Any, Exception], str]]) –**
- **thread (bool) –**

- **filenames** *(Optional[Union[Sequence[str], Callable[[ExtensionsManagerProtocol, Any], Sequence[str]]]])*
–
- **upload_trigger***(Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]])* –
- **context***(Optional[Any])* –
- **token***(Optional[str])* –

Return type

None

```
trigger: Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]] = (1, 'epoch')
```

pytorch_pfn_extras.training.extensions.slack.SlackWebhook

```
class pytorch_pfn_extras.training.extensions.slack.SlackWebhook(url, msg=None, *,  
                                         start_msg='{default}',  
                                         end_msg='{default}',  
                                         error_msg='{default}',  
                                         context=None)
```

Bases: `_SlackBase`

An extension to communicate with Slack using Incoming Webhook.

Example

```
>>> ppe.training.extensions.SlackWebhook(  
...     url="https://hooks.slack.com/services/Txxxxx.....",  
...     msg="Epoch #{manager.epoch}: loss = {val/loss}",  
...     end_msg="{default} \n <@username> Check out the result!",  
... )
```

This extension posts a message when:

- `start_msg`: The training has started
- `msg`: The extension is triggered, usually at the end of each epoch
- `end_msg`: The training has finished
- `error_msg`: An exception has raised during the training

These messages can be specified as a format string, a callable that returns a string, or None to disable posting on that event.

When using a format string, the following variables are available for use:

- `manager`: an ExtensionsManager object
- `default`: the default message string
- `context`: an arbitrary object passed to this extension
- `error`: an Exception object (for `error_msg` only)
- All reported values (`manager.observations`)

When using a callable, it should take (*ExtensionsManager, context*) or (*ExtensionsManager, Exception, context*) (for `error_msg`) and return a string.

Parameters

- **url** (*str*) – Incoming webhook URL to send messages.
- **msg** (*str, callable, or None*) – A message to be sent when triggered. It can be a string to be formatted using `.format` or a callable that returns a string.
- **start_msg** (*str, callable, or None*) – A message to be sent at the beginning of the experiment.
- **end_msg** (*str, callable, or None*) – A message to be sent at the completion of the experiment.
- **error_msg** (*str, callable, or None*) – A message to be sent when an exception is raised during the experiment.
- **context** (*object*) – Any arbitrary user object you will need when generating a message.

Methods

`__init__(url[, msg, start_msg, end_msg, ...])`

`default_end_msg(context)`

`default_error_msg(exc, context)`

`default_msg(context)`

`default_start_msg(context)`

`finalize(manager)` Finalizes the extension.

`initialize(manager)` Initializes up the manager state.

`load_state_dict(to_load)`

`on_error(manager, exc, tb)` Handles the error raised during training before finalization.

`state_dict()` Serializes the extension state.

Attributes

`default_name` Default name of the extension.

`is_async`

`name`

`needs_model_state`

`priority`

`trigger`

`__init__(url, msg=None, *, start_msg='{default}', end_msg='{default}', error_msg='{default}', context=None)`

Parameters

- `url (str) –`
- `msg (Optional[Union[str, Callable[[ExtensionsManagerProtocol, Any], str]]]) –`
- `start_msg(Optional[Union[str, Callable[[ExtensionsManagerProtocol, Any], str]]) –`
- `end_msg(Optional[Union[str, Callable[[ExtensionsManagerProtocol, Any], str]]) –`
- `error_msg(Optional[Union[str, Callable[[ExtensionsManagerProtocol, Any, Exception], str]]) –`
- `context (Optional[Any]) –`

Return type

None

pytorch_pfn_extras.training.extensions.snapshot_writers

Classes

<code>pytorch_pfn_extras.training.extensions.snapshot_writers.ProcessQueueWriter([...])</code>	Snapshot writer that uses process queue.
<code>pytorch_pfn_extras.training.extensions.snapshot_writers.ProcessWriter([...])</code>	Snapshot writer that uses a separate process.
<code>pytorch_pfn_extras.training.extensions.snapshot_writers.QueueWriter([...])</code>	Base class of queue snapshot writers.
<code>pytorch_pfn_extras.training.extensions.snapshot_writers.SimpleWriter([...])</code>	The most simple snapshot writer.
<code>pytorch_pfn_extras.training.extensions.snapshot_writers.StandardWriter([...])</code>	Base class of snapshot writers which use thread or process.
<code>pytorch_pfn_extras.training.extensions.snapshot_writers.TensorBoardWriter([...])</code>	Writer that sends statistics to TensorBoard.
<code>pytorch_pfn_extras.training.extensions.snapshot_writers.ThreadQueueWriter([...])</code>	Snapshot writer that uses a thread queue.
<code>pytorch_pfn_extras.training.extensions.snapshot_writers.ThreadWriter([...])</code>	Snapshot writer that uses a separate thread.
<code>pytorch_pfn_extras.training.extensions.snapshot_writers.Writer([...])</code>	Base class of snapshot writers.

[pytorch_pfn_extras.training.extensions.snapshot_writers.ProcessQueueWriter](#)

```
class pytorch_pfn_extras.training.extensions.snapshot_writers.ProcessQueueWriter(savefun=<function  
    save>,  
    fs=None,  
    out_dir='',  
    task=None)
```

Bases: [QueueWriter](#)[Process]

Snapshot writer that uses process queue.

This class creates a process and a queue by `multiprocessing` module. The process will be a consumer of this queue, and the main process will be a producer of this queue.

Note: Forking a new process from MPI process might be danger. Consider using [ThreadQueueWriter](#) instead of `ProcessQueueWriter` if you are using MPI.

See also:

- [pytorch_pfn_extras.training.extensions.snapshot\(\)](#)

Methods

`__init__`([savefun, fs, out_dir, task])

`consume`(q)

`create_consumer`(q)

`create_queue`()

`create_task`(savefun)

`finalize`() Finalizes the writer.
`initialize`(out_dir)

`save`(filename, out_dir, target, savefun, ...)

`__init__`(savefun=<function save>, fs=None, out_dir='', task=None)

Parameters

- `savefun` (`Callable[[...], None]`) –
- `fs` (`Optional[Any]`) –
- `out_dir` (`str`) –
- `task` (`Optional[Callable[[...], None]]`) –

Return type

None

create_consumer(*q*)

Parameters
q (`queue.Queue[_QueUnit]`) –

Return type
`Process`

create_queue()

Return type
`queue.Queue[_QueUnit]`

`pytorch_pfn_extras.training.extensions.snapshot_writers.ProcessWriter`

```
class pytorch_pfn_extras.training.extensions.snapshot_writers.ProcessWriter(savefun=<function
    save>, fs=None,
    out_dir='',
    **kwds)
```

Bases: `StandardWriter[Process]`

Snapshot writer that uses a separate process.

This class creates a new process that invokes the actual saving function.

Note: Forking a new process from a MPI process might be danger. Consider using `ThreadWriter` instead of `ProcessWriter` if you are using MPI.

See also:

- `pytorch_pfn_extras.training.extensions.snapshot()`

Methods

`__init__([savefun, fs, out_dir])`

<code>create_worker(filename, out_dir, target, *)</code>	Creates a worker for the snapshot.
--	------------------------------------

<code>finalize()</code>	Finalizes the writer.
-------------------------	-----------------------

<code>initialize(out_dir)</code>	
----------------------------------	--

<code>save(filename, out_dir, target, savefun, ...)</code>	
--	--

`__init__(savefun=<function save>, fs=None, out_dir='', **kwds)`

Parameters

- **savefun** (`Callable[..., None]`) –
- **fs** (`Optional[Any]`) –
- **out_dir** (`str`) –
- **kwds** (`Any`) –

Return type

None

create_worker(*filename*, *out_dir*, *target*, *, *savefun=None*, *append=False*, ***savefun_kwargs*)

Creates a worker for the snapshot.

This method creates a thread or a process to take a snapshot. The created worker must have `start()` and `join()` methods. If the worker has an `exitcode` attribute (e.g., `multiprocessing.Process`), the value will be tested.

Parameters

- **filename** (*str*) –
- **out_dir** (*str*) –
- **target** (*Union[Sequence[Any], Mapping[str, Any]]*) –
- **savefun** (*Optional[Callable[..., None]]*) –
- **append** (*bool*) –
- **savefun_kwargs** (*Any*) –

Return type

Process

[pytorch_pfn_extras.training.extensions.snapshot_writers.QueueWriter](#)

```
class pytorch_pfn_extras.training.extensions.snapshot_writers.QueueWriter(savefun=<function
    save>, fs=None,
    out_dir='',
    task=None)
```

Bases: `Writer`, `Generic[_Worker]`

Base class of queue snapshot writers.

This class is a base class of snapshot writers that use a queue. A Queue is created when this class is constructed, and every time when `__call__` is invoked, a snapshot task is put into the queue.

Parameters

- **savefun** – Callable object which is passed to the `create_task()` if the task is `None`. It takes three arguments: the output file path, the serialized dictionary object, and the optional keyword arguments.
- **fs** – FileSystem abstracting interface to implement all the operations. optional, defaults to `None`
- **out_dir** – str. Specifies the directory this writer will use. It takes precedence over the one specified in `__call__` optional, defaults to ''
- **task** – Callable object. Its `__call__` must have a same interface to `Writer.__call__`. This object is directly put into the queue.

See also:

- `pytorch_pfn_extras.training.extensions.snapshot()`

Methods

`__init__([savefun, fs, out_dir, task])`

`consume(q)`

`create_consumer(q)`

`create_queue()`

`create_task(savefun)`

`finalize()` Finalizes the writer.

`initialize(out_dir)`

`save(filename, out_dir, target, savefun, ...)`

`__call__(filename, out_dir, target, *, savefun=None, append=False)`

Does the actual writing to the file.

This method is invoked by a `Snapshot` object every time it takes a snapshot.

Parameters

- **filename** (`str`) – Name of the file into which the serialized target is saved. It is a concrete file name, i.e. not a pre-formatted template string.
- **out_dir** (`str`) – Output directory. Corresponds to :py:attr:`ExtensionsManager.out <pytorch_pfn_extras.training.ExtensionsManager.out>`.
- **target** (`dict`) – Serialized object which will be saved.
- **savefun** (`callable`) – A callable that accepts a two positional arguments (an object to be serialized, file path) like `torch.save`.
- **append** (`bool`) – Mode used to open the file. True to use the append mode, False to use the write mode (truncates the file if it already exists).

Return type

None

`__init__(savefun=<function save>, fs=None, out_dir='', task=None)`

Parameters

- **savefun** (`Callable[..., None]`) –
- **fs** (`Optional[Any]`) –
- **out_dir** (`str`) –
- **task** (`Optional[Callable[..., None]]`) –

Return type

None

`consume(q)`

Parameters
`q (queue.Queue[_QueUnit]) –`

Return type
None

create_consumer(`q`)

Parameters
`q (queue.Queue[_QueUnit]) –`

Return type
`_Worker`

create_queue()

Return type
`queue.Queue[_QueUnit]`

create_task(`savefun`)

Parameters
`savefun (Callable[..., None]) –`

Return type
`Callable[..., None]`

finalize()

Finalizes the writer.

Calling this method on already-finalized Writer does nothing.

Return type
None

[pytorch_pfn_extras.training.extensions.snapshot_writers.SimpleWriter](#)

```
class pytorch_pfn_extras.training.extensions.snapshot_writers.SimpleWriter(savefun=<function
    save>, fs=None,
    out_dir='',
    **kwds)
```

Bases: `Writer`

The most simple snapshot writer.

This class just passes the arguments to the actual saving function.

Parameters

- **savefun** (`Callable[..., None]`) – Callable object. It takes three arguments: the output file path, the serialized dictionary object, and the optional keyword arguments.
- **fs** (`Any`) – FileSystem abstracting interface to implement all the operations. optional, defaults to `None`
- **out_dir** (`str`) – str. Specifies the directory this writer will use. It takes precedence over the one specified in `__call__` optional, defaults to ''
- **kwds** (`Any`) – Keyword arguments for the `savefun`.

See also:

- `pytorch_pfn_extras.training.extensions.snapshot()`

Methods

`__init__([savefun, fs, out_dir])`

<code>finalize()</code>	Finalizes the writer.
<code>initialize(out_dir)</code>	

`save(filename, out_dir, target, savefun, ...)`

`__call__(filename, out_dir, target, *, savefun=None, append=False)`

Does the actual writing to the file.

This method is invoked by a `Snapshot` object every time it takes a snapshot.

Parameters

- **filename** (*str*) – Name of the file into which the serialized target is saved. It is a concrete file name, i.e. not a pre-formatted template string.
- **out_dir** (*str*) – Output directory. Corresponds to :py:attr:`ExtensionsManager.out` <pytorch_pfn_extras.training.ExtensionsManager.out>`.
- **target** (*dict*) – Serialized object which will be saved.
- **savefun** (*callable*) – A callable that accepts two positional arguments (an object to be serialized, file path) like `torch.save`.
- **append** (*bool*) – Mode used to open the file. True to use the append mode, False to use the write mode (truncates the file if it already exists).

Return type

None

`__init__(savefun=<function save>, fs=None, out_dir='', **kwds)`

Parameters

- **savefun** (*Callable[[...], None]*) –
- **fs** (*Optional[Any]*) –
- **out_dir** (*str*) –
- **kwds** (*Any*) –

Return type

None

[pytorch_pfn_extras.training.extensions.snapshot_writers.StandardWriter](#)

```
class pytorch_pfn_extras.training.extensions.snapshot_writers.StandardWriter(savefun=<function  
    save>,  
    fs=None,  
    out_dir='',  
    **kwds)
```

Bases: [Writer](#), [Generic\[_Worker\]](#)

Base class of snapshot writers which use thread or process.

This class creates a new thread or a process every time when `__call__` is invoked.

Parameters

- **savefun** – Callable object. It takes three arguments: the output file path, the serialized dictionary object, and the optional keyword arguments.
- **fs** – FileSystem abstracting interface to implement all the operations. optional, defaults to None
- **out_dir** – str. Specifies the directory this writer will use. It takes precedence over the one specified in `__call__` optional, defaults to ''
- **kwds** – Keyword arguments for the savefun.

See also:

- [pytorch_pfn_extras.training.extensions.snapshot\(\)](#)

Methods

`__init__([savefun, fs, out_dir])`

`create_worker(filename, out_dir, target, *)` Creates a worker for the snapshot.

`finalize()` Finalizes the writer.

`initialize(out_dir)`

`save(filename, out_dir, target, savefun, ...)`

`__call__(filename, out_dir, target, *, savefun=None, append=False)`

Does the actual writing to the file.

This method is invoked by a `Snapshot` object every time it takes a snapshot.

Parameters

- **filename** (*str*) – Name of the file into which the serialized target is saved. It is a concrete file name, i.e. not a pre-formatted template string.
- **out_dir** (*str*) – Output directory. Corresponds to :py:attr:`ExtensionsManager.out` <pytorch_pfn_extras.training.ExtensionsManager.out>`.
- **target** (*dict*) – Serialized object which will be saved.
- **savefun** (*callable*) – A callable that accepts a two positional arguments (an object to be serialized, file path) like `torch.save`.

- **append** (*bool*) – Mode used to open the file. True to use the append mode, False to use the write mode (truncates the file if it already exists).

Return type

None

`__init__(savefun=<function save>, fs=None, out_dir='', **kwds)`**Parameters**

- **savefun** (*Callable*[...], *None*] –
- **fs** (*Optional[Any]*) –
- **out_dir** (*str*) –
- **kwds** (*Any*) –

Return type

None

`create_worker(filename, out_dir, target, *, savefun=None, append=False, **savefun_kwargs)`

Creates a worker for the snapshot.

This method creates a thread or a process to take a snapshot. The created worker must have `start()` and `join()` methods. If the worker has an `exitcode` attribute (e.g., `multiprocessing.Process`), the value will be tested.

Parameters

- **filename** (*str*) –
- **out_dir** (*str*) –
- **target** (*Union[Sequence[Any], Mapping[str, Any]]*) –
- **savefun** (*Optional[Callable[[...], None]]*) –
- **append** (*bool*) –
- **savefun_kwargs** (*Any*) –

Return type*_Worker*`finalize()`

Finalizes the writer.

Calling this method on already-finalized Writer does nothing.

Return type

None

pytorch_pfn_extras.training.extensions.snapshot_writers.TensorBoardWriter

```
class pytorch_pfn_extras.training.extensions.snapshot_writers.TensorBoardWriter(savefun=None,
                                                                           fs=None,
                                                                           out_dir='',
                                                                           stats=None,
                                                                           **kwds)
```

Bases: `object`

Writer that sends statistics to TensorBoard.

This class contains a `torch.utils.tensorboard.SummaryWriter` object that is used to send the collected statistics to TensorBoard. A list of stats can be specified to report only the desired ones.

Parameters

- **savefun** (*Optional[Callable[[], None]]*) – Ignored.
- **fs** (*Any*) – Ignored.
- **out_dir** (*str*) – Passed as `log_dir` argument to `SummaryWriter`.
- **stats** (*list*) – List of statistic keys.
- **kwds** (*Any*) – Passed as an additional arguments to `SummaryWriter`.

Methods

`__init__([savefun, fs, out_dir, stats])`

`finalize()`

`__call__(filename, out_dir, target, *, savefun=None, append=False)`

Sends the statistics to the TensorBoard.

Parameters

- **filename** (*str*) – Ignored.
- **out_dir** (*str*) – Ignored.
- **target** (*dict or list*) – The statistics of the iteration. If given as a list, only the last element (assumed to be a dict containing the latest iteration statistics) is reported.
- **savefun** (*Optional[Callable[[], None]]*) – Ignored.
- **append** (*bool*) – Ignored.

Return type

None

`__init__(savefun=None, fs=None, out_dir='', stats=None, **kwds)`

Parameters

- **savefun** (*Optional[Callable[[], None]]*) –
- **fs** (*Optional[Any]*) –
- **out_dir** (*str*) –
- **stats** (*Optional[KeysView[str]]*) –
- **kwds** (*Any*) –

Return type

None

`finalize()`

Return type

None

pytorch_pfn_extras.training.extensions.snapshot_writers.ThreadQueueWriter

```
class pytorch_pfn_extras.training.extensions.snapshot_writers.ThreadQueueWriter(savefun=<function
    save>,
    fs=None,
    out_dir='',
    task=None)
```

Bases: `QueueWriter`[`Thread`]

Snapshot writer that uses a thread queue.

This class creates a thread and a queue by `threading` and `queue` modules respectively. The thread will be a consumer of the queue, and the main thread will be a producer of the queue.

See also:

- `pytorch_pfn_extras.training.extensions.snapshot()`

Methods

`__init__`([`savefun`, `fs`, `out_dir`, `task`])

`consume(q)`

`create_consumer(q)`

`create_queue()`

`create_task(savefun)`

`finalize()` Finalizes the writer.

`initialize(out_dir)`

`save(filename, out_dir, target, savefun, ...)`

`__init__`(`savefun=<function save>`, `fs=None`, `out_dir=''`, `task=None`)

Parameters

- `savefun` (`Callable[[...], None]`) –
- `fs` (`Optional[Any]`) –
- `out_dir` (`str`) –
- `task` (`Optional[Callable[[...], None]]`) –

Return type

`None`

`create_consumer(q)`

Parameters

- `q` (`queue.Queue[_QueUnit]`) –

Return type

Thread

create_queue()

Return type

`queue.Queue[_QueUnit]`

[pytorch_pfn_extras.training.extensions.snapshot_writers.ThreadWriter](#)

```
class pytorch_pfn_extras.training.extensions.snapshot_writers.ThreadWriter(savefun=<function
    save>, fs=None,
    out_dir='',
    **kwds)
```

Bases: *StandardWriter*[`Thread`]

Snapshot writer that uses a separate thread.

This class creates a new thread that invokes the actual saving function.

See also:

- [`pytorch_pfn_extras.training.extensions.snapshot\(\)`](#)

Methods

`__init__([savefun, fs, out_dir])`

`create_worker(filename, out_dir, target, *)` Creates a worker for the snapshot.

`finalize()` Finalizes the writer.

`initialize(out_dir)`

`save(filename, out_dir, target, savefun, ...)`

`__init__(savefun=<function save>, fs=None, out_dir='', **kwds)`

Parameters

- **savefun** (`Callable[[...], None]`) –
- **fs** (`Optional[Any]`) –
- **out_dir** (`str`) –
- **kwds** (`Any`) –

Return type

`None`

create_worker(`filename, out_dir, target, *, savefun=None, append=False, **savefun_kwargs`)

Creates a worker for the snapshot.

This method creates a thread or a process to take a snapshot. The created worker must have `start()` and `join()` methods. If the worker has an `exitcode` attribute (e.g., `multiprocessing.Process`), the value will be tested.

Parameters

- **filename** (*str*) –
- **out_dir** (*str*) –
- **target** (*Union[Sequence[Any], Mapping[str, Any]]*) –
- **savefun** (*Optional[Callable[..., None]]*) –
- **append** (*bool*) –
- **savefun_kwargs** (*Any*) –

Return type*Thread***pytorch_pfn_extras.training.extensions.snapshot_writers.Writer****class** pytorch_pfn_extras.training.extensions.snapshot_writers.**Writer**(*fs=None, out_dir=''*)Bases: *object*

Base class of snapshot writers.

Snapshot invokes `__call__` of this class every time when taking a snapshot. This class determines how the actual saving function will be invoked.

Note: This extension first writes the serialized object to a temporary file and then rename it to the target file name. Thus, if the program stops right before the renaming, the temporary file might be left in the output directory.

See also:

- [pytorch_pfn_extras.training.extensions.snapshot\(\)](#)

Methods

`__init__([fs, out_dir])`

`finalize()` Finalizes the writer.`initialize(out_dir)`

`save(filename, out_dir, target, savefun, ...)`

Parameters

- **fs** (*Any*) –
- **out_dir** (*str*) –

`__call__(filename, out_dir, target, *, savefun=None, append=False)`

Does the actual writing to the file.

This method is invoked by a Snapshot object every time it takes a snapshot.

Parameters

- **filename** (*str*) – Name of the file into which the serialized target is saved. It is a concrete file name, i.e. not a pre-formatted template string.
- **out_dir** (*str*) – Output directory. Corresponds to :py:attr:`ExtensionsManager.out` <pytorch_pfn_extras.training.ExtensionsManager.out>`.
- **target** (*dict*) – Serialized object which will be saved.
- **savefun** (*callable*) – A callable that accepts a two positional arguments (an object to be serialized, file path) like *torch.save*.
- **append** (*bool*) – Mode used to open the file. True to use the append mode, False to use the write mode (truncates the file if it already exists).

Return type

None

__init__(fs=None, out_dir='')

Parameters

- **fs** (*Optional[Any]*) –
- **out_dir** (*str*) –

Return type

None

finalize()

Finalizes the writer.

Calling this method on already-finalized Writer does nothing.

Return type

None

initialize(out_dir)

Parameters

out_dir (*str*) –

Return type

None

save(filename, out_dir, target, savefun, append, **savefun_kwargs)

Parameters

- **filename** (*str*) –
- **out_dir** (*str*) –
- **target** (*Union[Sequence[Any], Mapping[str, Any]]*) –
- **savefun** (*Callable[..., None]*) –
- **append** (*bool*) –
- **savefun_kwargs** (*Any*) –

Return type

None

pytorch_pfn_extras.training.extensions.util**Classes**

```
pytorch_pfn_extras.training.extensions.  
util.ExtensionsManagerProtocol(...)  
pytorch_pfn_extras.training.extensions.  
util.ProgressBar([out])  
pytorch_pfn_extras.training.extensions.    Typed version of the return of open() in text mode.  
util.TextIO(...)
```

pytorch_pfn_extras.training.extensions.util.ExtensionsManagerProtocol

```
class pytorch_pfn_extras.training.extensions.util.ExtensionsManagerProtocol(*args,  
                           **kwargs)
```

Bases: Protocol

Methods

```
__init__(*args, **kwargs)
```

```
get_extension(name)
```

Attributes

```
elapsed_time
epoch
epoch_detail
is_before_training
iteration
models
observation
optimizers
out
raw_models
reporter
stop_trigger
writer
```

```
__init__(*args, **kwargs)
property elapsed_time: float
property epoch: int
property epoch_detail: float
get_extension(name)

    Parameters
        name (str) ->

    Return type
        Extension

    property is_before_training: bool
    property iteration: int
    property models: Mapping[str, Module]
    property observation: reporting.Observation
    property optimizers: Mapping[str, Optimizer]
```

```

property out: str
property raw_models: Mapping[str, Module]
property reporter: reporting.Reporter
property stop_trigger: bool
property writer: Optional[writing.Writer]

```

`pytorch_pfn_extras.training.extensions.util.ProgressBar`

```

class pytorch_pfn_extras.training.extensions.util.ProgressBar(out=None)
Bases: object

```

Methods

`__init__([out])`

`close()`

`erase_console()`

`flush()`

`get_lines()`

`move_cursor_up(n)`

`update([manager])`

`update_speed(iteration, epoch_detail)`

Parameters

`out (Optional[TextIO]) –`

`__init__([out=None])`

Parameters

`out (Optional[TextIO]) –`

Return type

None

`close()`

Return type

None

`erase_console()`

Return type

None

`flush()`

Return type

None

`get_lines()`

Return type

Sequence[str]

`move_cursor_up(n)`

Parameters

`n (int) –`

Return type

None

`update(manager=None)`

Parameters

`manager (Optional[ExtensionsManagerProtocol]) –`

Return type

None

`update_speed(iteration, epoch_detail)`

Parameters

- `iteration (int) –`

- `epoch_detail (float) –`

Return type

Tuple[float, float]

`pytorch_pfn_extras.training.extensions.util.TextIO`

`class pytorch_pfn_extras.training.extensions.util.TextIO(*args, **kwds)`

Bases: `IO[str]`

Typed version of the return of open() in text mode.

Methods

`__init__()`

`close()`

`fileno()`

`flush()`

`isatty()`

`read([n])`

`readable()`

`readline([limit])`

`readlines([hint])`

`seek(offset[, whence])`

`seekable()`

`tell()`

`truncate([size])`

`writable()`

`write(s)`

`writelines(lines)`

Attributes

`buffer`

`closed`

`encoding`

`errors`

`line_buffering`

`mode`

`name`

`newlines`

`abstract property buffer: BinaryIO`

`abstract property encoding: str`

`abstract property errors: Optional[str]`

`abstract property line_buffering: bool`

`abstract property newlines: Any`

[pytorch_pfn_extras.training.extensions.value_observation](#)

Functions

`pytorch_pfn_extras.training.extensions.value_observation.observe_lr(...)` Returns an extension to record the learning rate.

`pytorch_pfn_extras.training.extensions.value_observation.observe_value(...)` Returns an extension to continuously record a value.

[pytorch_pfn_extras.training.extensions.value_observation.observe_lr](#)

`pytorch_pfn_extras.training.extensions.value_observation.observe_lr(optimizer, param_group=0, observation_key='lr')`

Returns an extension to record the learning rate.

Parameters

- **optimizer** (*Optimizer*) – Optimizer whose learning rate is recorded.
- **param_group** (*int*) – Param group of the optimizer to observe
- **observation_key** (*str*) – Key of observation to record.

Returns

The extension function.

Return type

Any

This extension is triggered each epoch by default. To change this, use the `trigger` argument with the `ExtensionsManager.extend()` method.

`pytorch_pfn_extras.training.extensions.value_observation.observe_value`

```
pytorch_pfn_extras.training.extensions.value_observation.observe_value(observation_key,  
target_func)
```

Returns an extension to continuously record a value.

Parameters

- **`observation_key` (`str`)** – Key of observation to record.
- **`target_func` (`function`)** – Function that returns the value to record. It must take one argument: `:class:~pytorch_pfn_extras.training.ExtensionsManager` object.

Returns

The extension function.

Return type

Callable[[ExtensionsManagerProtocol], None]

This extension is triggered each epoch by default. To change this, use the `trigger` argument with the `ExtensionsManager.extend()` method.

Classes

```
pytorch_pfn_extras.training.  
extensions.value_observation.  
ExtensionsManagerProtocol(...)
```

`pytorch_pfn_extras.training.extensions.value_observation.ExtensionsManagerProtocol`

```
class pytorch_pfn_extras.training.extensions.value_observation.ExtensionsManagerProtocol(*args,  
**kwargs)
```

Bases: `Protocol`

Methods

```
__init__(*args, **kwargs)
```

```
get_extension(name)
```

Attributes

```
elapsed_time
epoch
epoch_detail
is_before_training
iteration
models
observation
optimizers
out
raw_models
reporter
stop_trigger
writer
```

```
__init__(*args, **kwargs)
property elapsed_time: float
property epoch: int
property epoch_detail: float
get_extension(name)

    Parameters
        name (str) ->

    Return type
        Extension

    property is_before_training: bool
    property iteration: int
    property models: Mapping[str, Module]
    property observation: reporting.Observation
    property optimizers: Mapping[str, Optimizer]
```

```
property out: str
property raw_models: Mapping[str, Module]
property reporter: reporting.Reporter
property stop_trigger: bool
property writer: Optional[writing.Writer]
```

pytorch_pfn_extras.training.extensions.variable_statistics_plot

Functions

```
pytorch_pfn_extras.training.
extensions.variable_statistics_plot.
matplotlib_savefun(...)
pytorch_pfn_extras.training.extensions.
variable_statistics_plot.percentile(a, ...)
```

pytorch_pfn_extras.training.extensions.variable_statistics_plot.matplotlib_savefun

pytorch_pfn_extras.training.extensions.variable_statistics_plot.**matplotlib_savefun**(*target*,
 file_o)

Parameters

- **target** (*Tuple[Any, Any]*) –
- **file_o** (*Any*) –

Return type

None

pytorch_pfn_extras.training.extensions.variable_statistics_plot.percentile

pytorch_pfn_extras.training.extensions.variable_statistics_plot.**percentile**(*a*, *q*, *axis*)

Parameters

- **a** (*Tensor*) –
- **q** (*Union[float, Tuple[float, ...]]*) –
- **axis** (*int*) –

Return type

Any

Classes

<code>pytorch_pfn_extras.training.extensions.variable_statistics_plot.ExtensionsManagerProtocol(...)</code>	
<code>pytorch_pfn_extras.training.extensions.variable_statistics_plot.Reservoir(...)</code>	Reservoir sample with a fixed sized buffer.
<code>pytorch_pfn_extras.training.extensions.variable_statistics_plot.Statistician(...)</code>	Helper to compute basic NumPy-like statistics.
<code>pytorch_pfn_extras.training.extensions.variable_statistics_plot.VariableStatisticsPlot(targets)</code>	An extension to plot statistics for Tensors.

`pytorch_pfn_extras.training.extensions.variable_statistics_plot.ExtensionsManagerProtocol`

```
class pytorch_pfn_extras.training.extensions.variable_statistics_plot.ExtensionsManagerProtocol(*args,  
                                         **kwargs)
```

Bases: Protocol

Methods

```
__init__(*args, **kwargs)
```

```
get_extension(name)
```

Attributes

elapsed_time

epoch

epoch_detail

is_before_training

iteration

models

observation

optimizers

out

raw_models

reporter

stop_trigger

writer

`__init__(*args, **kwargs)`

`property elapsed_time: float`

`property epoch: int`

`property epoch_detail: float`

`get_extension(name)`

Parameters

`name (str) –`

Return type

Extension

`property is_before_training: bool`

`property iteration: int`

`property models: Mapping[str, Module]`

`property observation: reporting.Observation`

`property optimizers: Mapping[str, Optimizer]`

```
property out: str
property raw_models: Mapping[str, Module]
property reporter: reporting.Reporter
property stop_trigger: bool
property writer: Optional[writing.Writer]
```

`pytorch_pfn_extras.training.extensions.variable_statistics_plot.Reservoir`

```
class pytorch_pfn_extras.training.extensions.variable_statistics_plot.Reservoir(size,
                                data_shape,
                                dtype=<class
                                'numpy.float32'>)
```

Bases: object

Reservoir sample with a fixed sized buffer.

Methods

```
__init__(size, data_shape[, dtype])
```

```
add(x[, idx])
```

```
get_data()
```

Parameters

- **size** (`int`) –
- **data_shape** (`Tuple[int, ...]`) –
- **dtype** (`Any`) –

```
__init__(size, data_shape, dtype=<class 'numpy.float32'>)
```

Parameters

- **size** (`int`) –
- **data_shape** (`Tuple[int, ...]`) –
- **dtype** (`Any`) –

Return type

None

```
add(x, idx=None)
```

Parameters

- **x** (`Any`) –
- **idx** (`Optional[Any]`) –

Return type

None

`get_data()`**Return type***Tuple[Any, Any]***pytorch_pfn_extras.training.extensions.variable_statistics_plot.Statistician**

```
class pytorch_pfn_extras.training.extensions.variable_statistics_plot.Statistician(collect_mean,
                                    collect_std,
                                    percentile_sigmas)
```

Bases: `object`

Helper to compute basic NumPy-like statistics.

Methods

`__init__(collect_mean, collect_std, ...)`

`collect(x, axis)`

Parameters

- `collect_mean (bool) –`
- `collect_std (bool) –`
- `percentile_sigmas (Union[float, Tuple[float, ...]]) –`

`__call__(x, axis=0, dtype=None)`

Call self as a function.

Parameters

- `x (Any) –`
- `axis (Any) –`
- `dtype (Optional[Any]) –`

Return type*Dict[str, Any]*`__init__(collect_mean, collect_std, percentile_sigmas)`**Parameters**

- `collect_mean (bool) –`
- `collect_std (bool) –`
- `percentile_sigmas (Union[float, Tuple[float, ...]]) –`

Return type

None

collect(*x*, *axis*)

Parameters

- **x** (*Any*) –
- **axis** (*int*) –

Return type

Dict[str, *Any*]

pytorch_pfn_extras.training.extensions.variable_statistics_plot.VariableStatisticsPlot

```
class pytorch_pfn_extras.training.extensions.variable_statistics_plot.VariableStatisticsPlot(targets,
                                         max_sample_size=1000000,
                                         reservoir_size=1000000,
                                         port_data=True,
                                         report_percentiles=[0.13, 0.28, 0.5, 0.84, 0.97, 0.99, 1.0],
                                         port_grad=True,
                                         plot_mean=True,
                                         plot_std=True,
                                         percentile_sigma=0.13,
                                         trigger=(1, 'epoch'),
                                         file_name='statistics',
                                         figsize=None,
                                         marker=None,
                                         grid=True)
```

Bases: *Extension*

An extension to plot statistics for Tensors.

This extension collects statistics for a single `torch.Tensor`, a list of `torch.Tensors` or similarly a single or a list of `torch.nn.Modules` containing one or more `torch.Tensors`. In case multiple `torch.Tensors` are found, the means are computed. The collected statistics are plotted and saved as an image in the directory specified by the Manager.

Statistics include mean, standard deviation and percentiles.

This extension uses reservoir sampling to preserve memory, using a fixed size running sample. This means that collected items in the sample are discarded uniformly at random when the number of items becomes larger than the maximum sample size, but each item is expected to occur in the sample with equal probability.

:param targets (torch.Tensor: or list of either): Parameters for which statistics are collected. :param torch.nn.Module: or list of either): Parameters for which statistics are collected. :param max_sample_size: Maximum number of running samples. :type max_sample_size: int :param report_data: If True, data (e.g. weights) statistics are plotted. If False, they are neither computed nor plotted.

False, they are neither computed nor plotted.

Parameters

- **report_grad** (bool) – If True, gradient statistics are plotted. If False, they are neither computed nor plotted.
- **plot_mean** (bool) – If True, means are plotted. If False, they are neither computed nor plotted.
- **plot_std** (bool) – If True, standard deviations are plotted. If False, they are neither computed nor plotted.
- **percentile_sigmas** (float or tuple of floats) – Percentiles to plot in the range [0, 100].
- **trigger** (Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]]) – Trigger that decides when to save the plots as an image. This is distinct from the trigger of this extension itself. If it is a tuple in the form <int>, 'epoch' or <int>, 'iteration', it is passed to IntervalTrigger.
- **filename** (str) – Name of the output image file under the output directory. For historical reasons file_name is also accepted as an alias of this argument.
- **figsize** (tuple of int) – Matplotlib figsize argument that specifies the size of the output image.
- **marker** (str) – Matplotlib marker argument that specified the marker style of the plots.
- **grid** (bool) – Matplotlib grid argument that specifies whether grids are rendered in the plots or not.
- **writer** (writer object, optional) – must be callable. object to dump the log to. If specified, it needs to have a correct *savefun* defined. The writer can override the save location in the [pytorch_pfn_extras.training.ExtensionsManager](#) object
- **targets** (Any) –
- **max_sample_size** (int) –
- **report_data** (bool) –
- **kwargs** (Any) –

Methods

<code>__init__(targets[, max_sample_size, ...])</code>	
<code>available()</code>	
<code>finalize(manager)</code>	Finalizes the extension.
<code>initialize(manager)</code>	Initializes up the manager state.
<code>load_state_dict(to_load)</code>	
<code>on_error(manager, exc, tb)</code>	Handles the error raised during training before finalization.
<code>save_plot_using_module(plt, manager)</code>	
<code>state_dict()</code>	Serializes the extension state.

Attributes

<code>default_name</code>	Default name of the extension.
<code>is_async</code>	
<code>name</code>	
<code>needs_model_state</code>	
<code>priority</code>	
<code>trigger</code>	

`__call__(manager)`

Invokes the extension.

Implementations should override this operator. This method is called at iterations which the corresponding trigger accepts.

Parameters

`manager` (`ExtensionsManager`) – Manager object to call this operator.

Return type

`None`

`__init__(targets, max_sample_size=1000, report_data=True, report_grad=True, plot_mean=True, plot_std=True, percentile_sigmas=(0, 0.13, 2.28, 15.87, 50, 84.13, 97.72, 99.87, 100), trigger=(1, 'epoch'), filename=None, figsize=None, marker=None, grid=True, **kwargs)`

Parameters

- `targets` (`Any`) –
- `max_sample_size` (`int`) –
- `report_data` (`bool`) –
- `report_grad` (`bool`) –

- **plot_mean** (bool) –
- **plot_std** (bool) –
- **percentile_sigmas** (*Union[float, Tuple[float, ...]]*) –
- **trigger** (*Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol], bool], Tuple[float, str]]]*) –
- **filename** (*Optional[str]*) –
- **figsize** (*Optional[Tuple[int, ...]]*) –
- **marker** (*Optional[str]*) –
- **grid** (bool) –
- **kwargs** (Any) –

static available()

Return type
bool

finalize(*manager*)
Finalizes the extension.

This method is called at the end of the training loop.

Parameters
manager (*ExtensionsManagerProtocol*) –

Return type
None

save_plot_using_module(*plt, manager*)

Parameters

- **plt** (Any) –
- **manager** (*ExtensionsManagerProtocol*) –

Return type
None

pytorch_pfn_extras.training.manager

Functions

pytorch_pfn_extras.training.manager.
default_transform_model(n, x)

pytorch_pfn_extras.training.manager.
record(tag)

Classes

<code>pytorch_pfn_extras.training.manager.ExtensionsManager(...)</code>	Manages the extensions and the current status.
<code>pytorch_pfn_extras.training.manager.IgniteExtensionsManager(...)</code>	Manages extensions and the current status in Ignite training loop.
<code>pytorch_pfn_extras.training.manager.StateObjectProtocol(...)</code>	

pytorch_pfn_extras.training.metrics

Classes

<code>pytorch_pfn_extras.training.metrics.AccuracyMetric(...)</code>	A metric for an evaluator to report accuracy.
--	---

pytorch_pfn_extras.training.metrics.AccuracyMetric

`class pytorch_pfn_extras.training.metrics.AccuracyMetric(label_key, output_key)`

Bases: `object`

A metric for an evaluator to report accuracy.

Parameters

- **label_key** (`str`) – The key name of label.
- **output_key** (`str`) – The key name of prediction.

Methods

`__init__(label_key, output_key)`

`__call__(batch, out)`

Call self as a function.

Parameters

- **batch** (`Dict[str, Tensor]`) –
- **out** (`Dict[str, Tensor]`) –

Return type

`Dict[str, Any]`

`__init__(label_key, output_key)`

Parameters

- **label_key** (`str`) –
- **output_key** (`str`) –

Return type

None

pytorch_pfn_extras.training.trigger**Functions**

<code>pytorch_pfn_extras.training.trigger. get_trigger(trigger)</code>	Gets a trigger object.
--	------------------------

pytorch_pfn_extras.training.trigger.get_trigger`pytorch_pfn_extras.training.trigger.get_trigger(trigger)`

Gets a trigger object.

Trigger object is a callable that accepts a `ExtensionsManager` object as an argument and returns a boolean value. When it returns True, various kinds of events can occur depending on the context in which the trigger is used. For example, if the trigger is passed to the `extend()` method of a manager, then the registered extension is invoked only when the trigger returns True.

This function returns a trigger object based on the argument. If `trigger` is already a callable, it just returns the trigger. If `trigger` is `None`, it returns a trigger that never fires. Otherwise, it creates a `IntervalTrigger`.

Parameters

`trigger` (`Optional[Union[Trigger, Callable[[ExtensionsManagerProtocol],
bool], Tuple[float, str]]]`) – Trigger object. It can be either an already built trigger object (i.e., a callable object that accepts a manager object and returns a bool value), or a tuple. In latter case, the tuple is passed to `IntervalTrigger`.

Returns`trigger` if it is a callable, otherwise a `IntervalTrigger` object made from `trigger`.**Return type**`Trigger`**Classes**

<code>pytorch_pfn_extras.training.trigger. IntervalTrigger(...)</code>	Trigger based on a fixed interval.
<code>pytorch_pfn_extras.training.trigger. Trigger()</code>	Base class for triggers.

[pytorch_pfn_extras.training.trigger.IntervalTrigger](#)

```
class pytorch_pfn_extras.training.trigger.IntervalTrigger(period, unit)
```

Bases: [Trigger](#)

Trigger based on a fixed interval.

This trigger accepts iterations divided by a given interval. There are two ways to specify the interval: per iterations and epochs. *Iteration* means the number of updates, while *epoch* means the number of sweeps over the training dataset. Fractional values are allowed if the interval is a number of epochs; the trigger uses the *iteration* and *epoch_detail* attributes defined by the manager.

For the description of triggers see `get_trigger()`.

Parameters

- **period** (*int or float*) – Length of the interval. Must be an integer if unit is '*iteration*'.
- **unit** (*str*) – Unit of the length specified by period. It must be either '*iteration*' or '*epoch*'.

Methods

```
__init__(period, unit)
```

```
get_training_length()
```

```
load_state_dict(state)
```

<code>may_fire(iteration, epoch_length)</code>	Flags if the trigger may fire at the current iteration
<code>state_dict()</code>	

```
__call__(manager)
```

Decides whether the extension should be called on this iteration.

Parameters

manager ([ExtensionsManager](#)) – Manager object that this trigger is associated with. The iteration related information in this manager is used to determine if the trigger should fire.

Returns

True if the corresponding extension should be invoked in this iteration.

Return type

bool

```
__init__(period, unit)
```

Parameters

- **period** (*float*) –
- **unit** (*UnitLiteral*) –

`get_training_length()`

Return type

Tuple[float, str]

`may_fire(iteration, epoch_length)`

Flags if the trigger may fire at the current iteration

This must not alter the trigger state

Parameters

- `iteration (int)` –
- `epoch_length (int)` –

Return type

bool

[pytorch_pfn_extras.training.trigger.Trigger](#)

`class pytorch_pfn_extras.training.trigger.Trigger`

Bases: `object`

Base class for triggers.

Methods

`__init__()`

`load_state_dict(state)`

`may_fire(iteration, epoch_len)`

Flags if the trigger may fire at the current iteration

`state_dict()`

`__call__(manager)`

Call self as a function.

Parameters

`manager (ExtensionsManagerProtocol)` –

Return type

bool

`load_state_dict(state)`

Parameters

`state (Dict[str, Any])` –

Return type

None

`may_fire(iteration, epoch_len)`

Flags if the trigger may fire at the current iteration

This must not alter the trigger state

Parameters

- **iteration** (*int*) –
- **epoch_len** (*int*) –

Return type

bool

state_dict()

Return type

Dict[str, Any]

pytorch_pfn_extras.training.triggers

Classes

<code>pytorch_pfn_extras.training.triggers. BestValueTrigger(...)</code>	Trigger invoked when specific value becomes best.
<code>pytorch_pfn_extras.training.triggers. EarlyStoppingTrigger(self)</code>	Trigger for Early Stopping
<code>pytorch_pfn_extras.training.triggers. IntervalTrigger(...)</code>	Trigger based on a fixed interval.
<code>pytorch_pfn_extras.training.triggers. ManualScheduleTrigger(...)</code>	Trigger invoked at specified point(s) of iterations or epochs.
<code>pytorch_pfn_extras.training.triggers. MaxValueTrigger(key)</code>	Trigger invoked when specific value becomes maximum.
<code>pytorch_pfn_extras.training.triggers. MinValueTrigger(key)</code>	Trigger invoked when specific value becomes minimum.
<code>pytorch_pfn_extras.training.triggers. OnceTrigger([...])</code>	Trigger based on the starting point of the iteration.
<code>pytorch_pfn_extras.training.triggers. TimeTrigger(period)</code>	Trigger based on a fixed time interval.

pytorch_pfn_extras.training.triggers.BestValueTrigger

`class pytorch_pfn_extras.training.triggers.BestValueTrigger(key, compare, trigger=(1, 'epoch'))`

Bases: `Trigger`

Trigger invoked when specific value becomes best.

Parameters

- **key** (*str*) – Key of value.
- **compare** (*callable*) – Compare function which takes current best value and new value and returns whether new value is better than current best.
- **trigger** (*TriggerLike*) – Trigger that decides the comparison interval between current best value and new value. This must be a tuple in the form of `<int>`, `'epoch'` or `<int>, 'iteration'` which is passed to `IntervalTrigger`.

Methods

`__init__(key, compare[, trigger])`

`load_state_dict(to_load)`

<code>may_fire(iteration, epoch_length)</code>	Flags if the trigger may fire at the current iteration
<code>state_dict()</code>	

`__call__(manager)`

Decides whether the extension should be called on this iteration.

Parameters

- `manager` (`ExtensionsManager`) – Manager object that this trigger is associated with.
The observation of this manager is used to determine if the trigger should fire.

Returns

True if the corresponding extension should be invoked in this iteration.

Return type

bool

`__init__(key, compare, trigger=(1, 'epoch'))`

Parameters

- `key` (`str`) –
- `compare` (`Callable[[float, float], bool]`) –
- `trigger` (`TriggerLike`) –

Return type

None

`load_state_dict(to_load)`

Parameters

`to_load` (`Dict[str, Any]`) –

Return type

None

`may_fire(iteration, epoch_length)`

Flags if the trigger may fire at the current iteration

This must not alter the trigger state

Parameters

- `iteration` (`int`) –
- `epoch_length` (`int`) –

Return type

bool

`state_dict()`

Return type

`Dict[str, Any]`

[pytorch_pfn_extras.training.triggers.EarlyStoppingTrigger](#)

```
class pytorch_pfn_extras.training.triggers.EarlyStoppingTrigger(self, check_trigger=(1, 'epoch'),
                                                               monitor='main/loss',
                                                               patience=3, mode='auto',
                                                               verbose=False,
                                                               max_trigger=(100, 'epoch'))
```

Bases: [Trigger](#)

Trigger for Early Stopping

This trigger works as follows. Within each *check interval* defined by the `check_trigger` argument, it monitors and accumulates the reported value at each iteration. At the end of each interval, it computes the mean of the accumulated values and compares it to the previous ones to maintain the *best* value. When it finds that the best value is not updated for some periods (defined by `patience`), this trigger fires.

Parameters

- `monitor` (`str`) – The metric you want to monitor
- `check_trigger` (`TriggerLike`) – Trigger that decides the comparison interval between current best value and new value. This must be a tuple in the form of `<int>, 'epoch'` or `<int>, 'iteration'` which is passed to `IntervalTrigger`.
- `patience` (`int`) – Counts to let the trigger be patient. The trigger will not fire until the condition is met for successive patience checks.
- `mode` (`str`) – `'max'`, `'min'`, or `'auto'`. It is used to determine how to compare the monitored values.
- `verbose` (`bool`) – Enable verbose output. If verbose is true, you can get more information
- `max_trigger` (`Tuple[int, UnitLiteral]`) – Upper bound of the number of training loops

Methods

`__init__([check_trigger, monitor, patience, ...])`

`get_training_length()`

`load_state_dict(state)`

<code>may_fire(iteration, epoch_length)</code>	Flags if the trigger may fire at the current iteration
<code>state_dict()</code>	

`__call__(manager)`

Decides whether the training loop should be stopped.

Parameters

`manager` (`ExtensionsManager`) – Manager object that this trigger is associated with.
The observation of this manager is used to determine if the trigger should fire.

Returns

True if the training loop should be stopped.

Return type
bool

__init__(check_trigger=(1, 'epoch'), monitor='main/loss', patience=3, mode='auto', verbose=False, max_trigger=(100, 'epoch'))

Parameters

- **check_trigger** (*TriggerLike*) –
- **monitor** (*str*) –
- **patience** (*int*) –
- **mode** (*str*) –
- **verbose** (*bool*) –
- **max_trigger** (*Tuple[int, UnitLiteral]*) –

Return type

None

get_training_length()

Return type

Tuple[float, str]

may_fire(iteration, epoch_length)

Flags if the trigger may fire at the current iteration

This must not alter the trigger state

Parameters

- **iteration** (*int*) –
- **epoch_length** (*int*) –

Return type

bool

pytorch_pfn_extras.training.triggers.IntervalTrigger

class pytorch_pfn_extras.training.triggers.**IntervalTrigger**(*period, unit*)

Bases: *Trigger*

Trigger based on a fixed interval.

This trigger accepts iterations divided by a given interval. There are two ways to specify the interval: per iterations and epochs. *Iteration* means the number of updates, while *epoch* means the number of sweeps over the training dataset. Fractional values are allowed if the interval is a number of epochs; the trigger uses the *iteration* and *epoch_detail* attributes defined by the manager.

For the description of triggers see `get_trigger()`.

Parameters

- **period** (*int or float*) – Length of the interval. Must be an integer if unit is '*iteration*'.
- **unit** (*str*) – Unit of the length specified by period. It must be either '*iteration*' or '*epoch*'.

Methods

<code>__init__(period, unit)</code>	
<code>get_training_length()</code>	
<code>load_state_dict(state)</code>	
<code>may_fire(iteration, epoch_length)</code>	Flags if the trigger may fire at the current iteration
<code>state_dict()</code>	

`__call__(manager)`

Decides whether the extension should be called on this iteration.

Parameters

`manager` ([ExtensionsManager](#)) – Manager object that this trigger is associated with.
The iteration related information in this manager is used to determine if the trigger should fire.

Returns

True if the corresponding extension should be invoked in this iteration.

Return type

bool

`__init__(period, unit)`

Parameters

- `period` (float) –
- `unit` ([UnitLiteral](#)) –

`get_training_length()`

Return type

`Tuple[float, str]`

`may_fire(iteration, epoch_length)`

Flags if the trigger may fire at the current iteration

This must not alter the trigger state

Parameters

- `iteration` (int) –
- `epoch_length` (int) –

Return type

bool

`pytorch_pfn_extras.training.triggers.ManualScheduleTrigger`

```
class pytorch_pfn_extras.training.triggers.ManualScheduleTrigger(points, unit)
```

Bases: `Trigger`

Trigger invoked at specified point(s) of iterations or epochs.

This trigger accepts iterations or epochs indicated by given point(s). There are two ways to specify the point(s): iteration and epoch. `iteration` means the number of updates, while epoch means the number of sweeps over the training dataset. Fractional values are allowed if the point is a number of epochs; the trigger uses the `iteration` and `epoch_detail` attributes defined by the manager.

Parameters

- `points` (`int`, `float`, or `list` of `int` or `float`) – time of the trigger. Must be an integer or list of integer if unit is '`iteration`'.
- `unit` (`str`) – Unit of the time specified by `points`. It must be either '`iteration`' or '`epoch`'.

Methods

`__init__(points, unit)`

`load_state_dict(state)`

<code>may_fire(iteration, epoch_length)</code>	Flags if the trigger may fire at the current iteration
<code>state_dict()</code>	

`__call__(manager)`

Decides whether the extension should be called on this iteration.

Parameters

`manager` (`ExtensionsManager`) – Manager object that this trigger is associated with.
The iteration information in this manager is used to determine if the trigger should fire.

Returns

True if the corresponding extension should be invoked in this iteration.

Return type

`bool`

`__init__(points, unit)`

Parameters

- `points` (`Union[float, Sequence[float]]`) –
- `unit` (`UnitLiteral`) –

`may_fire(iteration, epoch_length)`

Flags if the trigger may fire at the current iteration

This must not alter the trigger state

Parameters

- `iteration` (`int`) –

- **epoch_length (int)** –

Return type

bool

[pytorch_pfn_extras.training.triggers.MaxValueTrigger](#)

```
class pytorch_pfn_extras.training.triggers.MaxValueTrigger(key, trigger=(1, 'epoch'))
```

Bases: [BestValueTrigger](#)

Trigger invoked when specific value becomes maximum.

For example you can use this trigger to take snapshot on the epoch the validation accuracy is maximum.

Parameters

- **key (str)** – Key of value. The trigger fires when the value associated with this key becomes maximum.
- **trigger (TriggerLike)** – Trigger that decides the comparison interval between current best value and new value. This must be a tuple in the form of <int>, 'epoch' or <int>, 'iteration' which is passed to [IntervalTrigger](#).

Methods

```
__init__(key[, trigger])
```

```
load_state_dict(to_load)
```

<code>may_fire(iteration, epoch_length)</code>	Flags if the trigger may fire at the current iteration
<code>state_dict()</code>	

```
__init__(key, trigger=(1, 'epoch'))
```

Parameters

- **key (str)** –
- **trigger (TriggerLike)** –

[pytorch_pfn_extras.training.triggers.MinValueTrigger](#)

```
class pytorch_pfn_extras.training.triggers.MinValueTrigger(key, trigger=(1, 'epoch'))
```

Bases: [BestValueTrigger](#)

Trigger invoked when specific value becomes minimum.

For example you can use this trigger to take snapshot on the epoch the validation loss is minimum.

Parameters

- **key (str)** – Key of value. The trigger fires when the value associated with this key becomes minimum.

- **trigger** (*TriggerLike*) – Trigger that decides the comparison interval between current best value and new value. This must be a tuple in the form of <int>, 'epoch' or <int>, 'iteration' which is passed to `IntervalTrigger`.

Methods

<code>__init__(key[, trigger])</code>	
<code>load_state_dict(to_load)</code>	
<code>may_fire(iteration, epoch_length)</code>	Flags if the trigger may fire at the current iteration
<code>state_dict()</code>	

`__init__(key, trigger=(1, 'epoch'))`

Parameters

- **key** (*str*) –
- **trigger** (*TriggerLike*) –

pytorch_pfn_extras.training.triggers.OnceTrigger

`class pytorch_pfn_extras.training.triggers.OnceTrigger(call_on_resume=False)`

Bases: `Trigger`

Trigger based on the starting point of the iteration.

This trigger accepts only once at starting point of the iteration. There are two ways to specify the starting point: only starting point in whole iteration or called again when training resumed.

Parameters

`call_on_resume` (*bool*) – Whether the extension is called again or not when restored from a snapshot. It is set to `False` by default.

finished

Flag that indicates whether or not this trigger will

Type
bool

fire in the future. This flag is used to determine if the extension should be initialized after resume.

Methods

<code>__init__([call_on_resume])</code>	
<code>load_state_dict(to_load)</code>	
<code>may_fire(iteration, epoch_length)</code>	Flags if the trigger may fire at the current iteration
<code>state_dict()</code>	

Attributes

`finished`

`__call__(manager)`

Call self as a function.

Parameters

`manager` ([ExtensionsManagerProtocol](#)) –

Return type

`bool`

`__init__(call_on_resume=False)`

Parameters

`call_on_resume (bool)` –

Return type

`None`

`property finished: bool`

`load_state_dict(to_load)`

Parameters

`to_load (Dict[str, Any])` –

Return type

`None`

`may_fire(iteration, epoch_length)`

Flags if the trigger may fire at the current iteration

This must not alter the trigger state

Parameters

- `iteration (int)` –

- `epoch_length (int)` –

Return type

`bool`

`state_dict()`

Return type

Dict[str, Any]

`pytorch_pfn_extras.training.triggers.TimeTrigger`

`class pytorch_pfn_extras.training.triggers.TimeTrigger(period)`

Bases: `Trigger`

Trigger based on a fixed time interval.

This trigger accepts iterations with a given interval time.

Parameters

`period (float)` – Interval time. It is given in seconds.

Methods

`__init__(period)`

`load_state_dict(to_load)`

<code>may_fire(iteration, epoch_len)</code>	Flags if the trigger may fire at the current iteration
<code>state_dict()</code>	

`__call__(manager)`

Call self as a function.

Parameters

`manager (ExtensionsManagerProtocol)` –

Return type

`bool`

`__init__(period)`

Parameters

`period (float)` –

Return type

`None`

`load_state_dict(to_load)`

Parameters

`to_load (Dict[str, Any])` –

Return type

`None`

`state_dict()`

Return type

Dict[str, Any]

Modules

```
pytorch_pfn_extras.training.triggers.  
early_stopping_trigger  
pytorch_pfn_extras.training.triggers.  
interval_trigger  
pytorch_pfn_extras.training.triggers.  
manual_schedule_trigger  
pytorch_pfn_extras.training.triggers.  
minmax_value_trigger  
pytorch_pfn_extras.training.triggers.  
once_trigger  
pytorch_pfn_extras.training.triggers.  
time_trigger
```

[pytorch_pfn_extras.training.triggers.early_stopping_trigger](#)

Classes

pytorch_pfn_extras.training. triggers.early_stopping_trigger. EarlyStoppingTrigger(self) pytorch_pfn_extras.training. triggers.early_stopping_trigger. ExtensionsManagerProtocol(...)	Trigger for Early Stopping
--	----------------------------

[pytorch_pfn_extras.training.triggers.early_stopping_trigger.EarlyStoppingTrigger](#)

```
class pytorch_pfn_extras.training.triggers.early_stopping_trigger.EarlyStoppingTrigger(self,  
                                         check_trigger=(1,  
                                         'epoch'),  
                                         mon-  
                                         i-  
                                         tor='main/loss',  
                                         pa-  
                                         tience=3,  
                                         mode='auto',  
                                         ver-  
                                         bose=False,  
                                         max_trigger=(100,  
                                         'epoch'))
```

Bases: *Trigger*

Trigger for Early Stopping

This trigger works as follows. Within each *check interval* defined by the `check_trigger` argument, it monitors and accumulates the reported value at each iteration. At the end of each interval, it computes the mean of the accumulated values and compares it to the previous ones to maintain the *best* value. When it finds that the best value is not updated for some periods (defined by `patience`), this trigger fires.

Parameters

- **monitor** (*str*) – The metric you want to monitor
- **check_trigger** (*TriggerLike*) – Trigger that decides the comparison interval between current best value and new value. This must be a tuple in the form of <int>, 'epoch' or <int>, 'iteration' which is passed to IntervalTrigger.
- **patience** (*int*) – Counts to let the trigger be patient. The trigger will not fire until the condition is met for successive patience checks.
- **mode** (*str*) – 'max', 'min', or 'auto'. It is used to determine how to compare the monitored values.
- **verbose** (*bool*) – Enable verbose output. If verbose is true, you can get more information
- **max_trigger** (*Tuple[int, UnitLiteral]*) – Upper bound of the number of training loops

Methods

`__init__([check_trigger, monitor, patience, ...])`

`get_training_length()`

`load_state_dict(state)`

<code>may_fire(iteration, epoch_length)</code>	Flags if the trigger may fire at the current iteration
<code>state_dict()</code>	

`__call__(manager)`

Decides whether the training loop should be stopped.

Parameters

`manager` (`ExtensionsManager`) – Manager object that this trigger is associated with.
The observation of this manager is used to determine if the trigger should fire.

Returns

True if the training loop should be stopped.

Return type

`bool`

`__init__(check_trigger=(1, 'epoch'), monitor='main/loss', patience=3, mode='auto', verbose=False, max_trigger=(100, 'epoch'))`

Parameters

- **check_trigger** (*TriggerLike*) –
- **monitor** (*str*) –
- **patience** (*int*) –
- **mode** (*str*) –
- **verbose** (*bool*) –
- **max_trigger** (*Tuple[int, UnitLiteral]*) –

Return type

None

`get_training_length()`

Return type

Tuple[float, str]

`may_fire(iteration, epoch_length)`

Flags if the trigger may fire at the current iteration

This must not alter the trigger state

Parameters

- `iteration (int)` –
- `epoch_length (int)` –

Return type

bool

[pytorch_pfn_extras.training.triggers.early_stopping_trigger.ExtensionsManagerProtocol](#)

`class pytorch_pfn_extras.training.triggers.early_stopping_trigger.ExtensionsManagerProtocol(*args, **kwargs)`

Bases: Protocol

Methods

`__init__(*args, **kwargs)`

`get_extension(name)`

Attributes

elapsed_time

epoch

epoch_detail

is_before_training

iteration

models

observation

optimizers

out

raw_models

reporter

stop_trigger

writer

`__init__(*args, **kwargs)`

`property elapsed_time: float`

`property epoch: int`

`property epoch_detail: float`

`get_extension(name)`

Parameters

`name (str) –`

Return type

Extension

`property is_before_training: bool`

`property iteration: int`

`property models: Mapping[str, Module]`

`property observation: reporting.Observation`

`property optimizers: Mapping[str, Optimizer]`

```
property out: str
property raw_models: Mapping[str, Module]
property reporter: reporting.Reporter
property stop_trigger: bool
property writer: Optional[writing.Writer]
```

[pytorch_pfn_extras.training.triggers.interval_trigger](#)

Classes

<code>pytorch_pfn_extras.training. triggers.interval_trigger. ExtensionsManagerProtocol(...)</code>	
<code>pytorch_pfn_extras.training.triggers. interval_trigger.IntervalTrigger(...)</code>	Trigger based on a fixed interval.

[pytorch_pfn_extras.training.triggers.interval_trigger.ExtensionsManagerProtocol](#)

```
class pytorch_pfn_extras.training.triggers.interval_trigger.ExtensionsManagerProtocol(*args,  
                                         **kwargs)
```

Bases: Protocol

Methods

```
__init__(*args, **kwargs)  
get_extension(name)
```

Attributes

elapsed_time

epoch

epoch_detail

is_before_training

iteration

models

observation

optimizers

out

raw_models

reporter

stop_trigger

writer

`__init__(*args, **kwargs)`

`property elapsed_time: float`

`property epoch: int`

`property epoch_detail: float`

`get_extension(name)`

Parameters

`name (str) –`

Return type

Extension

`property is_before_training: bool`

`property iteration: int`

`property models: Mapping[str, Module]`

`property observation: reporting.Observation`

`property optimizers: Mapping[str, Optimizer]`

```
property out: str
property raw_models: Mapping[str, Module]
property reporter: reporting.Reporter
property stop_trigger: bool
property writer: Optional[writing.Writer]
```

pytorch_pfn_extras.training.triggers.interval_trigger.IntervalTrigger

```
class pytorch_pfn_extras.training.triggers.interval_trigger.IntervalTrigger(period, unit)
```

Bases: [Trigger](#)

Trigger based on a fixed interval.

This trigger accepts iterations divided by a given interval. There are two ways to specify the interval: per iterations and epochs. *Iteration* means the number of updates, while *epoch* means the number of sweeps over the training dataset. Fractional values are allowed if the interval is a number of epochs; the trigger uses the *iteration* and *epoch_detail* attributes defined by the manager.

For the description of triggers see [get_trigger\(\)](#).

Parameters

- **period** (*int or float*) – Length of the interval. Must be an integer if unit is 'iteration'.
- **unit** (*str*) – Unit of the length specified by period. It must be either 'iteration' or 'epoch'.

Methods

```
__init__(period, unit)
```

```
get_training_length()
```

```
load_state_dict(state)
```

may_fire (iteration, epoch_length)	Flags if the trigger may fire at the current iteration
state_dict ()	

```
__call__(manager)
```

Decides whether the extension should be called on this iteration.

Parameters

manager ([ExtensionsManager](#)) – Manager object that this trigger is associated with. The iteration related information in this manager is used to determine if the trigger should fire.

Returns

True if the corresponding extension should be invoked in this iteration.

Return type
bool

__init__(period, unit)

Parameters

- **period** (*float*) –
- **unit** (*UnitLiteral*) –

get_training_length()

Return type
Tuple[float, str]

may_fire(iteration, epoch_length)

Flags if the trigger may fire at the current iteration

This must not alter the trigger state

Parameters

- **iteration** (*int*) –
- **epoch_length** (*int*) –

Return type
bool

pytorch_pfn_extras.training.triggers.manual_schedule_trigger

Classes

<i>pytorch_pfn_extras.training.</i>	
<i>triggers.manual_schedule_trigger.</i>	
<i>ExtensionsManagerProtocol(...)</i>	
<i>pytorch_pfn_extras.training.</i>	Trigger invoked at specified point(s) of iterations or
<i>triggers.manual_schedule_trigger.</i>	epochs.
<i>ManualScheduleTrigger(...)</i>	

pytorch_pfn_extras.training.triggers.manual_schedule_trigger.ExtensionsManagerProtocol

class pytorch_pfn_extras.training.triggers.manual_schedule_trigger.ExtensionsManagerProtocol(*args, **kwargs)

Bases: Protocol

Methods

```
__init__(*args, **kwargs)
```

```
get_extension(name)
```

Attributes

```
elapsed_time
```

```
epoch
```

```
epoch_detail
```

```
is_before_training
```

```
iteration
```

```
models
```

```
observation
```

```
optimizers
```

```
out
```

```
raw_models
```

```
reporter
```

```
stop_trigger
```

```
writer
```

```
__init__(*args, **kwargs)
```

```
property elapsed_time: float
```

```
property epoch: int
```

```
property epoch_detail: float
```

```
get_extension(name)
```

Parameters

`name (str) –`

Return type

`Extension`

```

property is_before_training: bool
property iteration: int
property models: Mapping[str, Module]
property observation: reporting.Observation
property optimizers: Mapping[str, Optimizer]
property out: str
property raw_models: Mapping[str, Module]
property reporter: reporting.Reporter
property stop_trigger: bool
property writer: Optional[writing.Writer]

```

`pytorch_pfn_extras.training.triggers.manual_schedule_trigger.ManualScheduleTrigger`

```
class pytorch_pfn_extras.training.triggers.manual_schedule_trigger.ManualScheduleTrigger(points,
                                         unit)
```

Bases: `Trigger`

Trigger invoked at specified point(s) of iterations or epochs.

This trigger accepts iterations or epochs indicated by given point(s). There are two ways to specify the point(s): `iteration` and `epoch`. `iteration` means the number of updates, while `epoch` means the number of sweeps over the training dataset. Fractional values are allowed if the point is a number of epochs; the trigger uses the `iteration` and `epoch_detail` attributes defined by the manager.

Parameters

- `points` (`int`, `float`, or `list of int or float`) – time of the trigger. Must be an integer or list of integer if unit is '`iteration`'.
- `unit` (`str`) – Unit of the time specified by `points`. It must be either '`iteration`' or '`epoch`'.

Methods

`__init__(points, unit)`

`load_state_dict(state)`

<code>may_fire(iteration, epoch_length)</code>	Flags if the trigger may fire at the current iteration
<code>state_dict()</code>	

`__call__(manager)`

Decides whether the extension should be called on this iteration.

Parameters

manager (`ExtensionsManager`) – Manager object that this trigger is associated with.
The iteration information in this manager is used to determine if the trigger should fire.

Returns

True if the corresponding extension should be invoked in this iteration.

Return type

`bool`

`__init__(points, unit)`

Parameters

- **points** (`Union[float, Sequence[float]]`) –
- **unit** (`UnitLiteral`) –

`may_fire(iteration, epoch_length)`

Flags if the trigger may fire at the current iteration

This must not alter the trigger state

Parameters

- **iteration** (`int`) –
- **epoch_length** (`int`) –

Return type

`bool`

[pytorch_pfn_extras.training.triggers.minmax_value_trigger](#)

Classes

<code>pytorch_pfn_extras.training.triggers.minmax_value_trigger.BestValueTrigger(...)</code>	Trigger invoked when specific value becomes best.
<code>pytorch_pfn_extras.training.triggers.minmax_value_trigger.ExtensionsManagerProtocol(...)</code>	
<code>pytorch_pfn_extras.training.triggers.minmax_value_trigger.MaxValueTrigger(key)</code>	Trigger invoked when specific value becomes maximum.
<code>pytorch_pfn_extras.training.triggers.minmax_value_trigger.MinValueTrigger(key)</code>	Trigger invoked when specific value becomes minimum.

[pytorch_pfn_extras.training.triggers.minmax_value_trigger.BestValueTrigger](#)

```
class pytorch_pfn_extras.training.triggers.minmax_value_trigger.BestValueTrigger(key,
                                compare,
                                trig-
                                ger=(1,
                                'epoch'))
```

Bases: `Trigger`

Trigger invoked when specific value becomes best.

Parameters

- **key** (*str*) – Key of value.
- **compare** (*callable*) – Compare function which takes current best value and new value and returns whether new value is better than current best.
- **trigger** (*TriggerLike*) – Trigger that decides the comparison interval between current best value and new value. This must be a tuple in the form of <int>, 'epoch' or <int>, 'iteration' which is passed to IntervalTrigger.

Methods

<code>__init__(key, compare[, trigger])</code>	
<code>load_state_dict(to_load)</code>	
<code>may_fire(iteration, epoch_length)</code>	Flags if the trigger may fire at the current iteration
<code>state_dict()</code>	

`__call__(manager)`

Decides whether the extension should be called on this iteration.

Parameters

- manager** (*ExtensionsManager*) – Manager object that this trigger is associated with.
The observation of this manager is used to determine if the trigger should fire.

Returns

True if the corresponding extension should be invoked in this iteration.

Return type

bool

`__init__(key, compare, trigger=(1, 'epoch'))`

Parameters

- **key** (*str*) –
- **compare** (*Callable[[float, float], bool]*) –
- **trigger** (*TriggerLike*) –

Return type

None

`load_state_dict(to_load)`

Parameters

- to_load** (*Dict[str, Any]*) –

Return type

None

`may_fire(iteration, epoch_length)`

Flags if the trigger may fire at the current iteration

This must not alter the trigger state

Parameters

- **iteration** (*int*) –
- **epoch_length** (*int*) –

Return type

bool

state_dict()

Return type

Dict[str, *Any*]

pytorch_pfn_extras.training.triggers.minmax_value_trigger.ExtensionsManagerProtocol

class pytorch_pfn_extras.training.triggers.minmax_value_trigger.ExtensionsManagerProtocol(**args*,
***kwargs*)

Bases: Protocol

Methods

__init__(*args, **kwargs)

get_extension(name)

Attributes

elapsed_time

epoch

epoch_detail

is_before_training

iteration

models

observation

optimizers

out

raw_models

reporter

stop_trigger

writer

`__init__(*args, **kwargs)`

`property elapsed_time: float`

`property epoch: int`

`property epoch_detail: float`

`get_extension(name)`

Parameters

`name (str) –`

Return type

Extension

`property is_before_training: bool`

`property iteration: int`

`property models: Mapping[str, Module]`

`property observation: reporting.Observation`

`property optimizers: Mapping[str, Optimizer]`

```
property out: str
property raw_models: Mapping[str, Module]
property reporter: reporting.Reporter
property stop_trigger: bool
property writer: Optional[writing.Writer]
```

pytorch_pfn_extras.training.triggers.minmax_value_trigger.MaxValueTrigger

```
class pytorch_pfn_extras.training.triggers.minmax_value_trigger.MaxValueTrigger(key,
                                                                                 trigger=(1,
                                                                                 'epoch'))
```

Bases: [BestValueTrigger](#)

Trigger invoked when specific value becomes maximum.

For example you can use this trigger to take snapshot on the epoch the validation accuracy is maximum.

Parameters

- **key** (*str*) – Key of value. The trigger fires when the value associated with this key becomes maximum.
- **trigger** (*TriggerLike*) – Trigger that decides the comparison interval between current best value and new value. This must be a tuple in the form of <int>, 'epoch' or <int>, 'iteration' which is passed to `IntervalTrigger`.

Methods

```
__init__(key[, trigger])
```

```
load_state_dict(to_load)
```

<code>may_fire(iteration, epoch_length)</code>	Flags if the trigger may fire at the current iteration
<code>state_dict()</code>	

```
__init__(key, trigger=(1, 'epoch'))
```

Parameters

- **key** (*str*) –
- **trigger** (*TriggerLike*) –

pytorch_pfn_extras.training.triggers.minmax_value_trigger.MinValueTrigger

```
class pytorch_pfn_extras.training.triggers.minmax_value_trigger.MinValueTrigger(key,
                                                                           trigger=(1,
                                         'epoch'))
```

Bases: *BestValueTrigger*

Trigger invoked when specific value becomes minimum.

For example you can use this trigger to take snapshot on the epoch the validation loss is minimum.

Parameters

- **key** (*str*) – Key of value. The trigger fires when the value associated with this key becomes minimum.
- **trigger** (*TriggerLike*) – Trigger that decides the comparison interval between current best value and new value. This must be a tuple in the form of <int>, 'epoch' or <int>, 'iteration' which is passed to `IntervalTrigger`.

Methods

```
__init__(key[, trigger])
```

```
load_state_dict(to_load)
```

```
may_fire(iteration, epoch_length)           Flags if the trigger may fire at the current iteration
state_dict()
```

```
__init__(key, trigger=(1, 'epoch'))
```

Parameters

- **key** (*str*) –
- **trigger** (*TriggerLike*) –

pytorch_pfn_extras.training.triggers.once_trigger

Classes

```
pytorch_pfn_extras.training.triggers.
once_trigger.ExtensionsManagerProtocol(...)
```

```
pytorch_pfn_extras.training.triggers.      Trigger based on the starting point of the iteration.
once_trigger.OnceTrigger([...])
```

`pytorch_pfn_extras.training.triggers.once_trigger.ExtensionsManagerProtocol`

```
class pytorch_pfn_extras.training.triggers.once_trigger.ExtensionsManagerProtocol(*args,  
                                **kwargs)
```

Bases: Protocol

Methods

```
__init__(*args, **kwargs)
```

```
get_extension(name)
```

Attributes

```
elapsed_time
```

```
epoch
```

```
epoch_detail
```

```
is_before_training
```

```
iteration
```

```
models
```

```
observation
```

```
optimizers
```

```
out
```

```
raw_models
```

```
reporter
```

```
stop_trigger
```

```
writer
```

```
__init__(*args, **kwargs)
```

```
property elapsed_time: float
```

```
property epoch: int
```

```
property epoch_detail: float
```

```
get_extension(name)

    Parameters
        name (str) –

    Return type
        Extension

property is_before_training: bool

property iteration: int

property models: Mapping[str, Module]

property observation: reporting.Observation

property optimizers: Mapping[str, Optimizer]

property out: str

property raw_models: Mapping[str, Module]

property reporter: reporting.Reporter

property stop_trigger: bool

property writer: Optional[writing.Writer]
```

[pytorch_pfn_extras.training.triggers.once_trigger.OnceTrigger](#)

```
class pytorch_pfn_extras.training.triggers.once_trigger.OnceTrigger(call_on_resume=False)

Bases: Trigger
```

Trigger based on the starting point of the iteration.

This trigger accepts only once at starting point of the iteration. There are two ways to specify the starting point: only starting point in whole iteration or called again when training resumed.

Parameters

`call_on_resume` (bool) – Whether the extension is called again or not when restored from a snapshot. It is set to `False` by default.

finished

Flag that indicates whether or not this trigger will

Type

bool

`fire in the future. This flag is used to determine if the extension should be initialized after resume.`

Methods

<code>__init__([call_on_resume])</code>	
<code>load_state_dict(to_load)</code>	
<code>may_fire(iteration, epoch_length)</code>	Flags if the trigger may fire at the current iteration
<code>state_dict()</code>	

Attributes

`finished`

`__call__(manager)`

Call self as a function.

Parameters

`manager` ([ExtensionsManagerProtocol](#)) –

Return type

`bool`

`__init__(call_on_resume=False)`

Parameters

`call_on_resume (bool)` –

Return type

`None`

`property finished: bool`

`load_state_dict(to_load)`

Parameters

`to_load (Dict[str, Any])` –

Return type

`None`

`may_fire(iteration, epoch_length)`

Flags if the trigger may fire at the current iteration

This must not alter the trigger state

Parameters

- `iteration (int)` –

- `epoch_length (int)` –

Return type

`bool`

`state_dict()`

Return type

Dict[str, Any]

[pytorch_pfn_extras.training.triggers.time_trigger](#)

Classes

pytorch_pfn_extras.training.triggers.time_trigger.ExtensionsManagerProtocol(...)

pytorch_pfn_extras.training.triggers.time_trigger.TimeTrigger(period) Trigger based on a fixed time interval.

[pytorch_pfn_extras.training.triggers.time_trigger.ExtensionsManagerProtocol](#)

`class pytorch_pfn_extras.training.triggers.time_trigger.ExtensionsManagerProtocol(*args, **kwargs)`

Bases: `Protocol`

Methods

`__init__(*args, **kwargs)`

`get_extension(name)`

Attributes

```
elapsed_time
epoch
epoch_detail
is_before_training
iteration
models
observation
optimizers
out
raw_models
reporter
stop_trigger
writer
```

```
__init__(*args, **kwargs)
property elapsed_time: float
property epoch: int
property epoch_detail: float
get_extension(name)

    Parameters
        name (str) ->

    Return type
        Extension

    property is_before_training: bool
    property iteration: int
    property models: Mapping[str, Module]
    property observation: reporting.Observation
    property optimizers: Mapping[str, Optimizer]
```

```

property out: str
property raw_models: Mapping[str, Module]
property reporter: reporting.Reporter
property stop_trigger: bool
property writer: Optional[writing.Writer]

```

pytorch_pfn_extras.training.triggers.time_trigger.TimeTrigger

class pytorch_pfn_extras.training.triggers.time_trigger.TimeTrigger(*period*)

Bases: *Trigger*

Trigger based on a fixed time interval.

This trigger accepts iterations with a given interval time.

Parameters

period (*float*) – Interval time. It is given in seconds.

Methods

__init__(*period*)

load_state_dict(*to_load*)

may_fire(<i>iteration, epoch_len</i>)	Flags if the trigger may fire at the current iteration
state_dict()	

__call__(*manager*)

Call self as a function.

Parameters

manager (*ExtensionsManagerProtocol*) –

Return type

bool

__init__(*period*)

Parameters

period (*float*) –

Return type

None

load_state_dict(*to_load*)

Parameters

to_load (*Dict[str, Any]*) –

Return type

None

`state_dict()`

Return type

Dict[str, Any]

[pytorch_pfn_extras.utils](#)

Modules

[pytorch_pfn_extras.utils.checkpoint](#)

[pytorch_pfn_extras.utils.comparer](#)

[pytorch_pfn_extras.utils.checkpoint](#)

Functions

[pytorch_pfn_extras.utils.checkpoint.](#)
`checkpoint(...)`

[pytorch_pfn_extras.utils.checkpoint.checkpoint](#)

`pytorch_pfn_extras.utils.checkpoint.checkpoint(function, *args, **kwargs)`

Parameters

- **function** (*Module*) –
- **args** (*Any*) –
- **kwargs** (*Any*) –

Return type

Any

[pytorch_pfn_extras.utils.comparer](#)

Functions

[pytorch_pfn_extras.utils.comparer.](#)
`get_default_comparer(...)`

Creates default comparer function.

[pytorch_pfn_extras.utils.comparer.](#)
`intermediate_value(...)`

pytorch_pfn_extras.utils.comparer.get_default_comparer

`pytorch_pfn_extras.utils.comparer.get_default_comparer(rtol=0.0001, atol=0, equal_nan=True)`

Creates default comparer function.

The created function will compare the outputs by using `torch.testing.assert_allclose` with specified options.

Parameters

- **rtol** (*float*) – Relative tolerance.
- **atol** (*float*) – Absolute tolerance.
- **equal_nan** (*bool*) – If True, NaNs will be ignored.

Return type

Callable[[str, str, str, Any, Any], None]

pytorch_pfn_extras.utils.comparer.intermediate_value

`pytorch_pfn_extras.utils.comparer.intermediate_value(name, value)`

Parameters

- **name** (*str*) –
- **value** (*Tensor*) –

Return type

None

Classes

<code>pytorch_pfn_extras.utils.comparer.Comparer(*)</code>	A class for comparison of iteration outputs and model parameters.
<code>pytorch_pfn_extras.utils.comparer.ModelComparer(engines)</code>	A class for comparison of iteration model parameters.
<code>pytorch_pfn_extras.utils.comparer.OutputsComparer(engines)</code>	A class for comparison of iteration outputs.

pytorch_pfn_extras.utils.comparer.Comparer

```
class pytorch_pfn_extras.utils.comparer.Comparer(*, trigger=None, compare_fn=<function  
get_default_comparer.<locals>.compare_fn>,  
concurrency=None, outputs=True, params=False,  
baseline=None)
```

Bases: `object`

A class for comparison of iteration outputs and model parameters.

This class is mainly used to compare results between different devices.

Parameters

- **trigger** (`Trigger`) – Trigger object that determines when to compare values.

- **compare_fn** (*function*) – Comparison function. Default is `get_default_comparer()`.
- **concurrency** (*int, optional*) – The upper bound limit on the number of workers that run concurrently. If None, inferred from the size of engines.
- **outputs** (*tuple of str or bool*) – A set of keys of output dict to compare.
- **params** (*tuple of str or bool*) – A set of keys of model parameters to compare.
- **baseline** (*str, optional*) – The baseline engine that is assumed to be correct.

Examples

```
>>> trainer_cpu = ppe.engine.create_trainer(
    model, optimizer, 1, device='cpu')
>>> trainer_gpu = ppe.engine.create_trainer(
    model, optimizer, 1, device='cuda:0')
>>> comp = ppe.utils.comparer.Comparer()
>>> comp.add_engine("cpu", engine_cpu, train_1, eval_1)
>>> comp.add_engine("gpu", engine_gpu, train_2, eval_2)
>>> comp.compare()
```

Methods

<code>__init__(*[trigger, compare_fn, ...])</code>	A class for comparison of iteration outputs and model parameters.
<code>add_dump(name, dir)</code>	Add an engine to compare variables.
<code>add_engine(name, engine, *args, **kwargs)</code>	Add an engine to compare variables.
<code>compare()</code>	Compares outputs.
<code>dump(engine, dir, *args, **kwargs)</code>	Add an engine to compare variables.

`__init__(*, trigger=None, compare_fn=<function get_default_comparer.<locals>.compare_fn>, concurrency=None, outputs=True, params=False, baseline=None)`

A class for comparison of iteration outputs and model parameters.

This class is mainly used to compare results between different devices.

Parameters

- **trigger** (`Trigger`) – Trigger object that determines when to compare values.
- **compare_fn** (*function*) – Comparison function. Default is `get_default_comparer()`.
- **concurrency** (*int, optional*) – The upper bound limit on the number of workers that run concurrently. If None, inferred from the size of engines.
- **outputs** (*tuple of str or bool*) – A set of keys of output dict to compare.
- **params** (*tuple of str or bool*) – A set of keys of model parameters to compare.
- **baseline** (*str, optional*) – The baseline engine that is assumed to be correct.

Return type

None

Examples

```
>>> trainer_cpu = ppe.engine.create_trainer(
    model, optimizer, 1, device='cpu')
>>> trainer_gpu = ppe.engine.create_trainer(
    model, optimizer, 1, device='cuda:0')
>>> comp = ppe.utils.comparer.Comparer()
>>> comp.add_engine("cpu", engine_cpu, train_1, eval_1)
>>> comp.add_engine("gpu", engine_gpu, train_2, eval_2)
>>> comp.compare()
```

`add_dump(name, dir)`

Add an engine to compare variables.

Parameters

- **name** (*str*) – The name of dump.
- **dir** (*str*) – The directory that the results are saved to.

Return type

None

`add_engine(name, engine, *args, **kwargs)`

Add an engine to compare variables.

Parameters

- **name** (*str*) – Engine name.
- **engine** (*Trainer or Evaluator*) – An engine to compare variables.
- ****kwargs** (**args and*) – Arguments passed to `engine.run`.
- **args** (*Any*) –
- **kwargs** (*Any*) –

Return type

None

`compare()`

Compares outputs.

Return type

None

`dump(engine, dir, *args, **kwargs)`

Add an engine to compare variables.

Parameters

- **engine** (*Trainer or Evaluator*) – An engine to compare variables.
- **dir** (*str*) – Name of the directory that the results are saved to.
- ****kwargs** (**args and*) – Arguments passed to `engine.run`.
- **args** (*Any*) –
- **kwargs** (*Any*) –

Return type

None

[pytorch_pfn_extras.utils.comparer.ModelComparer](#)

```
class pytorch_pfn_extras.utils.comparer.ModelComparer(engines, to_compare_keys=None, *,  
                                                    compare_fn=<function  
                                                    get_default_comparer.<locals>.compare_fn>,  
                                                    concurrency=None)
```

Bases: `_ComparerBase`

A class for comparison of iteration model parameters.

This class is mainly used to compare results between different devices.

Parameters

- **engines** (*dict of Engines*) – Trainers or Evaluators to compare outputs.
- **to_compare_keys** (*tuple of str, optional*) – A set of keys of model parameters to compare.
- **compare_fn** (*function*) – Comparison function. Default is `get_default_comparer()`.
- **concurrency** (*int, optional*) – The upper bound limit on the number of workers that run concurrently. If None, inferred from the size of engines.

Examples

```
>>> trainer_cpu = ppe.engine.create_trainer(  
    model, optimizer, 1, device='cpu')  
>>> trainer_gpu = ppe.engine.create_trainer(  
    model, optimizer, 1, device='cuda:0')  
>>> comp = ppe.utils.comparer.ModelComparer(  
    {"cpu": trainer_cpu, "gpu": trainer_gpu})  
>>> comp.compare({"cpu": loader, "gpu": loader})
```

Methods

<code>__init__(engines[, to_compare_keys, ...])</code>	A class for comparison of iteration model parameters.
--	---

<code>compare(loaders[, n_iters])</code>	Compares outputs.
--	-------------------

<code>compare_targets(name, engine, batch_idx, target)</code>	
---	--

<code>run_engine(engine, loaders)</code>	
--	--

```
__init__(engines, to_compare_keys=None, *, compare_fn=<function  
get_default_comparer.<locals>.compare_fn>, concurrency=None)
```

A class for comparison of iteration model parameters.

This class is mainly used to compare results between different devices.

Parameters

- **engines** (*dict of Engines*) – Trainers or Evaluators to compare outputs.

- **to_compare_keys** (*tuple of str, optional*) – A set of keys of model parameters to compare.
- **compare_fn** (*function*) – Comparison function. Default is `get_default_comparer()`.
- **concurrency** (*int, optional*) – The upper bound limit on the number of workers that run concurrently. If None, inferred from the size of engines.

Examples

```
>>> trainer_cpu = ppe.engine.create_trainer(
    model, optimizer, 1, device='cpu')
>>> trainer_gpu = ppe.engine.create_trainer(
    model, optimizer, 1, device='cuda:0')
>>> comp = ppe.utils.comparer.ModelComparer(
    {"cpu": trainer_cpu, "gpu": trainer_gpu})
>>> comp.compare({"cpu": loader, "gpu": loader})
```

`pytorch_pfn_extras.utils.comparer.OutputsComparer`

```
class pytorch_pfn_extras.utils.comparer.OutputsComparer(engines, to_compare_keys=None, *,
                                                       compare_fn=<function
                                                       get_default_comparer.<locals>.compare_fn>,
                                                       concurrency=None)
```

Bases: `_ComparerBase`

A class for comparison of iteration outputs.

This class is mainly used to compare results between different devices.

Parameters

- **engines** (*dict of Engines*) – Trainers or Evaluators to compare outputs.
- **to_compare_keys** (*tuple of str, optional*) – A set of keys of output dict to compare.
- **compare_fn** (*function*) – Comparison function. Default is `get_default_comparer()`.
- **concurrency** (*int, optional*) – The upper bound limit on the number of workers that run concurrently. If None, inferred from the size of engines.

Examples

```
>>> trainer_cpu = ppe.engine.create_trainer(
    model, optimizer, 1, device='cpu')
>>> trainer_gpu = ppe.engine.create_trainer(
    model, optimizer, 1, device='cuda:0')
>>> comp = ppe.utils.comparer.OutputsComparer(
    {"cpu": trainer_cpu, "gpu": trainer_gpu})
>>> comp.compare({"cpu": loader, "gpu": loader})
```

Methods

<code>__init__(engines[, to_compare_keys, ...])</code>	A class for comparison of iteration outputs.
<code>compare(loaders[, n_iters])</code>	Compares outputs.
<code>compare_targets(name, engine, batch_idx, target)</code>	
<code>run_engine(engine, loaders)</code>	

`__init__(engines, to_compare_keys=None, *, compare_fn=<function
get_default_comparer.<locals>.compare_fn>, concurrency=None)`

A class for comparison of iteration outputs.

This class is mainly used to compare results between different devices.

Parameters

- **engines** (*dict of Engines*) – Trainers or Evaluators to compare outputs.
- **to_compare_keys** (*tuple of str, optional*) – A set of keys of output dict to compare.
- **compare_fn** (*function*) – Comparison function. Default is `get_default_comparer()`.
- **concurrency** (*int, optional*) – The upper bound limit on the number of workers that run concurrently. If None, inferred from the size of engines.

Return type

None

Examples

```
>>> trainer_cpu = ppe.engine.create_trainer(  
        model, optimizer, 1, device='cpu')  
>>> trainer_gpu = ppe.engine.create_trainer(  
        model, optimizer, 1, device='cuda:0')  
>>> comp = ppe.utils.comparer.OutputsComparer(  
        {"cpu": trainer_cpu, "gpu": trainer_gpu})  
>>> comp.compare({"cpu": loader, "gpu": loader})
```

pytorch_pfn_extras.writing

Classes

<code>pytorch_pfn_extras.writing.ProcessQueueWriter(...)</code>	Snapshot writer that uses process queue.
<code>pytorch_pfn_extras.writing.ProcessWriter(...)</code>	Snapshot writer that uses a separate process.
<code>pytorch_pfn_extras.writing.QueueWriter(...)</code>	Base class of queue snapshot writers.
<code>pytorch_pfn_extras.writing.SimpleWriter(...)</code>	The most simple snapshot writer.
<code>pytorch_pfn_extras.writing.StandardWriter(...)</code>	Base class of snapshot writers which use thread or process.
<code>pytorch_pfn_extras.writing.TensorBoardWriter(...)</code>	Writer that sends statistics to TensorBoard.
<code>pytorch_pfn_extras.writing.ThreadQueueWriter(...)</code>	Snapshot writer that uses a thread queue.
<code>pytorch_pfn_extras.writing.ThreadWriter(...)</code>	Snapshot writer that uses a separate thread.
<code>pytorch_pfn_extras.writing.Writer(fs, out_dir)</code>	Base class of snapshot writers.

`pytorch_pfn_extras.writing.ProcessQueueWriter`

```
class pytorch_pfn_extras.writing.ProcessQueueWriter(savefun=<function save>, fs=None, out_dir='', task=None)
```

Bases: `QueueWriter[Process]`

Snapshot writer that uses process queue.

This class creates a process and a queue by `multiprocessing` module. The process will be a consumer of this queue, and the main process will be a producer of this queue.

Note: Forking a new process from MPI process might be danger. Consider using `ThreadQueueWriter` instead of `ProcessQueueWriter` if you are using MPI.

See also:

- `pytorch_pfn_extras.training.extensions.snapshot()`

Methods

<code>__init__([savefun, fs, out_dir, task])</code>	
<code>consume(q)</code>	
<code>create_consumer(q)</code>	
<code>create_queue()</code>	
<code>create_task(savefun)</code>	
<code>finalize()</code>	Finalizes the writer.
<code>initialize(out_dir)</code>	
<code>save(filename, out_dir, target, savefun, ...)</code>	

`__init__(savefun=<function save>, fs=None, out_dir='', task=None)`

Parameters

- `savefun (Callable[..., None])` –
- `fs (Optional[Any])` –
- `out_dir (str)` –
- `task (Optional[Callable[..., None]])` –

Return type

`None`

`create_consumer(q)`

Parameters

`q (queue.Queue[_QueUnit])` –

Return type

`Process`

`create_queue()`

Return type

`queue.Queue[_QueUnit]`

[pytorch_pfn_extras.writing.ProcessWriter](#)

`class pytorch_pfn_extras.writing.ProcessWriter(savefun=<function save>, fs=None, out_dir='', **kwds)`

Bases: `StandardWriter[Process]`

Snapshot writer that uses a separate process.

This class creates a new process that invokes the actual saving function.

Note: Forking a new process from a MPI process might be danger. Consider using [ThreadWriter](#) instead of [ProcessWriter](#) if you are using MPI.

See also:

- [pytorch_pfn_extras.training.extensions.snapshot\(\)](#)

Methods

`__init__([savefun, fs, out_dir])`

<code>create_worker(filename, out_dir, target, *)</code>	Creates a worker for the snapshot.
--	------------------------------------

<code>finalize()</code>	Finalizes the writer.
-------------------------	-----------------------

<code>initialize(out_dir)</code>	
----------------------------------	--

<code>save(filename, out_dir, target, savefun, ...)</code>	
--	--

`__init__(savefun=<function save>, fs=None, out_dir='', **kwds)`

Parameters

- **savefun** (*Callable[[...], None]*) –
- **fs** (*Optional[Any]*) –
- **out_dir** (*str*) –
- **kwds** (*Any*) –

Return type

None

`create_worker(filename, out_dir, target, *, savefun=None, append=False, **savefun_kwargs)`

Creates a worker for the snapshot.

This method creates a thread or a process to take a snapshot. The created worker must have `start()` and `join()` methods. If the worker has an `exitcode` attribute (e.g., `multiprocessing.Process`), the value will be tested.

Parameters

- **filename** (*str*) –
- **out_dir** (*str*) –
- **target** (*Union[Sequence[Any], Mapping[str, Any]]*) –
- **savefun** (*Optional[Callable[[...], None]]*) –
- **append** (*bool*) –
- **savefun_kwargs** (*Any*) –

Return type

Process

[pytorch_pfn_extras.writing.QueueWriter](#)

```
class pytorch_pfn_extras.writing.QueueWriter(savefun=<function save>, fs=None, out_dir='', task=None)
```

Bases: [Writer](#), [Generic\[_Worker\]](#)

Base class of queue snapshot writers.

This class is a base class of snapshot writers that use a queue. A Queue is created when this class is constructed, and every time when `__call__` is invoked, a snapshot task is put into the queue.

Parameters

- **savefun** – Callable object which is passed to the `create_task()` if the task is `None`. It takes three arguments: the output file path, the serialized dictionary object, and the optional keyword arguments.
- **fs** – FileSystem abstracting interface to implement all the operations. optional, defaults to `None`
- **out_dir** – str. Specifies the directory this writer will use. It takes precedence over the one specified in `__call__` optional, defaults to ''
- **task** – Callable object. Its `__call__` must have a same interface to `Writer.__call__`. This object is directly put into the queue.

See also:

- [pytorch_pfn_extras.training.extensions.snapshot\(\)](#)

Methods

`__init__([savefun, fs, out_dir, task])`

`consume(q)`

`create_consumer(q)`

`create_queue()`

`create_task(savefun)`

`finalize()` Finalizes the writer.
`initialize(out_dir)`

`save(filename, out_dir, target, savefun, ...)`

`__call__(filename, out_dir, target, *, savefun=None, append=False)`

Does the actual writing to the file.

This method is invoked by a `Snapshot` object every time it takes a snapshot.

Parameters

- **filename** (*str*) – Name of the file into which the serialized target is saved. It is a concrete file name, i.e. not a pre-formatted template string.

- **out_dir** (*str*) – Output directory. Corresponds to :py:attr:`ExtensionsManager.out` <pytorch_pfn_extras.training.ExtensionsManager.out>.
- **target** (*dict*) – Serialized object which will be saved.
- **savefun** (*callable*) – A callable that accepts a two positional arguments (an object to be serialized, file path) like *torch.save*.
- **append** (*bool*) – Mode used to open the file. True to use the append mode, False to use the write mode (truncates the file if it already exists).

Return type

None

`__init__(savefun=<function save>, fs=None, out_dir='', task=None)`**Parameters**

- **savefun** (*Callable[[...], None]*) –
- **fs** (*Optional[Any]*) –
- **out_dir** (*str*) –
- **task** (*Optional[Callable[[...], None]]*) –

Return type

None

`consume(q)`**Parameters**`q(queue.Queue[_QueUnit]) –`**Return type**

None

`create_consumer(q)`**Parameters**`q(queue.Queue[_QueUnit]) –`**Return type**`_Worker``create_queue()`**Return type**`queue.Queue[_QueUnit]``create_task(savefun)`**Parameters**`savefun (Callable[[...], None]) –`**Return type**`Callable[[...], None]``finalize()`

Finalizes the writer.

Calling this method on already-finalized Writer does nothing.

Return type

None

[pytorch_pfn_extras.writing.SimpleWriter](#)

```
class pytorch_pfn_extras.writing.SimpleWriter(savefun=<function save>, fs=None, out_dir='', **kwds)
```

Bases: [Writer](#)

The most simple snapshot writer.

This class just passes the arguments to the actual saving function.

Parameters

- **savefun** (*Callable*[[...], *None*]) – Callable object. It takes three arguments: the output file path, the serialized dictionary object, and the optional keyword arguments.
- **fs** (*Any*) – FileSystem abstracting interface to implement all the operations. optional, defaults to *None*
- **out_dir** (*str*) – str. Specifies the directory this writer will use. It takes precedence over the one specified in `__call__` optional, defaults to ''
- **kwds** (*Any*) – Keyword arguments for the `savefun`.

See also:

- [pytorch_pfn_extras.training.extensions.snapshot\(\)](#)

Methods

```
__init__([savefun, fs, out_dir])
```

```
finalize() Finalizes the writer.  
initialize(out_dir)
```

```
save(filename, out_dir, target, savefun, ...)
```

```
__call__(filename, out_dir, target, *, savefun=None, append=False)
```

Does the actual writing to the file.

This method is invoked by a `Snapshot` object every time it takes a snapshot.

Parameters

- **filename** (*str*) – Name of the file into which the serialized target is saved. It is a concrete file name, i.e. not a pre-formatted template string.
- **out_dir** (*str*) – Output directory. Corresponds to :py:attr:`ExtensionsManager.out` <[pytorch_pfn_extras.training.ExtensionsManager.out](#)>.
- **target** (*dict*) – Serialized object which will be saved.
- **savefun** (*callable*) – A callable that accepts a two positional arguments (an object to be serialized, file path) like `torch.save`.
- **append** (*bool*) – Mode used to open the file. True to use the append mode, False to use the write mode (truncates the file if it already exists).

Return type

None

`__init__(savefun=<function save>, fs=None, out_dir='', **kwds)`

Parameters

- **savefun** (`Callable[[...], None]`) –
- **fs** (`Optional[Any]`) –
- **out_dir** (`str`) –
- **kwds** (`Any`) –

Return type`None`**pytorch_pfn_extras.writing.StandardWriter**

```
class pytorch_pfn_extras.writing.StandardWriter(savefun=<function save>, fs=None, out_dir='', **kwds)
```

Bases: `Writer`, `Generic[_Worker]`

Base class of snapshot writers which use thread or process.

This class creates a new thread or a process every time when `__call__` is invoked.

Parameters

- **savefun** – Callable object. It takes three arguments: the output file path, the serialized dictionary object, and the optional keyword arguments.
- **fs** – FileSystem abstracting interface to implement all the operations. optional, defaults to `None`
- **out_dir** – str. Specifies the directory this writer will use. It takes precedence over the one specified in `__call__` optional, defaults to ''
- **kwds** – Keyword arguments for the `savefun`.

See also:

- `pytorch_pfn_extras.training.extensions.snapshot()`

Methods

`__init__([savefun, fs, out_dir])`

<code>create_worker(filename, out_dir, target, *)</code>	Creates a worker for the snapshot.
--	------------------------------------

<code>finalize()</code>	Finalizes the writer.
-------------------------	-----------------------

<code>initialize(out_dir)</code>	
----------------------------------	--

<code>save(filename, out_dir, target, savefun, ...)</code>	
--	--

`__call__(filename, out_dir, target, *, savefun=None, append=False)`

Does the actual writing to the file.

This method is invoked by a `Snapshot` object every time it takes a snapshot.

Parameters

- **filename** (*str*) – Name of the file into which the serialized target is saved. It is a concrete file name, i.e. not a pre-formatted template string.
- **out_dir** (*str*) – Output directory. Corresponds to :py:attr:`ExtensionsManager.out` <pytorch_pfn_extras.training.ExtensionsManager.out>`.
- **target** (*dict*) – Serialized object which will be saved.
- **savefun** (*callable*) – A callable that accepts a two positional arguments (an object to be serialized, file path) like *torch.save*.
- **append** (*bool*) – Mode used to open the file. True to use the append mode, False to use the write mode (truncates the file if it already exists).

Return type

None

`__init__(savefun=<function save>, fs=None, out_dir='', **kwds)`

Parameters

- **savefun** (*Callable[[...], None]*) –
- **fs** (*Optional[Any]*) –
- **out_dir** (*str*) –
- **kwds** (*Any*) –

Return type

None

`create_worker(filename, out_dir, target, *, savefun=None, append=False, **savefun_kwargs)`

Creates a worker for the snapshot.

This method creates a thread or a process to take a snapshot. The created worker must have `start()` and `join()` methods. If the worker has an `exitcode` attribute (e.g., `multiprocessing.Process`), the value will be tested.

Parameters

- **filename** (*str*) –
- **out_dir** (*str*) –
- **target** (*Union[Sequence[Any], Mapping[str, Any]]*) –
- **savefun** (*Optional[Callable[[...], None]]*) –
- **append** (*bool*) –
- **savefun_kwargs** (*Any*) –

Return type

`_Worker`

`finalize()`

Finalizes the writer.

Calling this method on already-finalized Writer does nothing.

Return type

None

pytorch_pfn_extras.writing.TensorBoardWriter

```
class pytorch_pfn_extras.writing.TensorBoardWriter(savefun=None, fs=None, out_dir='', stats=None, **kwds)
```

Bases: `object`

Writer that sends statistics to TensorBoard.

This class contains a `torch.utils.tensorboard.SummaryWriter` object that is used to send the collected statistics to TensorBoard. A list of stats can be specified to report only the desired ones.

Parameters

- `savefun` (`Optional[Callable[..., None]]`) – Ignored.
- `fs` (`Any`) – Ignored.
- `out_dir` (`str`) – Passed as `log_dir` argument to `SummaryWriter`.
- `stats` (`list`) – List of statistic keys.
- `kwds` (`Any`) – Passed as an additional arguments to `SummaryWriter`.

Methods

```
__init__([savefun, fs, out_dir, stats])
```

```
finalize()
```

```
__call__(filename, out_dir, target, *, savefun=None, append=False)
```

Sends the statistics to the TensorBoard.

Parameters

- `filename` (`str`) – Ignored.
- `out_dir` (`str`) – Ignored.
- `target` (`dict or list`) – The statistics of the iteration. If given as a list, only the last element (assumed to be a dict containing the latest iteration statistics) is reported.
- `savefun` (`Optional[Callable[..., None]]`) – Ignored.
- `append` (`bool`) – Ignored.

Return type

`None`

```
__init__(savefun=None, fs=None, out_dir='', stats=None, **kwds)
```

Parameters

- `savefun` (`Optional[Callable[..., None]]`) –
- `fs` (`Optional[Any]`) –
- `out_dir` (`str`) –
- `stats` (`Optional[KeysView[str]]`) –
- `kwds` (`Any`) –

Return type

None

finalize()

Return type

None

pytorch_pfn_extras.writing.ThreadQueueWriter

```
class pytorch_pfn_extras.writing.ThreadQueueWriter(savefun=<function save>, fs=None, out_dir='', task=None)
```

Bases: *QueueWriter*[Thread]

Snapshot writer that uses a thread queue.

This class creates a thread and a queue by `threading` and `queue` modules respectively. The thread will be a consumer of the queue, and the main thread will be a producer of the queue.

See also:

- [`pytorch_pfn_extras.training.extensions.snapshot\(\)`](#)

Methods

`__init__([savefun, fs, out_dir, task])`

`consume(q)`

`create_consumer(q)`

`create_queue()`

`create_task(savefun)`

`finalize()` Finalizes the writer.
`initialize(out_dir)`

`save(filename, out_dir, target, savefun, ...)`

`__init__(savefun=<function save>, fs=None, out_dir='', task=None)`

Parameters

- **savefun** (`Callable[[...], None]`) –
- **fs** (`Optional[Any]`) –
- **out_dir** (`str`) –
- **task** (`Optional[Callable[[...], None]]`) –

Return type

None

```
create_consumer(q)

Parameters
q (queue.Queue[_QueUnit]) –
Return type
Thread

create_queue()

Return type
queue.Queue[_QueUnit]
```

pytorch_pfn_extras.writing.ThreadWriter

```
class pytorch_pfn_extras.writing.ThreadWriter(savefun=<function save>, fs=None, out_dir='', **kwds)
Bases: StandardWriter[Thread]
```

Snapshot writer that uses a separate thread.

This class creates a new thread that invokes the actual saving function.

See also:

- [pytorch_pfn_extras.training.extensions.snapshot\(\)](#)

Methods

```
__init__([savefun, fs, out_dir])
```

```
create_worker(filename, out_dir, target, *)
```

Creates a worker for the snapshot.

```
finalize()
```

Finalizes the writer.

```
initialize(out_dir)
```

```
save(filename, out_dir, target, savefun, ...)
```

```
__init__(savefun=<function save>, fs=None, out_dir='', **kwds)
```

Parameters

- **savefun** (*Callable*[...], *None*) –
- **fs** (*Optional[Any]*) –
- **out_dir** (*str*) –
- **kwds** (*Any*) –

Return type

None

```
create_worker(filename, out_dir, target, *, savefun=None, append=False, **savefun_kwargs)
```

Creates a worker for the snapshot.

This method creates a thread or a process to take a snapshot. The created worker must have `start()` and `join()` methods. If the worker has an `exitcode` attribute (e.g., `multiprocessing.Process`), the value will be tested.

Parameters

- **filename** (*str*) –
- **out_dir** (*str*) –
- **target** (*Union[Sequence[Any], Mapping[str, Any]]*) –
- **savefun** (*Optional[Callable[..., None]]*) –
- **append** (*bool*) –
- **savefun_kwargs** (*Any*) –

Return type

Thread

[pytorch_pfn_extras.writing.Writer](#)

```
class pytorch_pfn_extras.writing.Writer(fs=None, out_dir='')
```

Bases: *object*

Base class of snapshot writers.

Snapshot invokes `__call__` of this class every time when taking a snapshot. This class determines how the actual saving function will be invoked.

Note: This extension first writes the serialized object to a temporary file and then rename it to the target file name. Thus, if the program stops right before the renaming, the temporary file might be left in the output directory.

See also:

- [pytorch_pfn_extras.training.extensions.snapshot\(\)](#)

Methods

`__init__([fs, out_dir])`

`finalize()` Finalizes the writer.

`initialize(out_dir)`

`save(filename, out_dir, target, savefun, ...)`

Parameters

- **fs** (*Any*) –
- **out_dir** (*str*) –

`__call__(filename, out_dir, target, *, savefun=None, append=False)`

Does the actual writing to the file.

This method is invoked by a `Snapshot` object every time it takes a snapshot.

Parameters

- **filename** (*str*) – Name of the file into which the serialized target is saved. It is a concrete file name, i.e. not a pre-formatted template string.
- **out_dir** (*str*) – Output directory. Corresponds to :py:attr:`ExtensionsManager.out` <pytorch_pfn_extras.training.ExtensionsManager.out>`.
- **target** (*dict*) – Serialized object which will be saved.
- **savefun** (*callable*) – A callable that accepts a two positional arguments (an object to be serialized, file path) like *torch.save*.
- **append** (*bool*) – Mode used to open the file. True to use the append mode, False to use the write mode (truncates the file if it already exists).

Return type

None

__init__(fs=None, out_dir= '')**Parameters**

- **fs** (*Optional[Any]*) –
- **out_dir** (*str*) –

Return type

None

finalize()

Finalizes the writer.

Calling this method on already-finalized Writer does nothing.

Return type

None

initialize(out_dir)**Parameters****out_dir** (*str*) –**Return type**

None

save(filename, out_dir, target, savefun, append, **savefun_kwargs)**Parameters**

- **filename** (*str*) –
- **out_dir** (*str*) –
- **target** (*Union[Sequence[Any], Mapping[str, Any]]*) –
- **savefun** (*Callable[..., None]*) –
- **append** (*bool*) –
- **savefun_kwargs** (*Any*) –

Return type

None

2.2 Training Loop

2.2.1 Trainer

<code>engine.create_trainer(models, optimizers, ...)</code>	Creates a trainer object.
<code>engine.create_evaluator(models, *[...,])</code>	Creates an evaluator object.
<code>handler.BaseLogic([options])</code>	
<code>handler.Logic([model_name, options])</code>	A set of methods that defines the training logic.
<code>handler.BaseHandler(logic, options, *args, ...)</code>	Base class of Handler.
<code>handler.Handler(logic, entry_runtime, options)</code>	A set of callback functions to perform device-specific operations.
<code>runtime.BaseRuntime(device_spec, options)</code>	A base class for collections of device-specific callback functions.
<code>runtime.PyTorchRuntime(device_spec, options)</code>	A collections of callback functions for the devices that PyTorch supports by default.

2.2.2 Extensions Manager

<code>training.ExtensionsManager(models, ..., ...)</code>	Manages the extensions and the current status.
<code>training.IgniteExtensionsManager(engine, ...)</code>	Manages extensions and the current status in Ignite training loop.

2.2.3 Extensions

<code>training.extension.make_extension([trigger, ...])</code>	Decorator to make given function into an extension.
<code>training.extension.Extension()</code>	Base class of extensions.
<code>training.extension.ExtensionEntry(extension, *)</code>	Extension and options.

<code>training.extensions.BestValue(key, compare)</code>	Extension traces the best value of a specific key in the observation.
<code>training.extensions.Evaluator(self, ..., ...)</code>	An extension to evaluate models on a validation set.
<code>training.extensions.LogReport([keys, ...])</code>	An extension to output the accumulated results to a log file.
<code>training.extensions.MaxValue(key[, trigger])</code>	Extension traces the maximum value of a specific key in the observation.
<code>training.extensions.MicroAverage(...[, trigger])</code>	Calculates micro-average ratio.
<code>training.extensions.MinValue(key[, trigger])</code>	Extension traces the minimum value of a specific key in the observation.
<code>training.extensions.observe_lr(optimizer[, ...])</code>	Returns an extension to record the learning rate.
<code>training.extensions.observe_value(...)</code>	Returns an extension to continuously record a value.
<code>training.extensions.ParameterStatistics(links)</code>	An extension to report parameter statistics.
<code>training.extensions.PlotReport(y_keys[, ...])</code>	An extension to output plots.
<code>training.extensions.PrintReport([entries, ...])</code>	An extension to print the accumulated results.
<code>training.extensions.ProgressBar([...])</code>	An extension to print a progress bar and recent training status.
<code>training.extensions.ProfileReport([...])</code>	Writes the profile results to a file.
<code>training.extensions.snapshot([savefun, ...])</code>	Returns a trainer extension to take snapshots of the trainer.
<code>training.extensions.Slack(channel[, msg, ...])</code>	An extension to communicate with Slack.
<code>training.extensions.SlackWebhook(url[, msg, ...])</code>	An extension to communicate with Slack using Incoming Webhook.
<code>training.extensions.VariableStatisticsPlot(targets)</code>	An extension to plot statistics for Tensors.

2.2.4 Triggers

<code>training.triggers.EarlyStoppingTrigger(self)</code>	Trigger for Early Stopping
<code>training.triggers.IntervalTrigger(period, unit)</code>	Trigger based on a fixed interval.
<code>training.triggers.ManualScheduleTrigger(...)</code>	Trigger invoked at specified point(s) of iterations or epochs.
<code>training.triggers.BestValueTrigger(key, compare)</code>	Trigger invoked when specific value becomes best.
<code>training.triggers.MaxValueTrigger(key[, trigger])</code>	Trigger invoked when specific value becomes maximum.
<code>training.triggers.MinValueTrigger(key[, trigger])</code>	Trigger invoked when specific value becomes minimum.
<code>training.triggers.OnceTrigger([call_on_resume])</code>	Trigger based on the starting point of the iteration.
<code>training.triggers.TimeTrigger(period)</code>	Trigger based on a fixed time interval.

2.2.5 Reporting

<code>reporting.Reporter()</code>	Object to which observed values are reported.
<code>reporting.report(values[, observer])</code>	Reports observed values with the current reporter object.
<code>reporting.report_scope(observation)</code>	Returns a report scope with the current reporter.

2.2.6 Logging

<code>logging.get_logger(name)</code>	Returns a child logger to be used by applications.
---------------------------------------	--

2.2.7 Profiler

<code>profiler.TimeSummary.report(tag[, use_cuda])</code>	Context manager to automatically report execution times.
---	--

2.3 Distributed Training

<code>nn.parallel.DistributedDataParallel(module)</code>	Module for distributed data parallelism
<code>distributed.initialize_ompi_environment(*[...])</code>	Initialize <code>torch.distributed</code> environments with values taken from OpenMPI.

2.4 Check Pointing

<code>utils.checkpoint</code>	
-------------------------------	--

2.5 Lazy Modules

<code>nn.Ensure(*[shape, dtype, broadcastable, ...])</code>	Module to check the shape of a tensor.
<code>nn.ensure(tensor[, shape, dtype, ...])</code>	Checks the shape and type of a tensor.
<code>nn.LazyLinear(in_features, *args, **kwargs)</code>	Linear module with lazy weight initialization.
<code>nn.LazyConv1d(in_channels, *args, **kwargs)</code>	Conv1d module with lazy weight initialization.
<code>nn.LazyConv2d(in_channels, *args, **kwargs)</code>	Conv2d module with lazy weight initialization.
<code>nn.LazyConv3d(in_channels, *args, **kwargs)</code>	Conv3d module with lazy weight initialization.
<code>nn.LazyBatchNorm1d(num_features, *args, **kwargs)</code>	BatchNorm1d module with lazy weight initialization.
<code>nn.LazyBatchNorm2d(num_features, *args, **kwargs)</code>	BatchNorm2d module with lazy weight initialization.
<code>nn.LazyBatchNorm3d(num_features, *args, **kwargs)</code>	BatchNorm3d module with lazy weight initialization.

2.6 ONNX

2.6.1 Export

<code>onnx.export(model, args, f[, return_output, ...])</code>	Export model into ONNX Graph.
<code>onnx.export_testcase(model, args, out_dir, *)</code>	Export model and I/O tensors of the model in protobuf format.

2.6.2 Annotation

<code>onnx.annotate(**attrs)</code>	Annotation parameters to the target function.
<code>onnx.apply_annotation(fn, *args, **attrs)</code>	Annotation applier to the target function
<code>onnx.scoped_anchor(**attrs)</code>	Add anchor node to the scoped modules
<code>onnx.export(model, args, f[, return_output, ...])</code>	Export model into ONNX Graph.
<code>onnx.export_testcase(model, args, out_dir, *)</code>	Export model and I/O tensors of the model in protobuf format.

2.7 Datasets

<code>dataset.SharedDataset(sm_size[, cache_type])</code>	Dataset that caches the load samples in shared memory
<code>dataset.TabularDataset(*args, **kwds)</code>	An abstract class that represents tabular dataset.
<code>dataset.ItemNotFoundException</code>	

2.8 Config

<code>config.Config(config[, types])</code>	
<code>config_types.optuna_types(trial)</code>	
<code>config_types.load_path_with_optuna_types(...)</code>	

2.9 NumPy/CuPy Compatibility

<code>from_ndarray(ndarray)</code>	Creates a <code>torch.Tensor</code> from a <code>numpy.ndarray</code> or <code>cupy.ndarray</code> .
<code>as_ndarray(tensor)</code>	Creates a <code>numpy.ndarray</code> or <code>cupy.ndarray</code> from <code>torch.Tensor</code> .
<code>get_xp(obj)</code>	Returns a module of ndarray implementation (<code>numpy</code> or <code>cupy</code>) for the given <code>obj</code> .
<code>as_numpy_dtype(torch_dtype)</code>	Returns NumPy dtype for the given PyTorch dtype.
<code>from_numpy_dtype(numpy_dtype)</code>	Returns PyTorch dtype for the given NumPy dtype.

<code>cuda.stream(stream)</code>	Context-manager that selects a given stream.
<code>cuda.use_torch_mempool_in_cupy()</code>	Use the PyTorch memory pool in CuPy.
<code>cuda.use_default_mempool_in_cupy()</code>	Use the default memory pool in CuPy.

PYTHON MODULE INDEX

p

pytorch_pfn_extras, 37
pytorch_pfn_extras.config, 41
pytorch_pfn_extras.config_types, 43
pytorch_pfn_extras.cuda, 44
pytorch_pfn_extras.dataloaders, 45
pytorch_pfn_extras.dataloaders.dataloader, 48
pytorch_pfn_extras.dataloaders.utils, 54
pytorch_pfn_extras.dataset, 55
pytorch_pfn_extras.dataset.shared_dataset, 61
pytorch_pfn_extras.dataset.tabular, 63
pytorch_pfn_extras.dataset.tabular.delegate_dataset, 66
pytorch_pfn_extras.dataset.tabular.tabular_dataset, 68
pytorch_pfn_extras.distributed, 73
pytorch_pfn_extras.engine, 75
pytorch_pfn_extras.handler, 79
pytorch_pfn_extras.logging, 99
pytorch_pfn_extras.nn, 99
pytorch_pfn_extras.nn.modules, 123
pytorch_pfn_extras.nn.modules.ensure_shape, 123
pytorch_pfn_extras.nn.modules.extended_sequential, 127
pytorch_pfn_extras.nn.modules.lazy, 130
pytorch_pfn_extras.nn.modules.lazy_batchnorm, 149
pytorch_pfn_extras.nn.modules.lazy_conv, 176
pytorch_pfn_extras.nn.modules.lazy_linear, 204
pytorch_pfn_extras.nn.parallel, 226
pytorch_pfn_extras.nn.parallel.distributed, 231
pytorch_pfn_extras.onnx, 242
pytorch_pfn_extras.onnx.load, 247
pytorch_pfn_extras.onnx.pfto_exporter, 256
pytorch_pfn_extras.onnx.strip_large_tensor, 256
pytorch_pfn_extras.onnx.symbolic_registry, 257
pytorch_pfn_extras.onnx.unstrip_tensor, 257
pytorch_pfn_extras.profiler, 262
pytorch_pfn_extras.reporting, 266
pytorch_pfn_extras.runtime, 273
pytorch_pfn_extras.testing, 283
pytorch_pfn_extras.torchscript, 283
pytorch_pfn_extras.training, 284
pytorch_pfn_extras.training.extension, 302
pytorch_pfn_extras.training.extensions, 308
pytorch_pfn_extras.training.extensions.best_value, 354
pytorch_pfn_extras.training.extensions.evaluator, 361
pytorch_pfn_extras.training.extensions.fail_on_non_number, 372
pytorch_pfn_extras.training.extensions.log_report, 375
pytorch_pfn_extras.training.extensions.lr_scheduler, 381
pytorch_pfn_extras.training.extensions.micro_average, 387
pytorch_pfn_extras.training.extensions.parameter_statistics, 391
pytorch_pfn_extras.training.extensions.plot_report, 396
pytorch_pfn_extras.training.extensions.print_report, 401
pytorch_pfn_extras.training.extensions.profile_report, 409
pytorch_pfn_extras.training.extensions.progress_bar, 416
pytorch_pfn_extras.training.extensions.slack, 420
pytorch_pfn_extras.training.extensions.snapshot_writers, 427
pytorch_pfn_extras.training.extensions.util, 441
pytorch_pfn_extras.training.extensions.value_observation, 446
pytorch_pfn_extras.training.extensions.variable_statistics, 449
pytorch_pfn_extras.training.manager, 457
pytorch_pfn_extras.training.metrics, 458

pytorch_pfn_extras.training.trigger, 459
pytorch_pfn_extras.training.triggers, 462
pytorch_pfn_extras.training.triggers.early_stopping_trigger,
 472
pytorch_pfn_extras.training.triggers.interval_trigger,
 476
pytorch_pfn_extras.training.triggers.manual_schedule_trigger,
 479
pytorch_pfn_extras.training.triggers.minmax_value_trigger,
 482
pytorch_pfn_extras.training.triggers.once_trigger,
 487
pytorch_pfn_extras.training.triggers.time_trigger,
 491
pytorch_pfn_extras.utils, 494
pytorch_pfn_extras.utils.checkpoint, 494
pytorch_pfn_extras.utils.comparer, 494
pytorch_pfn_extras.writing, 500

INDEX

Symbols

__call__(pytorch_pfn_extras.dataloaders.utils.CollateAsDict method), 55
__call__(pytorch_pfn_extras.handler.CodeBlock method), 89
__call__(pytorch_pfn_extras.training.AccuracyMetric method), 285
__call__(pytorch_pfn_extras.training.Extension method), 288
__call__(pytorch_pfn_extras.training.extension.Extension method), 304
__call__(pytorch_pfn_extras.training.extensions.BestValue method), 313
__call__(pytorch_pfn_extras.training.extensions.Evaluator method), 318
__call__(pytorch_pfn_extras.training.extensions.FailOnNonNumber method), 321
__call__(pytorch_pfn_extras.training.extensions.LRScheduler method), 324
__call__(pytorch_pfn_extras.training.extensions.LogReport method), 327
__call__(pytorch_pfn_extras.training.extensions.MicroAverage method), 330
__call__(pytorch_pfn_extras.training.extensions.ParameterStatistics method), 334
__call__(pytorch_pfn_extras.training.extensions.PlotReport method), 337
__call__(pytorch_pfn_extras.training.extensions.PrintReport method), 339
__call__(pytorch_pfn_extras.training.extensions.ProfileReport method), 342
__call__(pytorch_pfn_extras.training.extensions.ProgressBar method), 344
__call__(pytorch_pfn_extras.training.extensions.VariableStatistics method), 351
__call__(pytorch_pfn_extras.training.extensions.best_value.BestValue method), 355
__call__(pytorch_pfn_extras.training.extensions.evaluator.Evaluator method), 365
__call__(pytorch_pfn_extras.training.extensions.fail_on_non_number.FailOnNonNumber method), 375
__call__(pytorch_pfn_extras.training.extensions.log_report.LogReport method), 379
__call__(pytorch_pfn_extras.training.extensions.log_report.LogWriter method), 380
__call__(pytorch_pfn_extras.training.extensions.lr_scheduler.LRSched method), 384
__call__(pytorch_pfn_extras.training.extensions.micro_average.Micro method), 390
__call__(pytorch_pfn_extras.training.extensions.parameter_statistics.P method), 395
__call__(pytorch_pfn_extras.training.extensions.plot_report.PlotReport method), 399
__call__(pytorch_pfn_extras.training.extensions.print_report.PrintRep method), 408
__call__(pytorch_pfn_extras.training.extensions.profile_report.Profile method), 414
__call__(pytorch_pfn_extras.training.extensions.progress_bar.Progress method), 419
__call__(pytorch_pfn_extras.training.extensions.snapshot_writers.Que method), 431
__call__(pytorch_pfn_extras.training.extensions.snapshot_writers.Simple method), 433
__call__(pytorch_pfn_extras.training.extensions.snapshot_writers.Standard method), 434
__call__(pytorch_pfn_extras.training.extensions.snapshot_writers.Tensors method), 436
__call__(pytorch_pfn_extras.training.extensions.snapshot_writers.Writer method), 439
__call__(pytorch_pfn_extras.training.extensions.variable_statistics_pl method), 453
__call__(pytorch_pfn_extras.training.extensions.variable_statistics_pl method), 456
__call__(pytorch_pfn_extras.training.extensions.metrics.AccuracyMetric method), 458
__call__(pytorch_pfn_extras.training.trigger.IntervalTrigger method), 460
__call__(pytorch_pfn_extras.training.trigger.Trigger method), 461
__call__(pytorch_pfn_extras.training.triggers.BestValueTrigger method), 463
__call__(pytorch_pfn_extras.training.triggers.EarlyStoppingTrigger method), 464
__call__(pytorch_pfn_extras.training.triggers.IntervalTrigger method), 465

method), 466
__call__(pytorch_pfn_extras.training.triggers.ManualScheduleTrigger (pytorch_pfn_extras.handler.CodeBlock
 method), 467
__call__(pytorch_pfn_extras.training.triggers.OnceTriggerinit__(pytorch_pfn_extras.handler.CodeBlockLogic
 method), 470
__call__(pytorch_pfn_extras.training.triggers.TimeTriggerinit__(pytorch_pfn_extras.handler.Handler
 method), 471
__call__(pytorch_pfn_extras.training.triggers.early_stopping_trigger(EarlyStoppingTriggerHandler.Logic
 method), 473
__call__(pytorch_pfn_extras.training.triggers.interval_trigger(IntervalTriggerHandler.nn.Ensure
 method), 478
__call__(pytorch_pfn_extras.training.triggers.manual_schedule_trigger.ManualScheduleTrigger(nn.LazyLinear
 method), 481
__call__(pytorch_pfn_extras.training.triggers.minmax_value_trigger(BatchNLLupTriggerHandler.nn.modules.ensure_shape.Ensure
 method), 483
__call__(pytorch_pfn_extras.training.triggers.once_triggerOnceTrigger(pytorch_pfn_extras.nn.modules.extended_sequential.TypeVar
 method), 490
__call__(pytorch_pfn_extras.training.triggers.time_triggerTimeTrigger(pytorch_pfn_extras.nn.modules.lazy.LazyInitializationMixin
 method), 493
__call__(pytorch_pfn_extras.writing.QueueWriter __init__(pytorch_pfn_extras.nn.modules.lazy_batchnorm.LazyInitialization
 method), 504
__call__(pytorch_pfn_extras.writing.SimpleWriter __init__(pytorch_pfn_extras.nn.modules.lazy_conv.LazyInitializationM
 method), 506
__call__(pytorch_pfn_extras.writing.StandardWriter __init__(pytorch_pfn_extras.nn.modules.lazy_linear.LazyInitialization
 method), 507
__call__(pytorch_pfn_extras.writing.TensorBoardWriter __init__(pytorch_pfn_extras.nn.modules.lazy_linear.LazyLinear
 method), 509
__call__(pytorch_pfn_extras.writing.Writer __init__(pytorch_pfn_extras.nn.parallel.DistributedDataParallel
 method), 512
__init__(pytorch_pfn_extras.config.Config method), __init__(pytorch_pfn_extras.nn.parallel.distributed.DistributedDataPar
 42
__init__(pytorch_pfn_extras.dataloaders.DataLoader __init__(pytorch_pfn_extras.nn.parallel.distributed.OrderedDict
 method), 47
__init__(pytorch_pfn_extras.dataloaders.dataloader.DataLoader __init__(pytorch_pfn_extras.nn.parallel.distributed.TypeVar
 method), 53
__init__(pytorch_pfn_extras.dataloaders.utils.CollateAsDistributed __init__(pytorch_pfn_extras.nn.parallel.distributed.record_function
 method), 55
__init__(pytorch_pfn_extras.dataset.SharedDataset __init__(pytorch_pfn_extras.profiler.TimeSummary
 method), 56
__init__(pytorch_pfn_extras.dataset.shared_dataset.InfiniteBatch __init__(pytorch_pfn_extras.reporting.DictSummary
 method), 62
__init__(pytorch_pfn_extras.dataset.shared_dataset.SharedDataset __init__(pytorch_pfn_extras.reporting.Reporter
 method), 62
__init__(pytorch_pfn_extras.dataset.tabular.DelegateDataset __init__(pytorch_pfn_extras.reporting.Summary
 method), 65
__init__(pytorch_pfn_extras.dataset.tabular.delegate_delegate_delegate_delegate_delegate_delegate_delegate_delegate_delegate
 method), 67
__init__(pytorch_pfn_extras.distributed.DistributedValidator __init__(PyTorchRuntime
 method), 74
__init__(pytorch_pfn_extras.engine.StateObjectProtocol __init__(pytorch_pfn_extras.training.AccuracyMetric
 method), 79
__init__(pytorch_pfn_extras.handler.BaseHandler __init__(pytorch_pfn_extras.training.DistributedEvaluator
 method), 81
__init__(pytorch_pfn_extras.handler.BaseLogic __init__(pytorch_pfn_extras.training.Evaluator
 method), 85
 method), 89
 method), 91
 method), 93
 method), 97
 method), 102
 method), 122
 method), 126
 method), 130
 method), 131
 method), 158
 method), 186
 method), 205
 method), 208
 method), 229
 method), 235
 method), 238
 method), 240
 method), 241
 method), 264
 method), 268
 method), 270
 method), 272
 method), 274
 method), 279
 method), 285
 method), 286
 method), 286

`method), 287`
`__init__(pytorch_pfn_extras.training.ExtensionEntry method), 290`
`__init__(pytorch_pfn_extras.training.ExtensionsManager method), 292`
`__init__(pytorch_pfn_extras.training.ExtensionsManagerProtocol method), 294`
`__init__(pytorch_pfn_extras.training.IgniteExtensionsMain method), 296`
`__init__(pytorch_pfn_extras.training.StateObjectProtocol method), 297`
`__init__(pytorch_pfn_extras.training.Trainer method), 299`
`__init__(pytorch_pfn_extras.training.extension.ExtensionEntry method), 306`
`__init__(pytorch_pfn_extras.training.extension.ExtensionManager method), 307`
`__init__(pytorch_pfn_extras.training.extensions.BestValue method), 314`
`__init__(pytorch_pfn_extras.training.extensions.DistributedEvaluator method), 316`
`__init__(pytorch_pfn_extras.training.extensions.Evaluator method), 318`
`__init__(pytorch_pfn_extras.training.extensions.FailOnNonNumber method), 321`
`__init__(pytorch_pfn_extras.training.extensions.IgniteEvaluator method), 322`
`__init__(pytorch_pfn_extras.training.extensions.LRScheduler method), 324`
`__init__(pytorch_pfn_extras.training.extensions.LogReport method), 327`
`__init__(pytorch_pfn_extras.training.extensions.MaxValue method), 329`
`__init__(pytorch_pfn_extras.training.extensions.MicroAverage method), 331`
`__init__(pytorch_pfn_extras.training.extensions.MinValue method), 332`
`__init__(pytorch_pfn_extras.training.extensions.ParameterStatistics method), 334`
`__init__(pytorch_pfn_extras.training.extensions.PlotReport method), 337`
`__init__(pytorch_pfn_extras.training.extensions.PrintReport method), 339`
`__init__(pytorch_pfn_extras.training.extensions.ProfileReport method), 342`
`__init__(pytorch_pfn_extras.training.extensions.ProgressBar method), 344`
`__init__(pytorch_pfn_extras.training.extensions.Slack __init__ method), 347`
`__init__(pytorch_pfn_extras.training.extensions.SlackWebhook __init__ method), 349`
`__init__(pytorch_pfn_extras.training.extensions.VariableStatistics __init__ method), 352`
`__init__(pytorch_pfn_extras.training.extensions.best_value.BestValue __init__ method), 355`
`__init__(pytorch_pfn_extras.training.extensions.best_value.Extensions method), 357`
`__init__(pytorch_pfn_extras.training.extensions.best_value.MaxValue method), 359`
`__init__(pytorch_pfn_extras.training.extensions.best_value.MinValue method), 360`
`__init__(pytorch_pfn_extras.training.extensions.evaluator.DistributedEvaluator method), 362`
`__init__(pytorch_pfn_extras.training.extensions.evaluator.Evaluator method), 365`
`__init__(pytorch_pfn_extras.training.extensions.evaluator.ExtensionsEvaluator method), 367`
`__init__(pytorch_pfn_extras.training.extensions.evaluator.IgniteEvaluator method), 369`
`__init__(pytorch_pfn_extras.training.extensions.evaluator.IterationStateEvaluator method), 370`
`__init__(pytorch_pfn_extras.training.extensions.fail_on_non_number.FailOnNonNumber method), 373`
`__init__(pytorch_pfn_extras.training.extensions.fail_on_non_number.FailOnNonNumber method), 375`
`__init__(pytorch_pfn_extras.training.extensions.log_report.ExtensionsLogReport method), 376`
`__init__(pytorch_pfn_extras.training.extensions.log_report.LogReport method), 379`
`__init__(pytorch_pfn_extras.training.extensions.log_report.LogWriter method), 380`
`__init__(pytorch_pfn_extras.training.extensions.lr_scheduler.ExtensionsLRScheduler method), 382`
`__init__(pytorch_pfn_extras.training.extensions.lr_scheduler.LRScheduler method), 384`
`__init__(pytorch_pfn_extras.training.extensions.micro_average.ExtensionsMicroAverage method), 386`
`__init__(pytorch_pfn_extras.training.extensions.micro_average.MicroAverage method), 388`
`__init__(pytorch_pfn_extras.training.extensions.parameter_statistics.ExtensionsParameterStatistics method), 390`
`__init__(pytorch_pfn_extras.training.extensions.parameter_statistics.ParameterStatistics method), 392`
`__init__(pytorch_pfn_extras.training.extensions.parameter_statistics.ProgressBar method), 395`
`__init__(pytorch_pfn_extras.training.extensions.plot_report.ExtensionsPlotReport method), 397`
`__init__(pytorch_pfn_extras.training.extensions.plot_report.PlotReport method), 400`
`__init__(pytorch_pfn_extras.training.extensions.print_report.ExtensionsPrintReport method), 403`
`__init__(pytorch_pfn_extras.training.extensions.print_report.PrintReport method), 408`
`__init__(pytorch_pfn_extras.training.extensions.profile_report.ExtensionsProfileReport method), 411`
`__init__(pytorch_pfn_extras.training.extensions.profile_report.OrderedProfileReport method), 412`
`__init__(pytorch_pfn_extras.training.extensions.profile_report.ProfileReport method), 413`

method), 415
__init__(pytorch_pfn_extras.training.extensions.progress_bar.ExternalManagerExtraTraining.triggers.MaxValueTrigger
 method), 417
__init__(pytorch_pfn_extras.training.extensions.progress_bar.ProgressBar(pytorch_pfn_extras.training.triggers.MinValueTrigger
 method), 419
__init__(pytorch_pfn_extras.training.extensions.slack.ExtensionsManagerPropsExtraTraining.triggers.OnceTrigger
 method), 421
__init__(pytorch_pfn_extras.training.extensions.slack.SlackInit__(pytorch_pfn_extras.training.triggers.TimeTrigger
 method), 424
__init__(pytorch_pfn_extras.training.extensions.slack.SlackWebhook(pytorch_pfn_extras.training.triggers.early_stopping_trigger.Early
 method), 427
__init__(pytorch_pfn_extras.training.extensions.snapshotwriters.PytorchQueueWriterExtraTraining.triggers.early_stopping_trigger.Early
 method), 428
__init__(pytorch_pfn_extras.training.extensions.snapshotwriters.PytorchWriterExtraTraining.triggers.interval_trigger.Extensions
 method), 429
__init__(pytorch_pfn_extras.training.extensions.snapshotwriters.QueueWriterExtraTraining.triggers.interval_trigger.Interval
 method), 431
__init__(pytorch_pfn_extras.training.extensions.snapshotwriters.SimpleWriterExtraTraining.triggers.manual_schedule_trigger
 method), 433
__init__(pytorch_pfn_extras.training.extensions.snapshotwriters.StandardWriterExtraTraining.triggers.manual_schedule_trigger
 method), 435
__init__(pytorch_pfn_extras.training.extensions.snapshotwriters.TensorBoardWriterExtraTraining.triggers.minmax_value_trigger.BestValue
 method), 436
__init__(pytorch_pfn_extras.training.extensions.snapshotwriters.TensorBoardWriterExtraTraining.triggers.minmax_value_trigger.Early
 method), 437
__init__(pytorch_pfn_extras.training.extensions.snapshotwriters.TensorBoardWriterExtraTraining.triggers.minmax_value_trigger.MinValue
 method), 438
__init__(pytorch_pfn_extras.training.extensions.snapshotwriters.TensorBoardWriterExtraTraining.triggers.minmax_value_trigger.MaxValue
 method), 439
__init__(pytorch_pfn_extras.training.extensions.util.ExtensionsManagerOnceTriggerExtraTraining.triggers.once_trigger.Extensions
 method), 442
__init__(pytorch_pfn_extras.training.extensions.util.ProgressBar__(pytorch_pfn_extras.training.triggers.once_trigger.OnceTrigger
 method), 443
__init__(pytorch_pfn_extras.training.extensions.value_observer.Init__(ExtensionsManagerTraining.triggers.time_trigger.Extensions
 method), 448
__init__(pytorch_pfn_extras.training.extensions.variable_intrinsic.ExtensionsManagerTraining.triggers.time_trigger.TimeTrigger
 method), 451
__init__(pytorch_pfn_extras.training.extensions.variable_intrinsic.PytorchFlopsManagerIntrinsicComparers.comparer.Comparer
 method), 452
__init__(pytorch_pfn_extras.training.extensions.variable_intrinsic.PytorchFlopsManagerIntrinsicComparers.comparer.ModelComparer
 method), 453
__init__(pytorch_pfn_extras.training.extensions.variable_intrinsic.PytorchMathematicalStatisticsPlotComparers.OutputsComparer
 method), 456
__init__(pytorch_pfn_extras.training.metrics.AccuracyMetric__(pytorch_pfn_extras.writing.ProcessQueueWriter
 method), 458
__init__(pytorch_pfn_extras.training.trigger.IntervalTriggerInit__(pytorch_pfn_extras.writing.ProcessWriter
 method), 460
__init__(pytorch_pfn_extras.training.triggers.BestValueTrigger__(pytorch_pfn_extras.writing.QueueWriter
 method), 463
__init__(pytorch_pfn_extras.training.triggers.EarlyStoppingTrigger__(pytorch_pfn_extras.writing.SimpleWriter
 method), 465
__init__(pytorch_pfn_extras.training.triggers.IntervalTriggerInit__(pytorch_pfn_extras.writing.StandardWriter
 method), 466
__init__(pytorch_pfn_extras.training.triggers.ManualScheduleTrigger__(pytorch_pfn_extras.writing.TensorBoardWriter
 method), 467

A
`absolute()` (pytorch_pfn_extras.onnx.load.Path method), 253
`absolute()` (pytorch_pfn_extras.onnx.unstrip_tensor.Path method), 260
`AccuracyMetric` (class in pytorch_pfn_extras.training), 285
`AccuracyMetric` (class in pytorch_pfn_extras.training.metrics), 458
`add()` (pytorch_pfn_extras.profiler.TimeSummary method), 264
`add()` (pytorch_pfn_extras.reporting.DictSummary method), 268
`add()` (pytorch_pfn_extras.reporting.Summary method), 272
`add()` (pytorch_pfn_extras.training.extensions.variable_statistics_plotter method), 452
`add_dump()` (pytorch_pfn_extras.utils.comparer.Comparer method), 497
`add_engine()` (pytorch_pfn_extras.utils.comparer.Comparer method), 497
`add_metric()` (pytorch_pfn_extras.training.extensions.Evaluator method), 319
`add_metric()` (pytorch_pfn_extras.training.extensions.evaluator method), 365
`add_observer()` (pytorch_pfn_extras.reporting.Reporter method), 270
`add_observers()` (pytorch_pfn_extras.reporting.Reporter method), 270
`add_to_cache()` (pytorch_pfn_extras.dataset.shared_dataset.Cache property), 314
`add_to_cache()` (pytorch_pfn_extras.dataset.shared_dataset.InfiniteIterator property), 355
`affine` (pytorch_pfn_extras.nn.modules.lazy_batchnorm.LazyBatchNorm property), 314
`affine` (pytorch_pfn_extras.nn.modules.lazy_batchnorm.LazyBatchNorm property), 313
`affine` (pytorch_pfn_extras.nn.modules.lazy_batchnorm.LazyBatchNorm property), 354
`annotate()` (in module pytorch_pfn_extras.onnx), 242
`apply_annotation()` (in module pytorch_pfn_extras.onnx), 243
`as_ndarray()` (in module pytorch_pfn_extras), 38
`as_numpy_dtype()` (in module pytorch_pfn_extras), 38
`as_output()` (in module pytorch_pfn_extras.onnx), 243

B
`backprop` (pytorch_pfn_extras.handler.CodeBlock attribute), 89
`backprop_from` (pytorch_pfn_extras.handler.CodeBlock attribute), 90
`backprop_to` (pytorch_pfn_extras.handler.CodeBlock attribute), 90
`BaseHandler` (class in pytorch_pfn_extras.handler), 81
`BaseLogic` (class in pytorch_pfn_extras.handler), 84
`BaseRuntime` (class in pytorch_pfn_extras.runtime), 273
`batch_size` (pytorch_pfn_extras.dataloaders.DataLoader attribute), 47
`batch_size` (pytorch_pfn_extras.dataloaders.DataLoader attribute), 54
`best_epoch` (pytorch_pfn_extras.training_extensions.BestValue property), 355
`best_epoch` (pytorch_pfn_extras.training_extensions.BestValue property), 314
`best_iteration` (pytorch_pfn_extras.training_extensions.BestValue property), 355
`best_iteration` (pytorch_pfn_extras.training_extensions.BestValue property), 355
`best_value` (pytorch_pfn_extras.training_extensions.BestValue property), 354
`BestValue` (class in pytorch_pfn_extras.training_extensions.BestValue), 313
`BestValue` (class in pytorch_pfn_extras.training_extensions.BestValue), 354
`BestValueTrigger` (class in pytorch_pfn_extras.training.triggers), 462
`BestValueTrigger` (class in pytorch_pfn_extras.training.triggers.minmax_value_trigger), 482

bias (*pytorch_pfn_extras.nn.modules.lazy_conv.LazyConv1dComparer* (*class in pytorch_pfn_extras.utils.comparer*), *attribute*), 179
bias (*pytorch_pfn_extras.nn.modules.lazy_conv.LazyConv2dCompiler* (*in module pytorch_pfn_extras*), 38
 attribute), 182
 complete_report() (py-
bias (*pytorch_pfn_extras.nn.modules.lazy_conv.LazyConv3d* *attribute*), 185
 method), 265
buffer (*pytorch_pfn_extras.training.extensions.evaluator.TextIO* *property*), 372
buffer (*pytorch_pfn_extras.training.extensions.util.TextIO* *compute_mean()* (*pytorch_pfn_extras.reporting.DictSummary method*), 268
 property), 446
concat () (*pytorch_pfn_extras.dataset.tabular.tabular_dataset.TabularDataset* *method*), 272
C
Cache (*class in pytorch_pfn_extras.dataset.shared_dataset*), concat () (*pytorch_pfn_extras.dataset.TabularDataset* *method*), 58
cache_item () (*pytorch_pfn_extras.dataset.shared_dataset.SharedDataset* *method*), 62
 Config (*class in pytorch_pfn_extras.config*), 42
 consume() (*pytorch_pfn_extras.training.extensions.snapshot_writers.QueueWriter* *method*), 431
cache_item () (*pytorch_pfn_extras.dataset.SharedDataset* *method*), 56
consume () (*pytorch_pfn_extras.writing.QueueWriter* *method*), 505
cast () (*in module pytorch_pfn_extras.engine*), 75
check_worker_number_rationality () (*py-
 torch_pfn_extras.dataloaders.DataLoader* *method*), 48
 method), 48
check_worker_number_rationality () (*py-
 torch_pfn_extras.dataloaders.dataloader.DataLoader* *method*), 54
checkpoint () (*in module torch_pfn_extras.utils.checkpoint*), 494
chmod () (*pytorch_pfn_extras.onnx.load.Path* *method*), 253
chmod () (*pytorch_pfn_extras.onnx.unstrip_tensor.Path* *method*), 260
clear () (*pytorch_pfn_extras.nn.parallel.distributed.OrderedDict* *method*), 238
clear () (*pytorch_pfn_extras.training.extensions.profile_report.OrderedDict* *method*), 412
close () (*pytorch_pfn_extras.onnx.load.IO* *method*), 249
close () (*pytorch_pfn_extras.training.extensions.print_report.IO* *method*), 405
close () (*pytorch_pfn_extras.training.extensions.util.ProgressBar* *method*), 443
closed (*pytorch_pfn_extras.onnx.load.IO* *property*), 249
closed (*pytorch_pfn_extras.training.extensions.print_report.IO* *property*), 405
ClosureLogic (*class in pytorch_pfn_extras.handler*), 87
CodeBlockLogic (*class in pytorch_pfn_extras.handler*), 88
CodeBlockLogic (*class in pytorch_pfn_extras.handler*), 90
CollateAsDict (*class in torch_pfn_extras.dataloaders.utils*), 54
collect () (*pytorch_pfn_extras.training.extensions.variable_statistics_processor* *method*), 454
compare () (*pytorch_pfn_extras.utils.comparer.Comparer* *method*), 497
concat () (*pytorch_pfn_extras.dataset.TabularDataset* *method*), 93
consume_options () (*pytorch_pfn_extras.handler.Handler* *method*), 97
consume_options () (*pytorch_pfn_extras.handler.Logic* *method*), 97
consume_options () (*pytorch_pfn_extras.handler.ClosureLogic* *method*), 87
consume_options () (*pytorch_pfn_extras.handler.CodeBlockLogic* *method*), 91
consume_options () (*pytorch_pfn_extras.handler.Handler* *method*), 232
convert () (*pytorch_pfn_extras.dataset.tabular.tabular_dataset.TabularDataset* *method*), 70
convert () (*pytorch_pfn_extras.dataset.TabularDataset* *method*), 58
convert_batch () (*py-
 torch_pfn_extras.runtime.BaseRuntime* *method*), 274
copy () (*pytorch_pfn_extras.nn.parallel.distributed.OrderedDict* *method*), 238
copy () (*pytorch_pfn_extras.training.extensions.profile_report.OrderedDict* *method*), 412
create_consumer () (*py-
 torch_pfn_extras.training.extensions.snapshot_writers.ProcessQueue* *method*), 428
create_consumer () (*py-*

```

torch_pfn_extras.training.extensions.snapshot_writers.create_consumer() (py-  

method), 432  

create_consumer() (py-  

torch_pfn_extras.training.extensions.snapshot_writers.ConsumerWriter (in module  

method), 437  

create_consumer() (py-  

torch_pfn_extras.writing.ProcessQueueWriter  

method), 502  

create_consumer() (py-  

torch_pfn_extras.writing.QueueWriter  

method), 505  

create_consumer() (py-  

torch_pfn_extras.writing.ThreadQueueWriter  

method), 510  

create_distributed_subset_indices() (in module  

torch_pfn_extras.distributed), 73  

create_evaluator() (in module py-  

torch_pfn_extras.engine), 75  

create_header_and_templates() (in module py-  

torch_pfn_extras.training.extensions.print_report)  

401  

create_queue() (pytorch_pfn_extras.training.extensions.snapshot_writers.QueueWriter  

method), 429  

create_queue() (pytorch_pfn_extras.training.extensions.snapshot_writers.QueueWriter  

method), 432  

create_queue() (pytorch_pfn_extras.training.extensions.snapshot_writers.ThreadQueueWriter  

method), 438  

create_queue() (pytorch_pfn_extras.writing.QueueWriter  

method), 505  

create_queue() (pytorch_pfn_extras.writing.ThreadQueueWriter  

method), 511  

create_task() (pytorch_pfn_extras.training.extensions.snapshot_writers.QueueWriter  

method), 432  

create_task() (pytorch_pfn_extras.writing.QueueWriter  

method), 505  

create_trainer() (in module py-  

torch_pfn_extras.engine), 76  

create_worker() (py-  

torch_pfn_extras.training.extensions.snapshot_writers.ProcessWriter  

method), 430  

create_worker() (py-  

torch_pfn_extras.training.extensions.snapshot_writers.StandardWriter  

method), 435  

create_worker() (py-  

torch_pfn_extras.training.extensions.snapshot_writers.ThreadWriter  

method), 438  

create_worker() (py-  

torch_pfn_extras.writing.ProcessWriter  

method), 503  

create_worker() (py-  

torch_pfn_extras.writing.StandardWriter  

method), 508

```

(py-
torch_pfn_extras.writing.ThreadWriter
method), 511
torch_pfn_extras.writing.ThreadQueueWriter (in module
torch_pfn_extras.config), 42
cwd() (pytorch_pfn_extras.onnx.load.Path class method),
253
cwd() (pytorch_pfn_extras.onnx.unstrip_tensor.Path
class method), 260

D

DataLoader (class in pytorch_pfn_extras.dataloaders),
45
DataLoader (class in py-
torch_pfn_extras.dataloaders.dataloader),
51
Dataset (class in py-
torch_pfn_extras.dataset.tabular.tabular_dataset),
68
dataset (pytorch_pfn_extras.dataloaders.DataLoader
attribute), 48
dataset (pytorch_pfn_extras.dataloaders.dataloader.DataLoader
attribute), 54
deepcopy() (in module py-
torch_pfn_extras.training.extensions.print_report),
401
default_collate() (in module py-
torch_pfn_extras.dataloaders.dataloader),
48
default_convert() (in module py-
torch_pfn_extras.dataloaders.dataloader),
50
default_name (pytorch_pfn_extras.training.Extension
property), 289
default_name (pytorch_pfn_extras.training.Extension
property), 304
default_name (pytorch_pfn_extras.training.extensions.best_value.BestValue
attribute), 355
default_name (pytorch_pfn_extras.training.extensions.best_value.MaxValue
attribute), 359
default_name (pytorch_pfn_extras.training.extensions.best_value.MinValue
attribute), 360
default_name (pytorch_pfn_extras.training.extensions.BestValue
attribute), 314
default_name (pytorch_pfn_extras.training.extensions.Evaluator
attribute), 319
default_name (pytorch_pfn_extras.training.extensions.Evaluator
attribute), 366
default_name (pytorch_pfn_extras.training.extensions.parameter_statistics
attribute), 395

default_name (pytorch_pfn_extras.training.extensions.ParameterStatistics attribute), 335
default_statistics (pytorch_pfn_extras.training.extensions.ParameterStatistics attribute), 395
default_statistics (pytorch_pfn_extras.training.extensions.ParameterStatistics attribute), 335
default_transform_model() (in module torch_pfn_extras.engine), 77
DelegateDataset (class in torch_pfn_extras.dataset.tabular), 64
DelegateDataset (class in torch_pfn_extras.dataset.tabular.delegate_dataset), 66
DictSummary (class in pytorch_pfn_extras.reporting), 268
dilation (pytorch_pfn_extras.nn.modules.lazy_conv.LazyConv1d attribute), 179
dilation (pytorch_pfn_extras.nn.modules.lazy_conv.LazyConv2d attribute), 182
dilation (pytorch_pfn_extras.nn.modules.lazy_conv.LazyConv3d attribute), 185
DistributedDataParallel (class in torch_pfn_extras.nn.parallel), 226
DistributedDataParallel (class in torch_pfn_extras.nn.parallel.distributed), 233
DistributedEvaluator (class in torch_pfn_extras.training), 286
DistributedEvaluator (class in torch_pfn_extras.training.extensions), 315
DistributedEvaluator (class in torch_pfn_extras.training.extensions.evaluator), 361
DistributedValidationSampler (class in torch_pfn_extras.distributed), 74
drop_last (pytorch_pfn_extras.dataloaders.DataLoader attribute), 48
drop_last (pytorch_pfn_extras.dataloaders.DataLoader attribute), 54
dump() (pytorch_pfn_extras.utils.comparer.Comparer method), 497

E

EarlyStoppingTrigger (class in torch_pfn_extras.training.triggers), 464
EarlyStoppingTrigger (class in torch_pfn_extras.training.triggers.early_stopping_trigger), 472
elapsed_time (pytorch_pfn_extras.training.extension.ExtensionsManagerProtocol property), 307
elapsed_time (pytorch_pfn_extras.training.extensions.best_value.ExtensionsManagerProtocol property), 357

elapsed_time (pytorch_pfn_extras.training.extensions.evaluator.ExtensionsManagerProtocol property), 367
(pytorch_pfn_extras.training.extensions.parameter_statistics.PropertyStatistics property), 392
elapsed_time (pytorch_pfn_extras.training.extensions.lr_scheduler.ExtensionsManagerProtocol property), 382
elapsed_time (pytorch_pfn_extras.training.extensions.micro_average.ExtensionsManagerProtocol property), 388
elapsed_time (pytorch_pfn_extras.training.extensions.parameter_statistics.PropertyStatistics property), 392
elapsed_time (pytorch_pfn_extras.training.extensions.plot_report.ExtensionsManagerProtocol property), 397
elapsed_time (pytorch_pfn_extras.training.extensions.print_report.ExtensionsManagerProtocol property), 403
elapsed_time (pytorch_pfn_extras.training.extensions.profile_report.ExtensionsManagerProtocol property), 411
elapsed_time (pytorch_pfn_extras.training.extensions.progress_bar.ExtensionsManagerProtocol property), 417
elapsed_time (pytorch_pfn_extras.training.extensions.slack.ExtensionsManagerProtocol property), 421
elapsed_time (pytorch_pfn_extras.training.extensions.util.ExtensionsManagerProtocol property), 442
elapsed_time (pytorch_pfn_extras.training.extensions.value_observation.Properties property), 448
elapsed_time (pytorch_pfn_extras.training.extensions.variable_statistics.VariableStatistics property), 451
elapsed_time (pytorch_pfn_extras.training.ExtensionsManagerProtocol property), 294
elapsed_time (pytorch_pfn_extras.training.triggers.early_stopping_trigger.Trigger property), 475
elapsed_time (pytorch_pfn_extras.training.triggers.interval_trigger.ExtensionsManagerProtocol property), 477
elapsed_time (pytorch_pfn_extras.training.triggers.manual_schedule_trigger.Trigger property), 480
elapsed_time (pytorch_pfn_extras.training.triggers.minmax_value_trigger.Trigger property), 485
elapsed_time (pytorch_pfn_extras.training.triggers.once_trigger.ExtensionsManagerProtocol property), 488
elapsed_time (pytorch_pfn_extras.training.triggers.time_trigger.ExtensionsManagerProtocol property), 492
encoding (pytorch_pfn_extras.training.extensions.evaluator.TextIO property), 372
encoding (pytorch_pfn_extras.training.extensions.util.TextIO property), 446
Ensure (class in pytorch_pfn_extras.nn), 100
Ensure (class in pytorch_pfn_extras.nn.modules.ensure_shape), 124
ensure() (in module pytorch_pfn_extras.nn), 100
ENSURE_MANAGER_PROTOCOL (module pytorch_pfn_extras.nn.modules.ensure_shape), 123
epoch (pytorch_pfn_extras.training.extension.ExtensionsManagerProtocol)

property), 307
epoch (pytorch_pfn_extras.training.extensions.best_value.EpochDetail (pytorch_pfn_extras.training.extensions.fail_on_non_number_property), 357
epoch (pytorch_pfn_extras.training.extensions.evaluator.EpochDetail (pytorch_pfn_extras.training.extensions.log_report.ExtensionsManagerProtocol.property), 367
epoch (pytorch_pfn_extras.training.extensions.fail_on_non_epoch_detail (pytorch_pfn_extras.training.extensions.lr_scheduler.ExtensionsManagerProtocol.property), 373
epoch (pytorch_pfn_extras.training.extensions.log_report.EpochDetail (pytorch_pfn_extras.training.extensions.micro_average.ExtensionsManagerProtocol.property), 376
epoch (pytorch_pfn_extras.training.extensions.lr_scheduler.EpochDetail (pytorch_pfn_extras.training.extensions.parameter_statistics.ExtensionsManagerProtocol.property), 382
epoch (pytorch_pfn_extras.training.extensions.micro_average.EpochDetail (pytorch_pfn_extras.training.extensions.plot_report.ExtensionsManagerProtocol.property), 388
epoch (pytorch_pfn_extras.training.extensions.parameter_statistics.EpochDetail (pytorch_pfn_extras.training.extensions.print_report.ExtensionsManagerProtocol.property), 392
epoch (pytorch_pfn_extras.training.extensions.plot_report.EpochDetail (pytorch_pfn_extras.training.extensions.profile_report.ExtensionsManagerProtocol.property), 397
epoch (pytorch_pfn_extras.training.extensions.print_report.EpochDetail (pytorch_pfn_extras.training.extensions.progress_bar.ExtensionsManagerProtocol.property), 403
epoch (pytorch_pfn_extras.training.extensions.profile_report.EpochDetail (pytorch_pfn_extras.training.extensions.slack.ExtensionsManagerProtocol.property), 411
epoch (pytorch_pfn_extras.training.extensions.progress_bar.EpochDetail (pytorch_pfn_extras.training.extensions.util.ExtensionsManagerProtocol.property), 417
epoch (pytorch_pfn_extras.training.extensions.slack.ExtensionsManagerProtocol.property), 421
epoch (pytorch_pfn_extras.training.extensions.util.ExtensionsManagerProtocol.property), 442
epoch (pytorch_pfn_extras.training.extensions.value_observation.EpochDetail (pytorch_pfn_extras.training.extensions.value_observation.ExtensionsManagerProtocol.property), 448
epoch (pytorch_pfn_extras.training.extensions.util.ExtensionsManagerProtocol.property), 451
epoch (pytorch_pfn_extras.training.extensions.value_observation.EpochDetail (pytorch_pfn_extras.training.ExtensionsManagerProtocol.property), 294
epoch (pytorch_pfn_extras.training.extensions.variable_statistics.EpochDetail (pytorch_pfn_extras.training.Trainer.ExtensionsManagerProtocol.property), 299
epoch (pytorch_pfn_extras.training.ExtensionsManagerProtocol.EpochDetail (pytorch_pfn_extras.training.triggers.early_stopping_trigger.ExtensionsManagerProtocol.property), 294
epoch (pytorch_pfn_extras.training.Trainer.property), epoch_detail (pytorch_pfn_extras.training.triggers.interval_trigger.ExtensionsManagerProtocol.property), 477
epoch (pytorch_pfn_extras.training.triggers.early_stopping_trigger.EpochDetail (pytorch_pfn_extras.training.triggers.manual_schedule_trigger.ExtensionsManagerProtocol.property), 475
epoch (pytorch_pfn_extras.training.triggers.interval_trigger.EpochDetail (pytorch_pfn_extras.training.triggers.minmax_value_trigger.ExtensionsManagerProtocol.property), 477
epoch (pytorch_pfn_extras.training.triggers.manual_schedule_trigger.EpochDetail (pytorch_pfn_extras.training.triggers.once_trigger.ExtensionsManagerProtocol.property), 480
epoch (pytorch_pfn_extras.training.triggers.minmax_value_trigger.EpochDetail (pytorch_pfn_extras.training.triggers.time_trigger.ExtensionsManagerProtocol.property), 485
epoch (pytorch_pfn_extras.training.triggers.once_trigger.ExtensionsManagerProtocol.property), 488
epoch (pytorch_pfn_extras.training.triggers.time_trigger.ExtensionsManagerProtocol.property), 492
epoch (pytorch_pfn_extras.training.triggers.once_trigger.ExtensionsManagerProtocol.attribute), 152
epoch (pytorch_pfn_extras.training.triggers.time_trigger.ExtensionsManagerProtocol.attribute), 155
epoch_detail (pytorch_pfn_extras.training.extension.ExtensionsManagerProtocol.attribute), 157
epoch_detail (pytorch_pfn_extras.training.extensions.best_value.ExtensionsManagerProtocol.property), 357
epoch_detail (pytorch_pfn_extras.training.extensions.evaluator.ExtensionsManagerProtocol.property), 367
epoch_detail (pytorch_pfn_extras.training.extensions.evaluator.TextIOErrors (pytorch_pfn_extras.training.extensions.evaluator.TextIO.property), 372

errors (pytorch_pfn_extras.training.extensions.util.TextIO evaluate() (pytorch_pfn_extras.training.extensions.Evaluator property), 446
eval_func (pytorch_pfn_extras.training.extensions.Evaluator evaluate() (pytorch_pfn_extras.training.extensions.evaluator.Evaluator method), 317
eval_func (pytorch_pfn_extras.training.extensions.evaluator evaluate() (pytorch_pfn_extras.training.extensions.evaluator.IgniteEvaluator attribute), 364
eval_func() (pytorch_pfn_extras.training.extensions.Evaluator evaluate() (pytorch_pfn_extras.training.extensions.IgniteEvaluator method), 319
eval_func() (pytorch_pfn_extras.training.extensions.evaluator evaluate() (pytorch_pfn_extras.training.extensions.evaluator.IgniteEvaluator method), 323
eval_func() (pytorch_pfn_extras.training.extensions.evaluator evaluate() (pytorch_pfn_extras.training.extensions.evaluator.IgniteEvaluator method), 366
eval_hook (pytorch_pfn_extras.training.extensions.Evaluator eval_hook (pytorch_pfn_extras.training.extensions.evaluator.Evaluator attribute), 317
eval_hook (pytorch_pfn_extras.training.extensions.evaluator.Evaluator eval_hook (pytorch_pfn_extras.training.extensions.evaluator attribute), 364
eval_loop_begin() (pytorch_pfn_extras.handler.BaseHandler method), 82
eval_loop_end() (pytorch_pfn_extras.handler.BaseHandler method), 82
eval_loop_end() (pytorch_pfn_extras.handler.Handler method), 93
eval_post_step() (pytorch_pfn_extras.handler.BaseHandler method), 82
eval_post_step() (pytorch_pfn_extras.handler.Handler method), 94
eval_post_step() (pytorch_pfn_extras.runtime.BaseRuntime method), 274
eval_post_step() (pytorch_pfn_extras.runtime.PyTorchRuntime method), 279
eval_pre_step() (pytorch_pfn_extras.runtime.BaseRuntime method), 275
eval_pre_step() (pytorch_pfn_extras.runtime.PyTorchRuntime method), 279
eval_setup() (pytorch_pfn_extras.handler.BaseHandler method), 82
eval_setup() (pytorch_pfn_extras.handler.Handler method), 94
eval_step() (pytorch_pfn_extras.handler.BaseHandler method), 82
eval_step() (pytorch_pfn_extras.handler.CodeBlockLogic method), 85
eval_step() (pytorch_pfn_extras.handler.CodeBlockLogic method), 91
eval_step() (pytorch_pfn_extras.handler.Handler method), 94
eval_step() (pytorch_pfn_extras.handler.Logic method), 97
evaluator (pytorch_pfn_extras.training.evaluator.Evaluator method), 319
Evaluator (class in pytorch_pfn_extras.training), 286
Evaluator (class in pytorch_pfn_extras.training.evaluator), 316
Evaluator (class in pytorch_pfn_extras.training.extensions.evaluator), 363
evaluator (pytorch_pfn_extras.training.Trainer property), 300
execute() (pytorch_pfn_extras.runtime.BaseRuntime method), 275
execute() (pytorch_pfn_extras.runtime.PyTorchRuntime method), 280
exists() (pytorch_pfn_extras.onnx.load.Path method), 254
exists() (pytorch_pfn_extras.onnx.unstrip_tensor.Path method), 260
expanduser() (pytorch_pfn_extras.onnx.load.Path method), 254
expanduser() (pytorch_pfn_extras.onnx.unstrip_tensor.Path method), 260
export() (in module pytorch_pfn_extras.onnx), 244
export testcase() (in module pytorch_pfn_extras.onnx), 244
extend() (pytorch_pfn_extras.training.Trainer method), 300
ExtendedSequential (class in pytorch_pfn_extras.nn), 103
ExtendedSequential (class in pytorch_pfn_extras.nn.modules.extended_sequential), 127
Extension (class in pytorch_pfn_extras.training), 287
Extension (class in pytorch_pfn_extras.training.extension), 303
ExtensionEntry (class in pytorch_pfn_extras.training), 290
ExtensionEntry (class in pytorch_pfn_extras.training.extension), 305
ExtensionsManager (class in pytorch_pfn_extras.training), 291
ExtensionsManagerProtocol (class in pytorch_pfn_extras.training), 293
ExtensionsManagerProtocol (class in pytorch_pfn_extras.training.extension), 306
ExtensionsManagerProtocol (class in pytorch_pfn_extras.training.extensions.best_value), 356

ExtensionsManagerProtocol (class in py-	ExtensionsManagerProtocol (class in py-
torch_pfn_extras.training.extensions.evaluator),	torch_pfn_extras.training.triggers.once_trigger),
367	488
ExtensionsManagerProtocol (class in py-	ExtensionsManagerProtocol (class in py-
torch_pfn_extras.training.extensions.fail_on_non_number), torch_pfn_extras.training.triggers.time_trigger),	torch_pfn_extras.training.extensions.time_trigger),
372	491
ExtensionsManagerProtocol (class in py-	F
torch_pfn_extras.training.extensions.log_report),	FailOnNonNumber (class in py-
376	torch_pfn_extras.training.extensions), 320
ExtensionsManagerProtocol (class in py-	FailOnNonNumber (class in py-
torch_pfn_extras.training.extensions.lr_scheduler),	torch_pfn_extras.training.extensions.fail_on_non_number),
381	381
ExtensionsManagerProtocol (class in py-	374
torch_pfn_extras.training.extensions.micro_average),	fetch() (pytorch_pfn_extras.dataset.tabular_dataset.TabularDataset method), 71
387	
ExtensionsManagerProtocol (class in py-	fetch() (pytorch_pfn_extras.dataset.TabularDataset method), 58
torch_pfn_extras.training.extensions.parameter_statistics),	391
391	fileno() (pytorch_pfn_extras.onnx.load.IO method),
ExtensionsManagerProtocol (class in py-	249
torch_pfn_extras.training.extensions.plot_report),	fileno() (pytorch_pfn_extras.training.extensions.print_report.IO method), 405
396	
ExtensionsManagerProtocol (class in py-	filter_and_sort_entries() (in module py-
torch_pfn_extras.training.extensions.print_report),	torch_pfn_extras.training.extensions.print_report),
402	401
ExtensionsManagerProtocol (class in py-	filter_state_objects() (in module py-
torch_pfn_extras.training.extensions.profile_report),	torch_pfn_extras.engine), 77
410	filter_state_objects_dict() (in module py-
ExtensionsManagerProtocol (class in py-	torch_pfn_extras.engine), 77
torch_pfn_extras.training.extensions.progress_bar),	finalize() (pytorch_pfn_extras.profiler.TimeSummary method), 265
416	
ExtensionsManagerProtocol (class in py-	finalize() (pytorch_pfn_extras.training.Extension method), 289
torch_pfn_extras.training.extensions.slack),	420
420	finalize() (pytorch_pfn_extras.training.extension.Extension method), 304
ExtensionsManagerProtocol (class in py-	finalize() (pytorch_pfn_extras.training.extensions.log_report.LogReport method), 379
torch_pfn_extras.training.extensions.util),	441
441	finalize() (pytorch_pfn_extras.training.extensions.plot_report.PlotReport method), 327
ExtensionsManagerProtocol (class in py-	447
torch_pfn_extras.training.extensions.value_observation),	finalize() (pytorch_pfn_extras.training.extensions.plot_report.PlotReport method), 400
447	
ExtensionsManagerProtocol (class in py-	finalize() (pytorch_pfn_extras.training.extensions.variable_statistics.VarStatPlot),
torch_pfn_extras.training.extensions.variable_statistics.VarStatPlot),	method), 338
450	
ExtensionsManagerProtocol (class in py-	finalize() (pytorch_pfn_extras.training.extensions.profile_report.ProfileReport method), 415
torch_pfn_extras.training.triggers.early_stopping_trigger),	474
474	finalize() (pytorch_pfn_extras.training.extensions.ProfileReport method), 342
ExtensionsManagerProtocol (class in py-	method), 342
torch_pfn_extras.training.triggers.interval_trigger),	finalize() (pytorch_pfn_extras.training.extensions.progress_bar.Progress method), 419
476	
ExtensionsManagerProtocol (class in py-	finalize() (pytorch_pfn_extras.training.extensions.ProgressBar method), 344
torch_pfn_extras.training.triggers.manual_schedule_trigger),	479
479	finalize() (pytorch_pfn_extras.training.extensions.snapshot_writers.QueueWriter method), 432
ExtensionsManagerProtocol (class in py-	484
torch_pfn_extras.training.triggers.minmax_value),	finalize() (pytorch_pfn_extras.training.extensions.snapshot_writers.Stan
484	method), 435

G

finalize() (pytorch_pfn_extras.training.extensions.snapshot_writers.Writer method), 436
finalize() (pytorch_pfn_extras.training.extensions.snapshot_writers.Writer method), 440
finalize() (pytorch_pfn_extras.training.extensions.variable_statistics.VariableStatisticsPlot method), 457
finalize() (pytorch_pfn_extras.training.extensions.VariableStatisticsPlot method), 319
finalize() (pytorch_pfn_extras.training.ExtensionsManager method), 293
finalize() (pytorch_pfn_extras.writing.QueueWriter method), 505
finalize() (pytorch_pfn_extras.writing.StandardWriter method), 508
finalize() (pytorch_pfn_extras.writing.TensorBoardWriter method), 510
finalize() (pytorch_pfn_extras.writing.Writer method), 513
find_inplace() (in module torch_pfn_extras.torchscript), 283
finished(pytorch_pfn_extras.training.triggers.once_triggered.Trigger_comparer attribute), 489
finished(pytorch_pfn_extras.training.triggers.once_triggered.Trigger_comparer attribute), 490
finished(pytorch_pfn_extras.training.triggers.OnceTrigger attribute), 469
finished(pytorch_pfn_extras.training.triggers.OnceTrigger attribute), 470
flush() (pytorch_pfn_extras.onnx.load.IO method), 250
flush() (pytorch_pfn_extras.training.extensions.print_report.IO method), 406
flush() (pytorch_pfn_extras.training.extensions.util.ProgressBar method), 443
forward() (in module pytorch_pfn_extras.handler), 79
forward() (pytorch_pfn_extras.nn.Ensure method), 102
forward() (pytorch_pfn_extras.nn.LazyLinear method), 122
forward() (pytorch_pfn_extras.nn.modules.ensure_shape.Ensure method), 126
forward() (pytorch_pfn_extras.nn.modules.lazy_linear.LazyLinear method), 208
forward() (pytorch_pfn_extras.nn.parallel.distributed.DistributedDataParallel method), 236
forward() (pytorch_pfn_extras.nn.parallel.DistributedDataParallel method), 229
from_data() (in module torch_pfn_extras.dataset.tabular), 63
from_ndarray() (in module pytorch_pfn_extras), 39
from_numpy_dtype() (in module pytorch_pfn_extras), 39
fromkeys() (pytorch_pfn_extras.nn.parallel.distributed.OrderedDict method), 238
fromkeys() (pytorch_pfn_extras.training.extensions.profile.get_extensions_profile method), 412
fromkeys() (pytorch_pfn_extras.training.extensions.lr_scheduler.ExtensionsManager method), 382
get_all_iterators() (pytorch_pfn_extras.training.evaluator.Evaluator method), 366
get_all_targets() (pytorch_pfn_extras.training.evaluator.Evaluator method), 366
get_all_targets() (pytorch_pfn_extras.training.evaluator.Evaluator method), 366
get_current_reporter() (in module torch_pfn_extras.reporting), 266
get_data() (pytorch_pfn_extras.training.extensions.variable_statistics_plot.get_variable_statistics_plot method), 453
get_example() (pytorch_pfn_extras.dataset.TabularDataset method), 58
get_examples() (pytorch_pfn_extras.dataset.tabular.delegate_dataset.DelegateDataset method), 67
get_examples() (pytorch_pfn_extras.dataset.tabular.TabularDataset method), 58
get_extension() (pytorch_pfn_extras.training_extensions.ExtensionsManagerProtocol method), 307
get_extension() (pytorch_pfn_extras.training_extensions.best_value.ExtensionsManager method), 367
get_extension() (pytorch_pfn_extras.training_extensions.fail_on_non_number.ExtensionsManager method), 373
get_extension() (pytorch_pfn_extras.training_extensions.log_report.ExtensionsManager method), 376
get_extension() (pytorch_pfn_extras.training_extensions.micro_average.ExtensionsManager method), 382

method), 388
`get_extension()` (py-
`torch_pfn_extras.training.extensions.parameter_scheduler_manager_for_Pxtra`(`method`), 392
`get_extension()` (py-
`torch_pfn_extras.training.extensions.plot_report.ExtensionsManagerForPxtra`(`method`), 397
`get_extension()` (py-
`torch_pfn_extras.training.extensions.print_report.ExtensionsManagerForPxtra`(`method`), 403
`get_extension()` (py-
`torch_pfn_extras.training.extensions.print_report.ExtensionsManagerForPxtra`(`method`), 408
`get_extension()` (py-
`torch_pfn_extras.training.extensions.print_report.ExtensionsManagerForPxtra`(`method`), 409
`get_extension()` (py-
`torch_pfn_extras.training.extensions.profile_report.ExtensionsManagerProtocol`(`method`), 411
`get_extension()` (py-
`torch_pfn_extras.training.extensions.progress_bar_manager`(`method`), 417
`get_extension()` (py-
`torch_pfn_extras.training.extensions.slack.ExtensionsManagerProtocol`(`method`), 421
`get_extension()` (py-
`torch_pfn_extras.training.extensions.util.ExtensionsManagerProtocol`(`method`), 442
`get_extension()` (py-
`torch_pfn_extras.training.extensions.value_observer`(`method`), 448
`get_extension()` (py-
`torch_pfn_extras.training.extensions.variable_state`(`method`), 451
`get_extension()` (py-
`torch_pfn_extras.training.ExtensionsManagerProtocol`(`method`), 294
`get_extension()` (py-
`torch_pfn_extras.training.triggers.early_stopping_trigger`(`method`), 445
`get_extension()` (py-
`torch_pfn_extras.training.triggers.early_stopping_trigger`(`method`), 475
`get_extension()` (py-
`torch_pfn_extras.training.triggers.interval_trigger`(`method`), 477
`get_extension()` (py-
`torch_pfn_extras.training.triggers.manual_schedule`(`method`), 480
`get_extension()` (py-
`torch_pfn_extras.training.triggers.minmax_value_trigger`(`method`), 485
`get_extension()` (py-
`torch_pfn_extras.training.triggers.once_trigger`(`method`), 488
`get_extension()` (py-
`torch_pfn_extras.training.triggers.time_trigger`(`method`), 492
`get_foreach_wrapper()` (in module `torch_pfn_extras.nn.parallel.distributed`), 232
`get_iterator()` (pytorch_pfn_extras.training_extensions.Evaluator)(`method`), 320
`get_iterator()` (pytorch_pfn_extras.training_extensions.ExtensionsManagerForPxtra)(`method`), 366
`get_log_report()` (py-
`torch_pfn_extras.training_extensions.plot_report.ExtensionsManagerForPxtra`(`method`), 444
`get_log_report()` (py-
`torch_pfn_extras.training_extensions.print_report.ExtensionsManagerForPxtra`(`method`), 408
`get_log_report()` (py-
`torch_pfn_extras.training_extensions.print_report.ExtensionsManagerForPxtra`(`method`), 339
`get_logger()` (in module `pytorch_pfn_extras.logging`), 300
`get_optimizer()` (pytorch_pfn_extras.training.Trainer)(`method`), 320
`get_target()` (pytorch_pfn_extras.training_extensions.evaluator.Evaluator)(`method`), 320
`get_time_summary()` (in module `torch_pfn_extras.profiler`), 263
`get_time_summary()` (in module `torch_pfn_extras.training_extensions.profile_report`), 409
`get_training_length()` (py-
`torch_pfn_extras.training.trigger.IntervalTriggerProtocol`(`method`), 460
`get_training_length()` (py-
`torch_pfn_extras.training.triggers.early_stopping_trigger.EarlyStoppingTriggerProtocol`(`method`), 474
`get_training_length()` (py-
`torch_pfn_extras.training.triggers.interval_trigger.IntervalTriggerProtocol`(`method`), 465
`get_training_length()` (py-
`torch_pfn_extras.training.triggers.interval_trigger.IntervalTriggerProtocol`(`method`), 479
`get_training_length()` (py-
`torch_pfn_extras.training.triggers.interval_trigger.IntervalTriggerProtocol`(`method`), 477
`get_training_length()` (py-
`torch_pfn_extras.training.triggers.interval_trigger.IntervalTriggerProtocol`(`method`), 466
`get_trigger_extensions()` (py-
`torch_pfn_extras.training.trigger_extensions_manager_protocol`(`method`), 459
`get_value()` (pytorch_pfn_extras.dataset.shared_dataset.Cache)(`method`), 62
`get_value()` (pytorch_pfn_extras.dataset.shared_dataset.InfiniteCache)(`method`), 62
`get_value()` (py-
`torch_pfn_extras.dataset.workers_manager_protocol`(`method`), 254
`glob()` (pytorch_pfn_extras.onnx.load.Path)(`method`), 254
`glob()` (pytorch_pfn_extras.onnx.unstrip_tensor.Path)(`method`), 260
`group()` (pytorch_pfn_extras.onnx.load.Path)(`method`), 245

254
group() (`pytorch_pfn_extras.onnx.unstrip_tensor.Path` method), 260
groups (`pytorch_pfn_extras.nn.modules.lazy_conv.LazyConv1d` attribute), 179
groups (`pytorch_pfn_extras.nn.modules.lazy_conv.LazyConv2d` attribute), 182
groups (`pytorch_pfn_extras.nn.modules.lazy_conv.LazyConv3d` attribute), 185
method), 275
initialize_module() (`pytorch_pfn_extras.runtime.PyTorchRuntime` method), 280
initialize_ompi_environment() (in module `pytorch_pfn_extras.distributed`), 73
intermediate_value() (in module `pytorch_pfn_extras.utils.comparer`), 495
IntervalTrigger (class in `pytorch_pfn_extras.training.trigger`), 460
IntervalTrigger (class in `pytorch_pfn_extras.training.triggers`), 465
IntervalTrigger (class in `pytorch_pfn_extras.training.triggers.interval_trigger`), 478
IO (class in `pytorch_pfn_extras.onnx.load`), 248
IO (class in `pytorch_pfn_extras.training.extensions.print_report`), 404
H
Handler (class in `pytorch_pfn_extras.handler`), 92
home() (`pytorch_pfn_extras.onnx.load.Path` class method), 254
home() (`pytorch_pfn_extras.onnx.unstrip_tensor.Path` class method), 260
I
IgniteEvaluator (class in `pytorch_pfn_extras.training.extensions`), 321
IgniteEvaluator (class in `pytorch_pfn_extras.training.extensions.evaluator`), 368
IgniteExtensionsManager (class in `pytorch_pfn_extras.training`), 295
in_channels (`pytorch_pfn_extras.nn.modules.lazy_conv.LazyConv1d` attribute), 179
in_channels (`pytorch_pfn_extras.nn.modules.lazy_conv.LazyConv2d` attribute), 182
in_channels (`pytorch_pfn_extras.nn.modules.lazy_conv.LazyConv3d` attribute), 185
in_cooldown (`pytorch_pfn_extras.training.extensions.lr_scheduler.ReduceLROnPlateau` property), 386
in_features (`pytorch_pfn_extras.nn.modules.lazy_linear.LazyLinear` attribute), 209
InfiniteCache (class in `pytorch_pfn_extras.dataset.shared_dataset`), 61
initialize() (`pytorch_pfn_extras.profiler.TimeSummary` method), 265
initialize() (`pytorch_pfn_extras.training.Extension` method), 289
initialize() (`pytorch_pfn_extras.training.extension.Extension` method), 304
initialize() (`pytorch_pfn_extras.training.extensions.print_report` method), 409
initialize() (`pytorch_pfn_extras.training.extensions.PrintReport` method), 340
initialize() (`pytorch_pfn_extras.training.extensions.snapshot_writers.Writer` method), 440
initialize() (`pytorch_pfn_extras.writing.Writer` method), 513
initialize_module() (`pytorch_pfn_extras.runtime.BaseRuntime` method), 275
initialize_ompi_environment() (in module `pytorch_pfn_extras.distributed`), 73
is_before_training (pytorch_pfn_extras.training.Extension attribute), 289
is_before_training (pytorch_pfn_extras.training.extension.Extension attribute), 304
is_before_training (pytorch_pfn_extras.training.extension.ExtensionsManagerProtocol property), 307
is_before_training (pytorch_pfn_extras.training.extensions.best_value.ExtensionsManager property), 357
is_before_training (pytorch_pfn_extras.training.extensions.evaluator.ExtensionsManager property), 368
is_before_training (pytorch_pfn_extras.training.extensions.fail_on_non_number.ExtensionsManager property), 373
is_before_training (pytorch_pfn_extras.training.extensions.log_report.ExtensionsManager property), 377
is_before_training (pytorch_pfn_extras.training.extensions.lr_scheduler.ExtensionsManager property), 382
is_before_training (pytorch_pfn_extras.training.extensions.micro_average.ExtensionsManager property), 388
is_before_training (pytorch_pfn_extras.training.extensions.parameter_statistics.ExtensionsManager property), 392
is_before_training (pytorch_pfn_extras.training.extensions.plot_report.ExtensionsManager property), 397
is_before_training (pytorch_pfn_extras.training.extensions.profile_report.ExtensionsManager property), 403
is_before_training (pytorch_pfn_extras.training.extensions.print_report.ExtensionsManager property), 403
is_before_training (pytorch_pfn_extras.training.extensions.profile_report.ExtensionsManager property), 403

property), 411
is_before_training (pytorch_pfn_extras.training.extensions.progress_bar.ExtensionsManagerProtocol), 254
 torch_pfn_extras.training.extensions.slack.ExtensionsManagerProtocol), 254
 property), 417
is_before_training (pytorch_pfn_extras.training.extensions.util.ExtensionsManagerProtocol), 260
 property), 421
is_before_training (pytorch_pfn_extras.training.extensions.value_observer.ExtensionsManagerProtocol), 260
 property), 442
is_before_training (pytorch_pfn_extras.training.extensions.variable_stats.ExtensionsManagerProtocol), 260
 property), 448
is_before_training (pytorch_pfn_extras.training.extensions.value_observer.ExtensionsManagerProtocol), 260
 property), 448
is_before_training (pytorch_pfn_extras.training.extensions.variable_stats.ExtensionsManagerProtocol), 260
 property), 451
is_before_training (pytorch_pfn_extras.training.ExtensionsManagerProtocol), 260
 property), 294
is_before_training (pytorch_pfn_extras.training.Trainer property), 260
 300
is_before_training (pytorch_pfn_extras.training.triggers.early_stopping_trigger.ExtensionsManagerProtocol), 245
 property), 475
is_before_training (pytorch_pfn_extras.training.triggers.interval_trigger.ExtensionsManagerProtocol), 245
 property), 477
is_before_training (pytorch_pfn_extras.training.triggers.manual_schedule.ExtensionsManagerProtocol), 175
 property), 480
is_before_training (pytorch_pfn_extras.training.triggers.minmax_value_trigger.ExtensionsManagerProtocol), 175
 property), 485
is_before_training (pytorch_pfn_extras.training.triggers.once_trigger.ExtensionsManagerProtocol), 254
 property), 489
is_before_training (pytorch_pfn_extras.training.triggers.time_trigger.ExtensionsManagerProtocol), 254
 property), 492
is_better() (pytorch_pfn_extras.training.extensions.lr_scheduler.ReduceLROnPlateau method), 386
is_block_device() (pytorch_pfn_extras.onnx.load.Path method), 254
 torch_pfn_extras.onnx.load.Path
is_block_device() (pytorch_pfn_extras.onnx.unstrip_tensor.Path method), 260
 torch_pfn_extras.onnx.unstrip_tensor.Path
is_cached() (pytorch_pfn_extras.dataset.shared_dataset.Cache method), 250
 method), 61
is_cached() (pytorch_pfn_extras.dataset.shared_dataset.InfiniteCache method), 406
 method), 62
is_cached() (pytorch_pfn_extras.dataset.shared_dataset.ItemsOrderedDict method), 238
 ItemsOrderedDict), 238
 torch_pfn_extras.nn.parallel.distributed.OrderedDict
 method), 238

```
items() (pytorch_pfn_extras.training.extensions.profile_report.OrderedDict  
         method), 413  
iteration (pytorch_pfn_extras.training.extension.ExtensionsManagerProtocol)  
         property), 308  
iteration (pytorch_pfn_extras.training.extensions.best_value.ExtensionsManagerProtocol  
         property), 357  
iteration (pytorch_pfn_extras.training.extensions.evaluator.ExtensionsManagerProtocol  
         property), 368  
iteration (pytorch_pfn_extras.training.extensions.fail_on_non_number.ExtensionsManagerProtocol  
         property), 374  
iteration (pytorch_pfn_extras.training.extensions.log_report.ExtensionsManagerProtocol  
         property), 377  
iteration (pytorch_pfn_extras.training.extensions.lr_scheduler.ExtensionsManagerProtocol  
         property), 382  
iteration (pytorch_pfn_extras.training.extensions.micro_average.ExtensionsManagerProtocol  
         property), 388  
iteration (pytorch_pfn_extras.training.extensions.parameter_statistics.ExtensionsManagerProtocol  
         property), 392  
iteration (pytorch_pfn_extras.training.extensions.plot_report.ExtensionsManagerProtocol  
         property), 397  
iteration (pytorch_pfn_extras.training.extensions.print_report.ExtensionsManagerProtocol  
         property), 403  
iteration (pytorch_pfn_extras.training.extensions.profile_report.ExtensionsManagerProtocol  
         property), 411  
iteration (pytorch_pfn_extras.training.extensions.progress_bar.ExtensionsManagerProtocol  
         property), 417  
iteration (pytorch_pfn_extras.training.extensions.slack.ExtensionsManagerProtocol  
         property), 421  
iteration (pytorch_pfn_extras.training.extensions.util.ExtensionsManagerProtocol  
         property), 442  
iteration (pytorch_pfn_extras.training.extensions.value_observation.ExtensionsManagerProtocol  
         property), 448  
iteration (pytorch_pfn_extras.training.extensions.variable_statistics_plot.ExtensionsManagerProtocol  
         property), 451  
iteration (pytorch_pfn_extras.training.ExtensionsManagerProtocol)  
         property), 294  
iteration (pytorch_pfn_extras.training.Trainer property), 300  
iteration (pytorch_pfn_extras.training.triggers.early_stopping_trigger.ExtensionsManagerProtocol  
         property), 475  
iteration (pytorch_pfn_extras.training.triggers.interval_trigger.ExtensionsManagerProtocol  
         property), 477  
iteration (pytorch_pfn_extras.training.triggers.manual_schedule_trigger.ExtensionsManagerProtocol  
         property), 481  
iteration (pytorch_pfn_extras.training.triggers.minmax_value_trigger.ExtensionsManagerProtocol  
         property), 485  
iteration (pytorch_pfn_extras.training.triggers.once_trigger.ExtensionsManagerProtocol  
         property), 489  
iteration (pytorch_pfn_extras.training.triggers.time_trigger.ExtensionsManagerProtocol  
         property), 492  
IterationStatus (class in pytorch_pfn_extras.training.extensions.evaluator), 370  
iterdir() (pytorch_pfn_extras.onnx.load.Path method),  
           iterdir() (pytorch_pfn_extras.onnx.unstrip_tensor.Path  
           method), 261  
join() (pytorch_pfn_extras.dataset.tabular.tabular_dataset.TabularDataset  
       attribute), 179  
join() (pytorch_pfn_extras.dataset.TabularDataset  
       attribute), 182  
kernel_size (pytorch_pfn_extras.nn.modules.lazy_conv.LazyConv1d  
            attribute), 185  
kernel_size (pytorch_pfn_extras.nn.modules.lazy_conv.LazyConv2d  
            attribute), 185  
kernel_size (pytorch_pfn_extras.nn.modules.lazy_conv.LazyConv3d  
            attribute), 185  
keys (pytorch_pfn_extras.dataset.tabular.delegate_dataset.DelegateDataset  
      property), 67  
keys (pytorch_pfn_extras.dataset.tabular.DelegateDataset  
      property), 69  
keys (pytorch_pfn_extras.dataset.tabular_dataset.TabularDataset  
      property), 71  
keys (pytorch_pfn_extras.dataset.TabularDataset prop-  
      erty), 359  
keys (pytorch_pfn_extras.training.extensions.profile_report.OrderedDict  
      method), 413  
lazy_buffer_names (py-  
torch_pfn_extras.nn.modules.lazy.LazyInitializationMixin  
attribute), 131  
lazy_buffer_names (py-  
torch_pfn_extras.nn.modules.lazy_batchnorm.LazyInitializationMix-  
in attribute), 158  
lazy_buffer_names (py-  
torch_pfn_extras.nn.modules.lazy_conv.LazyInitializationMix-  
in attribute), 186  
lazy_buffer_names (py-  
torch_pfn_extras.nn.modules.lazy_linear.LazyInitializationMix-  
in attribute), 205  
lazy_parameter_names (py-  
torch_pfn_extras.nn.modules.lazy_linear.LazyLinear  
attribute), 122  
lazy_parameter_names (py-  
torch_pfn_extras.nn.modules.lazy_linear.LazyLinear  
attribute), 132  
lazy_parameter_names (py-  
torch_pfn_extras.nn.modules.lazy.LazyInitializationMix-  
in attribute), 159
```

lazy_parameter_names	(py- torch_pfn_extras.nn.modules.lazy_conv.LazyInitializationMixin attribute), 187	torch_pfn_extras.nn.modules.lazy_linear.LazyLinear (class in pytorch_pfn_extras.nn), 120
lazy_parameter_names	(py- torch_pfn_extras.nn.modules.lazy_linear.LazyInitializationMixin attribute), 205	LazyLinear (class in pytorch_pfn_extras.nn), 120
lazy_parameter_names	(py- torch_pfn_extras.nn.modules.lazy_linear.LazyLinear attribute), 209	LazyLinear (class in pytorch_pfn_extras.nn), 120
lazy_parameters_determined	(py- torch_pfn_extras.nn.modules.lazy.LazyInitializationMixin property), 132	lchmod() (pytorch_pfn_extras.onnx.load.Path method), 254
lazy_parameters_determined	(py- torch_pfn_extras.nn.modules.lazy_batchnorm.LazyInitializationMixin property), 159	lchmod() (pytorch_pfn_extras.onnx.unstrip_tensor.Path method), 261
lazy_parameters_determined	(py- torch_pfn_extras.nn.modules.lazy_conv.LazyInitializationMixin property), 187	line_buffering() (pytorch_pfn_extras.training.extensions.util.TextIO property), 372
lazy_parameters_determined	(py- torch_pfn_extras.nn.modules.lazy_linear.LazyInitializationMixin property), 205	line_buffering() (pytorch_pfn_extras.training.extensions.util.TextIO property), 446
LazyBatchNorm1d	(class in pytorch_pfn_extras.nn), 106	link_to() (pytorch_pfn_extras.onnx.load.Path method), 254
LazyBatchNorm1d	(class in py- torch_pfn_extras.nn.modules.lazy_batchnorm), 150	link_to() (pytorch_pfn_extras.onnx.load.Path method), 261
LazyBatchNorm2d	(class in pytorch_pfn_extras.nn), 108	load_model() (in module pytorch_pfn_extras.onnx), 247
LazyBatchNorm2d	(class in py- torch_pfn_extras.nn.modules.lazy_batchnorm), 152	load_model() (in module py- torch_pfn_extras.config.Config class method), 42
LazyBatchNorm3d	(class in pytorch_pfn_extras.nn), 110	load_path_with_optuna_types() (in module py- torch_pfn_extras.config_types), 43
LazyBatchNorm3d	(class in py- torch_pfn_extras.nn.modules.lazy_batchnorm), 155	load_state_dict() (py- torch_pfn_extras.engine.StateObjectProtocol method), 79
LazyConv1d	(class in pytorch_pfn_extras.nn), 113	load_state_dict() (py- torch_pfn_extras.handler.CodeBlock method), 90
LazyConv1d	(class in py- torch_pfn_extras.nn.modules.lazy_conv), 177	load_state_dict() (py- torch_pfn_extras.nn.parallel.DistributedDataParallel method), 236
LazyConv2d	(class in pytorch_pfn_extras.nn), 115	load_state_dict() (py- torch_pfn_extras.nn.parallel.DistributedDataParallel method), 229
LazyConv2d	(class in py- torch_pfn_extras.nn.modules.lazy_conv), 180	load_state_dict() (py- torch_pfn_extras.reporting.DictSummary method), 269
LazyConv3d	(class in pytorch_pfn_extras.nn), 117	load_state_dict() (py- torch_pfn_extras.reporting.Summary method), 272
LazyConv3d	(class in py- torch_pfn_extras.nn.modules.lazy_conv), 183	load_state_dict() (py- torch_pfn_extras.training.Extension method), 289
LazyInitializationMixin	(class in py- torch_pfn_extras.nn.modules.lazy), 131	load_state_dict() (py- torch_pfn_extras.training.Extension method), 305
LazyInitializationMixin	(class in py- torch_pfn_extras.nn.modules.lazy_batchnorm), 158	load_state_dict() (py- torch_pfn_extras.training.extension.ExtensionEntry method), 306
LazyInitializationMixin	(class in py- torch_pfn_extras.nn.modules.lazy_conv), 186	load_state_dict() (py- torch_pfn_extras.training.extension.ExtensionEntry method), 306
LazyInitializationMixin	(class in py- torch_pfn_extras.nn.modules.lazy_conv)	load_state_dict() (py- torch_pfn_extras.training.extension.ExtensionEntry method), 306

`torch_pfn_extras.training.ExtensionEntry` `torch_pfn_extras.training.Trainer` `method),`
`method),` 291 `300`
`load_state_dict()` `(py-` `load_state_dict()` `(py-`
 `torch_pfn_extras.training.extensions.best_value.MaxValue` `torch_pfn_extras.training.trigger.Trigger`
 `method),` 356 `method),` 461
`load_state_dict()` `(py-` `load_state_dict()` `(py-`
 `torch_pfn_extras.training.extensions.MaxValue` `torch_pfn_extras.training.triggers.MaxValueTrigger`
 `method),` 314 `method),` 463
`load_state_dict()` `(py-` `load_state_dict()` `(py-`
 `torch_pfn_extras.training.extensions.log_report.LogReport` `torch_pfn_extras.training.triggers.minmax_value_trigger.MaxValueTrigger`
 `method),` 379 `method),` 483
`load_state_dict()` `(py-` `load_state_dict()` `(py-`
 `torch_pfn_extras.training.extensions.LogReport` `torch_pfn_extras.training.triggers.once_trigger.OnceTrigger`
 `method),` 327 `method),` 490
`load_state_dict()` `(py-` `load_state_dict()` `(py-`
 `torch_pfn_extras.training.extensions.lr_scheduler.LRScheduler` `torch_pfn_extras.training.triggers.OnceTrigger`
 `method),` 384 `method),` 470
`load_state_dict()` `(py-` `load_state_dict()` `(py-`
 `torch_pfn_extras.training.extensions.lr_scheduler.ReduceLROnPlateau` `torch_pfn_extras.training.triggers.TimeTrigger`
 `method),` 386 `method),` 493
`load_state_dict()` `(py-` `load_state_dict()` `(py-`
 `torch_pfn_extras.training.extensions.LRScheduler` `torch_pfn_extras.training.triggers.TimeTrigger`
 `method),` 325 `method),` 471
`load_state_dict()` `(py-` `log (pytorch_pfn_extras.training.extensions.log_report.LogReport`
 `torch_pfn_extras.training.extensions.micro_average.MicroAverag` `torch_pfn_extras.training.extensions.LogReport`
 `method),` 391 `property),` 328
`load_state_dict()` `(py-` `log (pytorch_pfn_extras.training.extensions.LogReport`
 `torch_pfn_extras.training.extensions.MicroAverageLogic` `property),` 328
 `method),` 331 `LogReport` `(class` `in` `py-`
`load_state_dict()` `(py-` `torch_pfn_extras.training.extensions),` 325
 `torch_pfn_extras.training.extensions.plot_report.PlotReport` `torch_pfn_extras.training.extensions),` 325
 `method),` 400 `torch_pfn_extras.training.extensions.log_report),`
`load_state_dict()` `(py-` `377`
 `torch_pfn_extras.training.extensions.PlotReport` `LogWriterSaveFunc` `(class` `in` `py-`
 `method),` 338 `torch_pfn_extras.training.extensions.log_report),`
`load_state_dict()` `(py-` `380`
 `torch_pfn_extras.training.extensions.print_report.PrintRedu` `(class` `in` `py-`
 `method),` 409 `torch_pfn_extras.training.extensions),` 323
`load_state_dict()` `(py-` `LRScheduler` `(class` `in` `py-`
 `torch_pfn_extras.training.extensions.PrintReport` `torch_pfn_extras.training.extensions.lr_scheduler),`
 `method),` 340 `383`
`load_state_dict()` `(py-` `lstat()` `(pytorch_pfn_extras.onnx.load.Path` `method),`
 `torch_pfn_extras.training.extensions.profile_report.ProfileRe` `lstat()` `(pytorch_pfn_extras.onnx.unstrip_tensor.Path`
 `method),` 415 `method),` 261
`load_state_dict()` `(py-` `M`
 `torch_pfn_extras.training.extensions.ProfileReport`
 `method),` 342
`load_state_dict()` `(py-` `make_extension()` `(in` `module` `py-`
 `torch_pfn_extras.training.IgniteExtensionsManager` `torch_pfn_extras.training),` 284
 `method),` 297
`load_state_dict()` `(py-` `make_extension()` `(in` `module` `py-`
 `torch_pfn_extras.training.StateObjectProtocol` `torch_pfn_extras.training.extension),` 302
 `method),` 297
`load_state_dict()` `(py-` `make_statistics()` `(py-`
 `torch_pfn_extras.reporting.DictSummary` `torch_pfn_extras.reporting.DictSummary`
 `method),` 269

make_statistics() (pytorch_pfn_extras.reporting.Summary method), 482
 torch_pfn_extras.reporting.Summary method), 272
 manager (pytorch_pfn_extras.training.Trainer property), 300
 ManualScheduleTrigger (class in pytorch_pfn_extras.training.triggers), 467
 ManualScheduleTrigger (class in pytorch_pfn_extras.training.triggers.manual_schedule_trigger), 471
 481
 map() (in module pytorch_pfn_extras), 39
 map() (pytorch_pfn_extras.runtime.BaseRuntime method), 275
 map() (pytorch_pfn_extras.runtime.PyTorchRuntime method), 280
 materialize() (pytorch_pfn_extras.nn.modules.lazy.UninitializedParameter), 331
 materialize() (pytorch_pfn_extras.nn.modules.lazy_batchnorm.UninitializedParameter), 359
 materialize() (pytorch_pfn_extras.nn.modules.lazy_conv.MinValueLazyParameter), 468
 materialize() (pytorch_pfn_extras.nn.modules.lazy_linear.MinValueLazyParameter), 468
 matplotlib_savefun() (in module pytorch_pfn_extras.training.extensions.plot_report), 396
 matplotlib_savefun() (in module pytorch_pfn_extras.training.extensions.variable_statistics_plot), 449
 MaxValue (class in pytorch_pfn_extras.training.extensions), 328
 MaxValue (class in pytorch_pfn_extras.training.extensions.best_value), 358
 MaxValueTrigger (class in pytorch_pfn_extras.training.triggers), 468
 MaxValueTrigger (class in pytorch_pfn_extras.training.triggers.minmax_value), 486
 may_fire() (pytorch_pfn_extras.training.trigger.IntervalTrigger method), 461
 may_fire() (pytorch_pfn_extras.training.trigger.Trigger models), 461
 may_fire() (pytorch_pfn_extras.training.triggers.BestValueTrigger), 463
 may_fire() (pytorch_pfn_extras.training.triggers.early_stopping.EarlyStopTrigger), 474
 may_fire() (pytorch_pfn_extras.training.triggers.EarlyStopTrigger), 465
 may_fire() (pytorch_pfn_extras.training.triggers.interval_trigger), 479
 may_fire() (pytorch_pfn_extras.training.triggers.IntervalTrigger), 466
 may_fire() (pytorch_pfn_extras.training.triggers.manual_schedule_trigger), 481
 method), 467
 method), 467
 method), 483
 may_fire() (pytorch_pfn_extras.training.triggers.OnceTrigger method), 490
 may_fire() (pytorch_pfn_extras.training.triggers.OnceTrigger method), 470
 MicroAverage (class in pytorch_pfn_extras.training.extensions), 329
 MicroAverage (class in pytorch_pfn_extras.training.extensions.micro_average), 389
 MinValue (class in pytorch_pfn_extras.training.extensions), 331
 MinValue (class in pytorch_pfn_extras.training.extensions.best_value), 359
 MinValueLazyParameter (class in pytorch_pfn_extras.training.triggers), 468
 MinValueLazyParameter (class in pytorch_pfn_extras.training.triggers.minmax_value_trigger), 468
 mkdir() (pytorch_pfn_extras.onnx.load.Path method), 255
 mkdir() (pytorch_pfn_extras.onnx.unstrip_tensor.Path method), 261
 mode (pytorch_pfn_extras.dataset.tabular.delegate_dataset.DelegateDataset property), 67
 mode (pytorch_pfn_extras.dataset.tabular.DelegateDataset property), 65
 mode (pytorch_pfn_extras.dataset.tabular.tabular_dataset.TabularDataset property), 71
 mode (pytorch_pfn_extras.dataset.TabularDataset property), 59
 mode (pytorch_pfn_extras.onnx.load.IO property), 250
 mode (pytorch_pfn_extras.training.extensions.print_report.IO property), 406
 NodeComparer (class in pytorch_pfn_extras.utils.comparer), 498
 models (pytorch_pfn_extras.training.extension.ExtensionsManagerProtocol property), 308
 ModelComparer (pytorch_pfn_extras.training.extensions.best_value.ExtensionsManager property), 357
 ModelComparer (pytorch_pfn_extras.training.extensions.evaluator.ExtensionsManager property), 368
 model (pytorch_pfn_extras.training.extensions.fail_on_non_number.ExtensionsManager property), 374
 model (pytorch_pfn_extras.training.extensions.log_report.ExtensionsManager property), 377
 model (pytorch_pfn_extras.training.extensions.lr_scheduler.ExtensionsManager property), 382
 model (pytorch_pfn_extras.training.triggers.ManualScheduleTrigger), 481
 extensions.micro_average.ExtensionsManager property), 382

property), 388
models (pytorch_pfn_extras.training.extensions.parameter_statistics_manager_logging, 99
 property), 392
models (pytorch_pfn_extras.training.extensions.plot_report.ExtensionsManagerProtocol
 property), 397
models (pytorch_pfn_extras.training.extensions.print_report.ExtensionsManagerProtocol
 property), 403
models (pytorch_pfn_extras.training.extensions.profile_report.ExtensionsManagerProtocol
 property), 411
models (pytorch_pfn_extras.training.extensions.progress_bar.ExtensionsManagerProtocol
 property), 417
models (pytorch_pfn_extras.training.extensions.slack.ExtensionsManagerProtocol
 property), 421
models (pytorch_pfn_extras.training.extensions.util.ExtensionsManagerProtocol
 property), 442
models (pytorch_pfn_extras.training.extensions.value_observation.ExtensionsManagerProtocol_parallel, 226
 property), 448
models (pytorch_pfn_extras.training.extensions.variable_statistics_extensions_manager_protocol, 226
 property), 451
models (pytorch_pfn_extras.training.ExtensionsManagerProtocol
 property), 294
models (pytorch_pfn_extras.training.Trainer property), 300
models (pytorch_pfn_extras.training.triggers.early_stopping_trigger.ExtensionsManagerProtocol
 property), 475
models (pytorch_pfn_extras.training.triggers.interval_trigger.ExtensionsManagerProtocol
 property), 477
models (pytorch_pfn_extras.training.triggers.manual_schedule_trigger.ExtensionsManagerProtocol
 property), 481
models (pytorch_pfn_extras.training.triggers.minmax_value_trigger.ExtensionsManagerProtocol
 property), 485
models (pytorch_pfn_extras.training.triggers.once_trigger.ExtensionsManagerProtocol
 property), 489
models (pytorch_pfn_extras.training.triggers.time_trigger.ExtensionsManagerProtocol
 property), 492
module
 pytorch_pfn_extras, 37
 pytorch_pfn_extras.config, 41
 pytorch_pfn_extras.config_types, 43
 pytorch_pfn_extras.cuda, 44
 pytorch_pfn_extras.dataloaders, 45
 pytorch_pfn_extras.dataloaders.dataloader,
 48
 pytorch_pfn_extras.dataloaders.utils, 54
 pytorch_pfn_extras.dataset, 55
 pytorch_pfn_extras.dataset.shared_dataset,
 61
 pytorch_pfn_extras.dataset.tabular, 63
 pytorch_pfn_extras.dataset.tabular.delegate_data_loader, 66
 pytorch_pfn_extras.dataset.tabular.tabular_data_loader, 68
 pytorch_pfn_extras.distributed, 73
 pytorch_pfn_extras.engine, 75
 pytorch_pfn_extras.handler, 79
 pytorch_pfn_extras.nn, 99
 pytorch_pfn_extras.nn.modules, 123
 pytorch_pfn_extras.nn.modules.ensure_shape,
 123
 pytorch_pfn_extras.nn.modules.extended_sequential,
 123
 pytorch_pfn_extras.nn.modules.lazy, 130
 pytorch_pfn_extras.nn.modules.lazy_batchnorm,
 149
 pytorch_pfn_extras.nn.modules.lazy_conv,
 176
 pytorch_pfn_extras.nn.modules.lazy_linear,
 204
 pytorch_pfn_extras.onnx.pfto_exporter,
 256
 pytorch_pfn_extras.onnx.strip_large_tensor,
 256
 pytorch_pfn_extras.onnx.symbolic_registry,
 257
 pytorch_pfn_extras.onnx.unstrip_tensor,
 257
 pytorch_pfn_extras.profiler, 262
 pytorch_pfn_extras.runtime, 273
 pytorch_pfn_extras.testing, 283
 pytorch_pfn_extras.torchscript, 283
 pytorch_pfn_extras.training.extension,
 302
 pytorch_pfn_extras.training.extensions,
 308
 pytorch_pfn_extras.training.extensions.best_value,
 354
 pytorch_pfn_extras.training.extensions.evaluator,
 361
 pytorch_pfn_extras.training.extensions.fail_on_non_number, 372
 pytorch_pfn_extras.training.extensions.log_report,
 375
 pytorch_pfn_extras.training.extensions.lr_scheduler,
 381
 pytorch_pfn_extras.training.extensions.micro_average,
 387
 pytorch_pfn_extras.training.extensions.parameter_statistics_manager_logging, 391
 pytorch_pfn_extras.training.extensions.plot_report,
 396

```
pytorch_pfn_extras.training.extensions.print_report(method), 239
    move_to_end() (pytorch_pfn_extras.training.extensions.profile_report.Orde
pytorch_pfn_extras.training.extensions.profile_report(method), 413
    409                         multiprocessing_context (py-
    416                         torch_pfn_extras.dataloaders.DataLoader
    416                         property), 48
    420                         multiprocessing_context (py-
    420                         torch_pfn_extras.dataloader.DataLoader
pytorch_pfn_extras.training.extensions.snapshot_writer(path), 54
    427
pytorch_pfn_extras.training.extensions.utils
    441                         name (pytorch_pfn_extras.onnx.load.IO property), 250
pytorch_pfn_extras.training.extensions.value_observation
    446                         name (pytorch_pfn_extras.training.Extension attribute),
    289
pytorch_pfn_extras.training.extensions.variable_statistics_plot
    449                         name (pytorch_pfn_extras.training.extension.Extension
    305                         attribute), 305
pytorch_pfn_extras.training.manager, 457
pytorch_pfn_extras.training.metrics, 458
pytorch_pfn_extras.training.trigger, 459
pytorch_pfn_extras.training.triggers, 462
    pytorch_pfn_extras.training.triggers.early_stopping_trigger
        472                         needs_model_state (py-
    pytorch_pfn_extras.training.triggers.interval_trigger
        476                         needs_trigger_state (py-
        476                         torch_pfn_extras.training.extension.Extension
    pytorch_pfn_extras.training.triggers.manual_schedule
        479                         needs_model_state (py-
        479                         torch_pfn_extras.training.extension.Extension
    pytorch_pfn_extras.training.triggers.minmax_value_trigger
        482                         needs_model_state (py-
        482                         torch_pfn_extras.training.extensions.FailOnNonNumber
    pytorch_pfn_extras.training.triggers.once_trigger
        487                         needs_model_state (py-
        487                         torch_pfn_extras.training.extensions.FailOnNonNumber
    pytorch_pfn_extras.training.triggers.time_trigger
        491                         newlines (pytorch_pfn_extras.training.extensions.evaluator.TextIO
        491                         property), 372
    pytorch_pfn_extras.utils, 494
    pytorch_pfn_extras.utils.checkpoint, 494
    pytorch_pfn_extras.utils.comparer, 494
    pytorch_pfn_extras.writing, 500
momentum (pytorch_pfn_extras.nn.modules.lazy_batchnorm.LazyBatchNorm1d)
    attribute), 152                         torch_pfn_extras.nn.parallel.DistributedDataPar
    attribute), 152                         method), 236
momentum (pytorch_pfn_extras.nn.modules.lazy_batchnorm.LazyBatchNorm2d)
    attribute), 155                         torch_pfn_extras.nn.parallel.DistributedDataParallel
    attribute), 155                         method), 230
momentum (pytorch_pfn_extras.nn.modules.lazy_batchnorm.LazyBatchNorm3d)
    attribute), 157                         torch_pfn_extras.nn.modules.lazy_batchnorm.LazyBatchNorm1d
    attribute), 157                         num_batches_tracked (py-
move_cursor_up()
    (py-                                torch_pfn_extras.nn.modules.lazy_batchnorm.LazyBatchNorm2d
    method), 444                         num_batches_tracked (py-
    method), 444                         torch_pfn_extras.nn.modules.lazy_batchnorm.LazyBatchNorm3d
move_module() (pytorch_pfn_extras.runtime.BaseRuntime)
    method), 276                         num_batches_tracked (py-
move_module() (pytorch_pfn_extras.runtime.PyTorchRuntime)
    method), 281                         torch_pfn_extras.nn.modules.lazy_batchnorm.LazyBatchNorm3d
    attribute), 157
move_tensor() (pytorch_pfn_extras.runtime.BaseRuntime)
    method), 276                         num_features (pytorch_pfn_extras.nn.modules.lazy_batchnorm.LazyBatchN
    method), 276                         attribute), 152
move_tensor() (pytorch_pfn_extras.runtime.PyTorchRuntime)
    method), 281                         num_features (pytorch_pfn_extras.nn.modules.lazy_batchnorm.LazyBatchN
    method), 281                         attribute), 155
move_to_end() (pytorch_pfn_extras.nn.parallel.distributed.OrderedDict)
```

num_features (pytorch_pfn_extras.nn.modules.lazy_batchnorm.**observe_value**(**BatchNormAndPfn_extras.training.triggers.time_trigger.ExtensionsManagerProtocol**, property), 492
attribute), 157

num_workers (pytorch_pfn_extras.dataloaders.DataLoader.**observe_lr**() (in module pytorch_pfn_extras.training.extensions), 308
attribute), 48

num_workers (pytorch_pfn_extras.dataloaders.dataloader.**ObserveLr**() (in module pytorch_pfn_extras.training.extensions.value_observation), 446
attribute), 54

O

observation (pytorch_pfn_extras.reporting.Reporter **observe_value**() (in module pytorch_pfn_extras.training.extensions), 309
attribute), 270

observation (pytorch_pfn_extras.training.extension.ExtensionsManagerProtocol.**observe_value**() (in module pytorch_pfn_extras.training.extensions.value_observation), 447
property), 308

observation (pytorch_pfn_extras.training.extensions.best_value.**on_error**(ExtensionsManagerProtocol) (in module pytorch_pfn_extras.training.Extension method), 289
property), 357

observation (pytorch_pfn_extras.training.extensions.evaluator.ExtensionsManagerProtocol.**on_error**(ExtensionsManagerProtocol) (in module pytorch_pfn_extras.training.extension.Extension method), 305
property), 368

observation (pytorch_pfn_extras.training.extensions.fail_on_non_number.ExtensionsManagerProtocol.**on_error**(ExtensionsManagerProtocol) (in module pytorch_pfn_extras.training.triggers), 469
property), 374

observation (pytorch_pfn_extras.training.extensions.log_report.**on_error**(ExtensionsManagerProtocol) (in module pytorch_pfn_extras.training.triggers.once_trigger), 489
property), 377

observation (pytorch_pfn_extras.training.extensions.lr_scheduler.ExtensionsManagerProtocol.**open**() (pytorch_pfn_extras.onnx.load.Path method), 382
property), 382

observation (pytorch_pfn_extras.training.extensions.micro_average.ExtensionsManagerProtocol.**open**() (pytorch_pfn_extras.onnx.unstrip_tensor.Path method), 265
property), 388

observation (pytorch_pfn_extras.training.extensions.parameter_statistics.ExtensionsManagerProtocol.**optimizers**(pytorch_pfn_extras.handler.CodeBlock at property), 392
property), 392

observation (pytorch_pfn_extras.training.extensions.plot_report.ExtensionsManagerProtocol.**optimizers**(pytorch_pfn_extras.training.extension.ExtensionsManagerProtocol), 390
property), 397

observation (pytorch_pfn_extras.training.extensions.print_report.ExtensionsManagerProtocol.**optimizers**(pytorch_pfn_extras.training.extensions.best_value.ExtensionsManagerProtocol), 398
property), 403

observation (pytorch_pfn_extras.training.extensions.profile_report.ExtensionsManagerProtocol.**optimizers**(pytorch_pfn_extras.training.extensions.evaluator.ExtensionsManagerProtocol), 357
property), 411

observation (pytorch_pfn_extras.training.extensions.progress_bar.ExtensionsManagerProtocol.**optimizers**(pytorch_pfn_extras.training.extensions.fail_on_non_number.ExtensionsManagerProtocol), 268
property), 417

observation (pytorch_pfn_extras.training.extensions.slack.ExtensionsManagerProtocol.**optimizers**(pytorch_pfn_extras.training.extensions.log_report.ExtensionsManagerProtocol), 374
property), 421

observation (pytorch_pfn_extras.training.extensions.util.ExtensionsManagerProtocol.**optimizers**(pytorch_pfn_extras.training.extensions.lr_scheduler.ExtensionsManagerProtocol), 377
property), 442

observation (pytorch_pfn_extras.training.extensions.value_observation.ExtensionsManagerProtocol.**optimizers**(pytorch_pfn_extras.training.extensions.micro_average.ExtensionsManagerProtocol), 382
property), 448

observation (pytorch_pfn_extras.training.extensions.variable_statistics.ExtensionsManagerProtocol.**optimizers**(pytorch_pfn_extras.training.extensions.parameter_statistics.ExtensionsManagerProtocol), 388
property), 451

observation (pytorch_pfn_extras.training.ExtensionsManagerProtocol.**optimizers**(pytorch_pfn_extras.training.extensions.plot_report.ExtensionsManagerProtocol), 392
property), 294

observation (pytorch_pfn_extras.training.triggers.early_stopping_trigger.ExtensionsManagerProtocol.**optimizers**(pytorch_pfn_extras.training.extensions.print_report.ExtensionsManagerProtocol), 397
property), 475

observation (pytorch_pfn_extras.training.triggers.interval_trigger.ExtensionsManagerProtocol.**optimizers**(pytorch_pfn_extras.training.extensions.profile_report.ExtensionsManagerProtocol), 403
property), 477

observation (pytorch_pfn_extras.training.triggers.manual_schedule_trigger.ExtensionsManagerProtocol.**optimizers**(pytorch_pfn_extras.training.extensions.progress_bar.ExtensionsManagerProtocol), 411
property), 481

observation (pytorch_pfn_extras.training.triggers.minmax_value_trigger.ExtensionsManagerProtocol.**optimizers**(pytorch_pfn_extras.training.extensions.slack.ExtensionsManagerProtocol), 417
property), 485

observation (pytorch_pfn_extras.training.triggers.once_trigger.ExtensionsManagerProtocol.**optimizers**(pytorch_pfn_extras.training.extensions.util.ExtensionsManagerProtocol), 421
property), 489

padding_mode (`pytorch_pfn_extras.nn.modules.lazy_conv.LazyConv2dAttribute`), 303, 305
 attribute), 182
padding_mode (`pytorch_pfn_extras.nn.modules.lazy_conv.LazyConv3dAttribute`), 320
 attribute), 185
`ParameterStatistics` (class in `pytorch_pfn_extras.training.extensions`), 333
`ParameterStatistics` (class in `pytorch_pfn_extras.training.extensions.parameter_statistics`), 393
Path (class in `pytorch_pfn_extras.onnx.load`), 251
Path (class in `pytorch_pfn_extras.onnx.unstrip_tensor`), 258
`percentile()` (in `module` `pytorch_pfn_extras.training.extensions.variable_statistics`), 449
`pin_memory` (`pytorch_pfn_extras.dataloaders.DataLoader`
 attribute), 48
`pin_memory` (`pytorch_pfn_extras.dataloaders.dataloader`
 attribute), 54
`pin_memory_device` (py-
 `torch_pfn_extras.dataloaders.DataLoader`
 attribute), 48
`pin_memory_device` (py-
 `torch_pfn_extras.dataloaders.dataloader`
 attribute), 54
`PlotReport` (class in `pytorch_pfn_extras.training.extensions`), 335
`PlotReport` (class in `pytorch_pfn_extras.training.extensions.plot_report`), 398
`pop()` (`pytorch_pfn_extras.nn.parallel.distributed.OrderedDict`
 method), 239
`pop()` (`pytorch_pfn_extras.training.extensions.profile_report.OrderedDict`
 method), 413
`popitem()` (`pytorch_pfn_extras.nn.parallel.distributed.OrderedDict`
 method), 239
`popitem()` (`pytorch_pfn_extras.training.extensions.profile_report.OrderedDict`
 method), 413
`prefetch_factor` (py-
 `torch_pfn_extras.dataloaders.DataLoader`
 attribute), 48
`prefetch_factor` (py-
 `torch_pfn_extras.dataloaders.dataloader`
 attribute), 54
`PrintReport` (class in `pytorch_pfn_extras.training.extensions`), 338
`PrintReport` (class in `pytorch_pfn_extras.training.extensions.print_report`), 407
`PrintReportCLI` (in `module` `pytorch_pfn_extras.training.extensions`), 340
`priority` (`pytorch_pfn_extras.training.Extension`
 attribute), 288, 290
`priority` (`pytorch_pfn_extras.training.extension.Extension`
 attribute), 305
 priority (`pytorch_pfn_extras.training.extensions.Evaluator`
 attribute), 366
 priority (`pytorch_pfn_extras.training.extensions.evaluator.Evaluator`
 attribute), 391
 priority (`pytorch_pfn_extras.training.extensions.MicroAverage`
 attribute), 331
 priority (`pytorch_pfn_extras.training.extensions.parameter_statistics.ParameterStatistics`
 attribute), 395
 priority (`pytorch_pfn_extras.training.extensions.ProcessQueueWriter` (class in `pytorch_pfn_extras.training.extensions.snapshot_writers`),
 428
 `ProcessQueueWriter` (class in `pytorch_pfn_extras.training.extensions.snapshot_writers`),
 429
 `ProcessWriter` (class in `pytorch_pfn_extras.training_extensions`), 340
 `ProfileReport` (class in `pytorch_pfn_extras.training_extensions`), 340
 `ProfileReport` (class in `pytorch_pfn_extras.training_extensions.profile_report`),
 413
 `ProgressBar` (class in `pytorch_pfn_extras.training_extensions`), 343
 `ProgressBar` (class in `pytorch_pfn_extras.training_extensions.progress_bar`),
 413
 `ProgressbarDict` (in `module` `pytorch_pfn_extras.training_extensions`), 345
 `pytorch_pfn_extras`
 `module`, 37
 `pytorch_pfn_extras.config`
 `module`, 41
 `pytorch_pfn_extras.config_types`
 `module`, 43
 `pytorch_pfn_extras.cuda`
 `module`, 44
 `pytorch_pfn_extras.dataloaders`
 `module`, 45
 `pytorch_pfn_extras.dataloaders.dataloader`
 `module`, 48
 `pytorch_pfn_extras.dataloaders.utils`
 `module`, 54
 `pytorch_pfn_extras.dataset`
 `module`, 55

pytorch_pfn_extras.dataset.shared_dataset
 module, 61
pytorch_pfn_extras.dataset.tabular
 module, 63
pytorch_pfn_extras.dataset.tabular.delegate_datapoint
 module, 66
pytorch_pfn_extras.dataset.tabular.tabular_datapoint
 module, 68
pytorch_pfn_extras.distributed
 module, 73
pytorch_pfn_extras.engine
 module, 75
pytorch_pfn_extras.handler
 module, 79
pytorch_pfn_extras.logging
 module, 99
pytorch_pfn_extras.nn
 module, 99
pytorch_pfn_extras.nn.modules
 module, 123
pytorch_pfn_extras.nn.modules.ensure_shape
 module, 123
pytorch_pfn_extras.nn.modules.extended_sequential
 module, 127
pytorch_pfn_extras.nn.modules.lazy
 module, 130
pytorch_pfn_extras.nn.modules.lazy_batchnorm
 module, 149
pytorch_pfn_extras.nn.modules.lazy_conv
 module, 176
pytorch_pfn_extras.nn.modules.lazy_linear
 module, 204
pytorch_pfn_extras.nn.parallel
 module, 226
pytorch_pfn_extras.nn.parallel.distributed
 module, 231
pytorch_pfn_extras.onnx
 module, 242
pytorch_pfn_extras.onnx.load
 module, 247
pytorch_pfn_extras.onnx.pfto_exporter
 module, 256
pytorch_pfn_extras.onnx.strip_large_tensor
 module, 256
pytorch_pfn_extras.onnx.symbolic_registry
 module, 257
pytorch_pfn_extras.onnx.unstrip_tensor
 module, 257
pytorch_pfn_extras.profiler
 module, 262
pytorch_pfn_extras.reporting
 module, 266
pytorch_pfn_extras.runtime
 module, 273

pytorch_pfn_extras.testing
 module, 283
pytorch_pfn_extras.torchscript
 module, 283
pytorch_pfn_extras.training
 module, 284
pytorch_pfn_extras.training.extension
 module, 302
pytorch_pfn_extras.training.extensions
 module, 308
pytorch_pfn_extras.training.extensions.best_value
 module, 354
pytorch_pfn_extras.training.extensions.evaluator
 module, 361
pytorch_pfn_extras.training.extensions.fail_on_non_number
 module, 372
pytorch_pfn_extras.training.extensions.log_report
 module, 375
pytorch_pfn_extras.training.extensions.lr_scheduler
 module, 381
pytorch_pfn_extras.training.extensions.micro_average
 module, 387
pytorch_pfn_extras.training.extensions.parameter_statistics
 module, 391
pytorch_pfn_extras.training.extensions.plot_report
 module, 396
pytorch_pfn_extras.training.extensions.print_report
 module, 401
pytorch_pfn_extras.training.extensions.profile_report
 module, 409
pytorch_pfn_extras.training.extensions.progress_bar
 module, 416
pytorch_pfn_extras.training.extensions.slack
 module, 420
pytorch_pfn_extras.training.extensions.snapshot_writers
 module, 427
pytorch_pfn_extras.training.extensions.util
 module, 441
pytorch_pfn_extras.training.extensions.value_observation
 module, 446
pytorch_pfn_extras.training.extensions.variable_statistics
 module, 449
pytorch_pfn_extras.training.manager
 module, 457
pytorch_pfn_extras.training.metrics
 module, 458
pytorch_pfn_extras.training.trigger
 module, 459
pytorch_pfn_extras.training.triggers
 module, 462
pytorch_pfn_extras.training.triggers.early_stopping_trigger
 module, 472
pytorch_pfn_extras.training.triggers.interval_trigger
 module, 476

```
pytorch_pfn_extras.training.triggers.manual_schedule_trigger (pytorch_pfn_extras.training.extensions.value_observation.ExtensionsManagerProtocol property), 449
pytorch_pfn_extras.training.triggers.minmax_value_trigger (pytorch_pfn_extras.training.extensions.variable_statistics_property), 452
pytorch_pfn_extras.training.triggers.once_trigger (pytorch_pfn_extras.training.ExtensionsManagerProtocol property), 295
pytorch_pfn_extras.training.triggers.time_trigger (pytorch_pfn_extras.training.triggers.early_stopping_trigger.ExtensionsManagerProtocol property), 476
pytorch_pfn_extras.utils.raw_models (pytorch_pfn_extras.training.interval_trigger.ExtensionsManagerProtocol property), 478
pytorch_pfn_extras.utils.checkpoint.raw_models (pytorch_pfn_extras.training.triggers.manual_schedule_trigger.ExtensionsManagerProtocol property), 481
pytorch_pfn_extras.utils.comparer.raw_models (pytorch_pfn_extras.training.triggers.minmax_value_trigger.ExtensionsManagerProtocol property), 486
pytorch_pfn_extras.writing.raw_models (pytorch_pfn_extras.training.triggers.once_trigger.ExtensionsManagerProtocol property), 489
PyTorchRuntime (class in pytorch_pfn_extras.runtime), 278

Q
QueueWriter (class in pytorch_pfn_extras.training.extensions.snapshot_writer), 430
QueueWriter (class in pytorch_pfn_extras.writing), 504

R
raw_models (pytorch_pfn_extras.training.extension.ExtensionsManagerProtocol property), 308
raw_models (pytorch_pfn_extras.training.extensions.best_value.ExtensionsManagerProtocol property), 358
raw_models (pytorch_pfn_extras.training.extensions.evaluator.ExtensionsManagerProtocol property), 368
raw_models (pytorch_pfn_extras.training.extensions.fail_on_non_number.ExtensionsManagerProtocol property), 374
raw_models (pytorch_pfn_extras.training.extensions.log_report.ExtensionsManagerProtocol property), 377
raw_models (pytorch_pfn_extras.training.extensions.lr_scheduler.ExtensionsManagerProtocol property), 383
raw_models (pytorch_pfn_extras.training.extensions.micro_average.ExtensionsManagerProtocol property), 389
raw_models (pytorch_pfn_extras.training.extensions.parameter_statistics.ExtensionsManagerProtocol property), 393
raw_models (pytorch_pfn_extras.training.extensions.plot_report.ExtensionsManagerProtocol property), 398
raw_models (pytorch_pfn_extras.training.extensions.print_report.ExtensionsManagerProtocol property), 404
raw_models (pytorch_pfn_extras.training.extensions.profile_report.ExtensionsManagerProtocol property), 412
raw_models (pytorch_pfn_extras.training.extensions.progress_bar.ExtensionsManagerProtocol property), 418
raw_models (pytorch_pfn_extras.training.extensions.slack.ExtensionsManagerProtocol property), 422
raw_models (pytorch_pfn_extras.training.extensions.util.ExtensionsManagerProtocol property), 443
read() (pytorch_pfn_extras.onnx.load.IO method), 250
read() (pytorch_pfn_extras.training.extensions.print_report.IO method), 406
read_bytes() (pytorch_pfn_extras.onnx.load.Path method), 255
read_bytes() (pytorch_pfn_extras.onnx.unstrip_tensor.Path method), 261
read_text() (pytorch_pfn_extras.onnx.load.Path method), 255
read_text() (pytorch_pfn_extras.onnx.unstrip_tensor.Path method), 261
readable() (pytorch_pfn_extras.onnx.load.IO method), 250
readable() (pytorch_pfn_extras.training.extensions.print_report.IO method), 406
readline() (pytorch_pfn_extras.onnx.load.IO method), 250
readline() (pytorch_pfn_extras.training.extensions.print_report.IO method), 406
readlines() (pytorch_pfn_extras.onnx.load.IO method), 250
readlines() (pytorch_pfn_extras.training.extensions.print_report.IO method), 406
record() (in module pytorch_pfn_extras.training.extensions.print_report), 263
record() (in module pytorch_pfn_extras.training.extensions.plot_report), 232
record() (in module pytorch_pfn_extras.training.extensions.profile_report), 263
record_function (class in pytorch_pfn_extras.training.extensions.print_report), 263
record_function (in module pytorch_pfn_extras.training.extensions.plot_report), 232
record_function (in module pytorch_pfn_extras.training.extensions.profile_report), 263
record_iterable() (in module pytorch_pfn_extras.training.extensions.profile_report), 240
reduce() (pytorch_pfn_extras.onnx.strip_large_tensor), 443
```

257	reporter (pytorch_pfn_extras.training.extensions.micro_average.Extension
ReduceLROnPlateau (class in pytorch_pfn_extras.training.extensions.lr_scheduler)	property), 389 reporter (pytorch_pfn_extras.training.extensions.parameter_statistics.Extension
385	property), 393
register_comm_hook() (pytorch_pfn_extras.nn.parallel.DistributedDataParallel)	method), 398 reporter (pytorch_pfn_extras.training.extensions.plot_report.ExtensionsM
method), 237	reporter (pytorch_pfn_extras.training.extensions.print_report.ExtensionsM
register_comm_hook() (pytorch_pfn_extras.nn.parallel.DistributedDataParallel)	method), 404 reporter (pytorch_pfn_extras.training.extensions.profile_report.Extension
method), 230	property), 412
register_statistics() (pytorch_pfn_extras.training.extensions.parameter_statistics)	method), 395 reporter (pytorch_pfn_extras.training.extensions.progress_bar.ExtensionsM
method), 395	reporter (pytorch_pfn_extras.training.extensions.slack.ExtensionsManager
register_statistics() (pytorch_pfn_extras.training.extensions.ParameterState)	method), 335 reporter (pytorch_pfn_extras.training.extensions.util.ExtensionsManagerP
method), 335	roperty), 422 reporter (pytorch_pfn_extras.training.extensions.util.ExtensionsManagerP
rename() (pytorch_pfn_extras.onnx.load.Path method), 255	roperty), 443
rename() (pytorch_pfn_extras.onnx.unstrip_tensor.Path method), 261	reporter (pytorch_pfn_extras.training.extensions.value_observation.Extension
repeat() (pytorch_pfn_extras.nn.ExtendedSequential method), 105	property), 449 reporter (pytorch_pfn_extras.training.extensions.variable_statistics_plot.
repeat() (pytorch_pfn_extras.nn.modules.extended_sequen	method), 129 reporter (pytorch_pfn_extras.training.triggers.early_stopping_trigger.Extension
method), 129	property), 476
replace() (pytorch_pfn_extras.onnx.load.Path method), 255	reporter (pytorch_pfn_extras.training.triggers.interval_trigger.ExtensionsM
replace() (pytorch_pfn_extras.onnx.unstrip_tensor.Path method), 261	roperty), 478
report() (in module pytorch_pfn_extras.reporting), 266	reporter (pytorch_pfn_extras.training.triggers.manual_schedule_trigger.Extension
report() (pytorch_pfn_extras.profiler.TimeSummary method), 265	property), 481
report() (pytorch_pfn_extras.reporting.Reporter method), 271	reporter (pytorch_pfn_extras.training.triggers.minmax_value_trigger.Extension
report_key_template (pytorch_pfn_extras.training.extensions.parameter_statistics_attribute), 395	property), 486 reporter (pytorch_pfn_extras.training.triggers.once_trigger.ExtensionsM
report_key_template (pytorch_pfn_extras.training.extensions.ParameterStatistics_attribute), 335	roperty), 489
report_scope() (in module torch_pfn_extras.reporting), 267	reporter (pytorch_pfn_extras.training.triggers.time_trigger.ExtensionsM
Reporter (class in pytorch_pfn_extras.reporting), 269	roperty), 493
reporter (pytorch_pfn_extras.training.extension.ExtensionsManager)	Reservoir (class in pytorch_pfn_extras.training.extensions.variable_statistics_plot),
property), 308	452
reporter (pytorch_pfn_extras.training.extensions.best_value	reset_parameters() (pytorch_pfn_extras.nn.LazyLinear method), 122
property), 358	reset_parameters() (pytorch_pfn_extras.nn.modules.lazy_linear.LazyLinear method), 209
reporter (pytorch_pfn_extras.training.extensions.evaluato	reset_parameters() (pytorch_pfn_extras.nn.modules.lazy_linear.LazyLinear method), 255
property), 368	reset_parameters() (pytorch_pfn_extras.onnx.load.Path method), 261
reporter (pytorch_pfn_extras.training.extensions.fail_on_mal	reset_parameters() (pytorch_pfn_extras.onnx.load.Path method), 261
property), 374	reset_parameters() (pytorch_pfn_extras.onnx.load.Path method), 255
reporter (pytorch_pfn_extras.training.extensions.log_report	reset_parameters() (pytorch_pfn_extras.onnx.unstrip_tensor.Path method), 262
property), 377	reset_parameters() (pytorch_pfn_extras.onnx.unstrip_tensor.Path method), 262
reporter (pytorch_pfn_extras.training.extensions.lr_schedul	reset_parameters() (pytorch_pfn_extras.onnx.load.Path method), 255
property), 383	reset_parameters() (pytorch_pfn_extras.onnx.load.Path method), 255

rmdir() (*pytorch_pfn_extras.onnx.unstrip_tensor.Path method*), 262
run() (*pytorch_pfn_extras.training.Evaluator method*), 287
run() (*pytorch_pfn_extras.training.Trainer method*), 300
run_iteration() (*pytorch_pfn_extras.training.ExtensionsManager method*), 293
run_jit_pass() (*in module pytorch_pfn_extras.torchscript*), 283
running_mean(*pytorch_pfn_extras.nn.LazyBatchNorm1d attribute*), 108
running_mean(*pytorch_pfn_extras.nn.LazyBatchNorm2d attribute*), 110
running_mean(*pytorch_pfn_extras.nn.LazyBatchNorm3d attribute*), 112
running_mean(*pytorch_pfn_extras.nn.modules.lazy_batchnorm.LazyBatchNorm1d attribute*), 152
running_mean(*pytorch_pfn_extras.nn.modules.lazy_batchnorm.LazyBatchNorm2d attribute*), 155
running_mean(*pytorch_pfn_extras.nn.modules.lazy_batchnorm.LazyBatchNorm3d attribute*), 157
running_var(*pytorch_pfn_extras.nn.LazyBatchNorm1d attribute*), 108
running_var(*pytorch_pfn_extras.nn.LazyBatchNorm2d attribute*), 110
running_var(*pytorch_pfn_extras.nn.LazyBatchNorm3d attribute*), 113
running_var(*pytorch_pfn_extras.nn.modules.lazy_batchnorm.LazyBatchNorm1d attribute*), 152
running_var(*pytorch_pfn_extras.nn.modules.lazy_batchnorm.LazyBatchNorm2d attribute*), 155
running_var(*pytorch_pfn_extras.nn.modules.lazy_batchnorm.LazyBatchNorm3d attribute*), 157
runtime (*pytorch_pfn_extras.handler.CodeBlock attribute*), 90

S

samefile() (*pytorch_pfn_extras.onnx.load.Path method*), 255
samefile() (*pytorch_pfn_extras.onnx.unstrip_tensor.Path method*), 262
sampler (*pytorch_pfn_extras.dataloaders.DataLoader attribute*), 48
sampler (*pytorch_pfn_extras.dataloaders.DataLoader attribute*), 54
save() (*pytorch_pfn_extras.training.extensions.snapshot_writers.Writer method*), 440
save() (*pytorch_pfn_extras.writing.Writer method*), 513
save_plot_using_module() (*pytorch_pfn_extras.training.extensions.variable_statistics_plot VariableStatisticsPlot method*), 457
save_plot_using_module() (*pytorch_pfn_extras.training.extensions.VariableStatisticsPlot method*), 422
scope() (*pytorch_pfn_extras.reporting.Reporter method*), 271
scoped_anchor() (*in module pytorch_pfn_extras.onnx*), 246
seek() (*pytorch_pfn_extras.onnx.load.IO method*), 250
seek() (*pytorch_pfn_extras.training.extensions.print_report.IO method*), 406
seekable() (*pytorch_pfn_extras.onnx.load.IO method*), 250
seekable() (*pytorch_pfn_extras.training.extensions.print_report.IO method*), 406
set_evaluator_handlers() (*pytorch_pfn_extras.training_extensions.evaluator.IgniteEvaluator method*), 369
set_evaluator_handlers() (*pytorch_pfn_extras.training_extensions.IgniteEvaluator method*), 323
set_evaluator_handlers() (*pytorch_pfn_extras.training.IgniteExtensionsManager method*), 203d
set_optimizer() (*pytorch_pfn_extras.training.Trainer method*), 301
setdefault() (*pytorch_pfn_extras.nn.parallel.distributed.OrderedDict method*), 239
setdefault() (*pytorch_pfn_extras.training.extensions.profile_report.OrderedDict method*), 413
share_memory_() (*pytorch_pfn_extras.nn.modules.lazy_batchnorm.UninitializedParameter method*), 149
share_memory_() (*pytorch_pfn_extras.nn.modules.lazy_batchnorm2d.share_memory_() method*), 203d
share_memory_() (*pytorch_pfn_extras.nn.modules.lazy_batchnorm.UninitializedParameter method*), 203d
share_memory_() (*pytorch_pfn_extras.nn.modules.lazy_conv.UninitializedParameter method*), 204
share_memory_() (*pytorch_pfn_extras.nn.modules.lazy_linear.UninitializedParameter method*), 226
SharedDataset (*class in pytorch_pfn_extras.dataset*), 55
SharedDataset (*class in pytorch_pfn_extras.dataset.shared_dataset*), 62
SimpleWriter (*class in pytorch_pfn_extras.training_extensions.snapshot_writers*), 432
SimpleWriter (*class in pytorch_pfn_extras.writing*), 506
Slack (*class in pytorch_pfn_extras.training_extensions*), 345
Slack (*class in pytorch_pfn_extras.training_extensions.slack*), 422
SlackWebhook (*class in pytorch_pfn_extras.writing*), 422

<code>torch_pfn_extras.training.extensions), 348</code>	<code>method), 314</code>
<code>SlackWebhook (class in pytorch_pfn_extras.training.extensions.slack), 425</code>	<code>state_dict() (pytorch_pfn_extras.training.extensions.log_report.LogReport method), 380</code>
<code>slice (pytorch_pfn_extras.dataset.tabular.tabular_dataset.TabularDataset property), 71</code>	<code>state_dict() (pytorch_pfn_extras.training.extensions.LogReport</code>
<code>slice (pytorch_pfn_extras.dataset.TabularDataset property), 59</code>	<code>state_dict() (pytorch_pfn_extras.training.extensions.lr_scheduler.LRScheduler method), 384</code>
<code>snapshot() (in module pytorch_pfn_extras.training.extensions), 309</code>	<code>state_dict() (pytorch_pfn_extras.training.extensions.lr_scheduler.ReduceLROnPlateau method), 386</code>
<code>snapshot_object() (in module pytorch_pfn_extras.training.extensions), 311</code>	<code>state_dict() (pytorch_pfn_extras.training.extensions.LRScheduler method), 325</code>
<code>StandardWriter (class in pytorch_pfn_extras.training.extensions.snapshot_writer), 434</code>	<code>state_dict() (pytorch_pfn_extras.training.extensions.micro_average.MicroAverage method), 391</code>
<code>StandardWriter (class in pytorch_pfn_extras.writing), 507</code>	<code>state_dict() (pytorch_pfn_extras.training.extensions.MicroAverage method), 331</code>
<code>stat() (pytorch_pfn_extras.onnx.load.Path method), 255</code>	<code>state_dict() (pytorch_pfn_extras.training.extensions.plot_report.PlotReport method), 400</code>
<code>stat() (pytorch_pfn_extras.onnx.unstrip_tensor.Path method), 262</code>	<code>state_dict() (pytorch_pfn_extras.training.extensions.PlotReport method), 338</code>
<code>state (pytorch_pfn_extras.handler.CodeBlock attribute), 90</code>	<code>state_dict() (pytorch_pfn_extras.training.extensions.print_report.PrintReport method), 409</code>
<code>state_dict() (pytorch_pfn_extras.engine.StateObjectProtocol method), 79</code>	<code>state_dict() (pytorch_pfn_extras.training.extensions.PrintReport method), 340</code>
<code>state_dict() (pytorch_pfn_extras.handler.CodeBlock method), 90</code>	<code>state_dict() (pytorch_pfn_extras.training.extensions.profile_report.ProfileReport method), 415</code>
<code>state_dict() (pytorch_pfn_extras.nn.modules.lazy.LazyInitializationManager method), 132</code>	<code>state_dict() (pytorch_pfn_extras.training.extensions.ProfileReport method), 343</code>
<code>state_dict() (pytorch_pfn_extras.nn.modules.lazy_batchnorm.LazyBatchNormManager method), 159</code>	<code>state_dict() (pytorch_pfn_extras.training.IgniteExtensionsManager method), 297</code>
<code>state_dict() (pytorch_pfn_extras.nn.modules.lazy_conv.LazyConvInitializationManager method), 187</code>	<code>state_dict() (pytorch_pfn_extras.training.StateObjectProtocol method), 298</code>
<code>state_dict() (pytorch_pfn_extras.nn.modules.lazy_linear.LazyLinearInitializationManager method), 205</code>	<code>state_dict() (pytorch_pfn_extras.training.StateObjectProtocol method), 298</code>
<code>state_dict() (pytorch_pfn_extras.nn.parallel.distributed.DistributedDataParallelPfn method), 237</code>	<code>state_dict() (pytorch_pfn_extras.training.Trainer method), 301</code>
<code>state_dict() (pytorch_pfn_extras.nn.parallel.DistributedDataParallelPfn method), 230</code>	<code>state_dict() (pytorch_pfn_extras.training.StateObjectProtocol method), 298</code>
<code>state_dict() (pytorch_pfn_extras.reporting.DictSummary method), 269</code>	<code>state_dict() (pytorch_pfn_extras.training.trigger.Trigger method), 462</code>
<code>state_dict() (pytorch_pfn_extras.reporting.Summary method), 272</code>	<code>state_dict() (pytorch_pfn_extras.training.trigger.BestValueTrigger method), 463</code>
<code>state_dict() (pytorch_pfn_extras.training.Extension method), 290</code>	<code>state_dict() (pytorch_pfn_extras.training.triggers.minmax_value_trigger method), 484</code>
<code>state_dict() (pytorch_pfn_extras.training.extension.Extension method), 305</code>	<code>state_dict() (pytorch_pfn_extras.training.triggers.once_trigger.OnceTrigger method), 490</code>
<code>state_dict() (pytorch_pfn_extras.training.extension.Extension method), 306</code>	<code>state_dict() (pytorch_pfn_extras.training.triggers.OnceTrigger method), 470</code>
<code>state_dict() (pytorch_pfn_extras.training.ExtensionEntry method), 291</code>	<code>state_dict() (pytorch_pfn_extras.training.triggers.time_trigger.TimeTrigger method), 493</code>
<code>state_dict() (pytorch_pfn_extras.training.extensions.best_value.BestValue method), 356</code>	<code>state_dict() (pytorch_pfn_extras.training.triggers.TimeTrigger method), 471</code>
<code>state_dict() (pytorch_pfn_extras.training.extensions.BestValue method), 453</code>	<code>StateObjectProtocol (class in torch_pfn_extras.engine), 78</code>
	<code>StateObjectProtocol (class in torch_pfn_extras.training), 297</code>
	<code>Statics.MaxValue (class in torch_pfn_extras.training.extensions.variable_statistics_plot), 453</code>

step() (pytorch_pfn_extras.training.extensions.lr_scheduler.LRSchedulerProtocol), 386
step_by_value() (pytorch_pfn_extras.training.extensions.lr_scheduler.LRSchedulerProtocol), 384
step_by_value() (pytorch_pfn_extras.training.extensions.LRSchedulerProtocol), 325
stop_trigger (pytorch_pfn_extras.training.extensions.ExtensionsManagerProtocol), 308
stop_trigger (pytorch_pfn_extras.training.extensions.besides_summary (pytorch_pfn_extras.profiler.TimeSummary method)), 358
stop_trigger (pytorch_pfn_extras.training.extensions.evaluation_manager (pytorch_pfn_extras.onnx.load.Path method)), 368
stop_trigger (pytorch_pfn_extras.training.extensions.fail_silently (pytorch_pfn_extras.onnx.load.Path method)), 374
stop_trigger (pytorch_pfn_extras.training.extensions.log_synchronization_manager (pytorch_pfn_extras.profiler.TimeSummary method)), 377
stop_trigger (pytorch_pfn_extras.training.extensions.lr_scheduler.ExtensionsManagerProtocol), 383
stop_trigger (pytorch_pfn_extras.training.extensions.micro_average_extensions_manager_protocol.parallel.distributed.DistributedDataParallel attribute), 389
stop_trigger (pytorch_pfn_extras.training.extensions.parameter_statistics_extensions_manager_protocol.parallel.DistributedDataParallel attribute), 393
stop_trigger (pytorch_pfn_extras.training.extensions.plot_manager_extensions_manager_protocol.tabular_dataset (pytorch_pfn_extras.dataset), 398
stop_trigger (pytorch_pfn_extras.training.extensions.print_manager_extensions_manager_protocol.tabular_dataset (pytorch_pfn_extras.tabular.tabular_dataset), 404
stop_trigger (pytorch_pfn_extras.training.extensions.profile_report_extensions_manager_protocol.tell (pytorch_pfn_extras.onnx.load.IO method)), 412
stop_trigger (pytorch_pfn_extras.training.extensions.profile_report_extensions_manager_protocol.tell (pytorch_pfn_extras.training_extensions.print_report.IO method)), 418
stop_trigger (pytorch_pfn_extras.training.extensions.slack_extensions_manager_protocol (class in pytorch_pfn_extras.training_extensions.snapshot_writers), 422
stop_trigger (pytorch_pfn_extras.training.extensions.util.ExtensionsManagerProtocol), 443
stop_trigger (pytorch_pfn_extras.training.extensions.value_observation_extensions_manager_protocol.Text (in module pytorch_pfn_extras.onnx.load)), 449
stop_trigger (pytorch_pfn_extras.training.extensions.variable_statistics_extensions_manager_protocol.TEXT (class in pytorch_pfn_extras.training_extensions.evaluator), 452
stop_trigger (pytorch_pfn_extras.training.ExtensionsManagerProtocol), 295
stop_trigger (pytorch_pfn_extras.training.Trainer), 301
stop_trigger (pytorch_pfn_extras.training.triggers.early_stopping_trigger.ExtensionsManagerProtocol), 476
stop_trigger (pytorch_pfn_extras.training.triggers.interval_trigger.ExtensionsManagerProtocol), 478
stop_trigger (pytorch_pfn_extras.training.triggers.manual_schedule_extensions_manager_protocol.ThreadQueueWriter (class in pytorch_pfn_extras.training_extensions.snapshot_writers), 481
stop_trigger (pytorch_pfn_extras.training.triggers.minmax_extensions_manager_protocol.ThresholdTrigger.ExtensionsManagerProtocol), 486
stop_trigger (pytorch_pfn_extras.training.triggers.once_triggered_extensions_manager_protocol.timeout (pytorch_pfn_extras.dataloaders.DataLoader attribute)), 489

`timeout (pytorch_pfn_extras.dataloaders.dataloader.DataLoader attribute), 54`

`TimeSummary (class in pytorch_pfn_extras.profiler), 264`

`TimeTrigger (class in pytorch_pfn_extras.training.triggers), 471`

`TimeTrigger (class in pytorch_pfn_extras.training.triggers.time_trigger), 493`

`to() (in module pytorch_pfn_extras), 40`

`to_dataframe() (pytorch_pfn_extras.training.extensions.log_report.LogReport method), 380`

`to_dataframe() (pytorch_pfn_extras.training.extensions.LogReport torch_pfn_extras.handler.BaseHandler method), 328`

`torch_autocast() (in module pytorch_pfn_extras.handler), 80`

`touch() (pytorch_pfn_extras.onnx.load.Path method), 255`

`touch() (pytorch_pfn_extras.onnx.unstrip_tensor.Path method), 262`

`trace() (pytorch_pfn_extras.runtime.BaseRuntime class method), 276`

`trace() (pytorch_pfn_extras.runtime.PyTorchRuntime class method), 281`

`track_running_stats (pytorch_pfn_extras.nn.modules.lazy_batchnorm.LazyBatchNorm attribute), 152`

`track_running_stats (pytorch_pfn_extras.nn.modules.lazy_batchnorm.LazyBatchNorm attribute), 155`

`track_running_stats (pytorch_pfn_extras.nn.modules.lazy_batchnorm.LazyBatchNorm attribute), 157`

`train_cleanup() (pytorch_pfn_extras.handler.BaseHandler method), 83`

`train_cleanup() (pytorch_pfn_extras.handler.Handler method), 94`

`train_cleanup() (pytorch_pfn_extras.runtime.BaseRuntime method), 276`

`train_cleanup() (pytorch_pfn_extras.runtime.PyTorchRuntime method), 281`

`train_epoch_begin() (pytorch_pfn_extras.handler.BaseHandler method), 83`

`train_epoch_begin() (pytorch_pfn_extras.handler.BaseLogic method), 85`

`train_epoch_begin() (pytorch_pfn_extras.handler.CodeBlockLogic method), 91`

`train_epoch_begin() (pytorch_pfn_extras.handler.Handler method), 93`

`train_epoch_begin() (pytorch_pfn_extras.handler.Logic method), 94`

`train_epoch_end() (pytorch_pfn_extras.handler.Logic method), 98`

`train_epoch_end() (pytorch_pfn_extras.runtime.BaseRuntime method), 276`

`train_epoch_end() (pytorch_pfn_extras.runtime.PyTorchRuntime method), 281`

`train_epoch_end() (pytorch_pfn_extras.handler.BaseHandler method), 83`

`train_epoch_end() (pytorch_pfn_extras.handler.BaseLogic method), 86`

`train_epoch_end() (pytorch_pfn_extras.handler.CodeBlockLogic method), 91`

`train_epoch_end() (pytorch_pfn_extras.handler.Handler method), 95`

`train_epoch_end() (pytorch_pfn_extras.handler.Logic method), 98`

`train_epoch_end() (pytorch_pfn_extras.runtime.BaseRuntime method), 277`

`train_epoch_end() (pytorch_pfn_extras.runtime.PyTorchRuntime method), 281`

`train_post_step() (pytorch_pfn_extras.handler.BaseHandler method), 83`

`train_post_step() (pytorch_pfn_extras.handler.Handler method), 95`

`train_post_step() (pytorch_pfn_extras.runtime.BaseRuntime method), 277`

`train_post_step() (pytorch_pfn_extras.runtime.PyTorchRuntime method), 282`

`train_pre_step() (pytorch_pfn_extras.runtime.BaseRuntime method), 277`

`train_pre_step() (pytorch_pfn_extras.runtime.PyTorchRuntime method), 282`

`train_setup() (pytorch_pfn_extras.handler.BaseHandler method), 83`

`train_setup() (pytorch_pfn_extras.handler.Handler method), 95`

`train_step() (pytorch_pfn_extras.handler.BaseHandler method), 83`

train_step()	(<i>pytorch_pfn_extras.handler.BaseLogic method</i>), 86	99
train_step()	(<i>pytorch_pfn_extras.handler.ClosureLogic method</i>), 87	<i>train_validation_end()</i> (<i>pytorch_pfn_extras.runtime.BaseRuntime method</i>), 278
train_step()	(<i>pytorch_pfn_extras.handler.CodeBlockLogic method</i>), 91	<i>train_validation_end()</i> (<i>pytorch_pfn_extras.runtime.PyTorchRuntime method</i>), 282
train_step()	(<i>pytorch_pfn_extras.handler.Handler method</i>), 95	Trainer (<i>class in pytorch_pfn_extras.training</i>), 298
train_step()	(<i>pytorch_pfn_extras.handler.Logic method</i>), 98	training (<i>pytorch_pfn_extras.nn.Ensure attribute</i>), 103
train_step_optimizers()	(<i>pytorch_pfn_extras.handler.BaseLogic method</i>), 86	training (<i>pytorch_pfn_extras.nn.modules.ensure_shape.Ensure attribute</i>), 126
train_step_optimizers()	(<i>pytorch_pfn_extras.handler.ClosureLogic method</i>), 88	training (<i>pytorch_pfn_extras.nn.modules.extended_sequential.ExtendedSequential attribute</i>), 129
train_step_optimizers()	(<i>pytorch_pfn_extras.handler.Logic method</i>), 98	training (<i>pytorch_pfn_extras.nn.modules.lazy_batchnorm.LazyBatchNorm attribute</i>), 152
train_validation_begin()	(<i>pytorch_pfn_extras.handler.BaseHandler method</i>), 84	training (<i>pytorch_pfn_extras.nn.modules.lazy_batchnorm.LazyBatchNorm attribute</i>), 155
train_validation_begin()	(<i>pytorch_pfn_extras.handler.BaseLogic method</i>), 86	training (<i>pytorch_pfn_extras.nn.modules.lazy_batchnorm.LazyBatchNorm attribute</i>), 157
train_validation_begin()	(<i>pytorch_pfn_extras.handler.CodeBlockLogic method</i>), 92	training (<i>pytorch_pfn_extras.nn.modules.lazy_conv.LazyConv1d attribute</i>), 179
train_validation_begin()	(<i>pytorch_pfn_extras.handler.Handler method</i>), 95	training (<i>pytorch_pfn_extras.nn.modules.lazy_conv.LazyConv2d attribute</i>), 182
train_validation_begin()	(<i>pytorch_pfn_extras.handler.Logic method</i>), 98	training (<i>pytorch_pfn_extras.nn.modules.lazy_conv.LazyConv3d attribute</i>), 185
train_validation_begin()	(<i>pytorch_pfn_extras.runtime.BaseRuntime method</i>), 277	training (<i>pytorch_pfn_extras.nn.modules.lazy_linear.LazyLinear attribute</i>), 209
train_validation_begin()	(<i>pytorch_pfn_extras.runtime.PyTorchRuntime method</i>), 282	training (<i>pytorch_pfn_extras.nn.parallel.distributed.DistributedDataParallel attribute</i>), 238
train_validation_end()	(<i>pytorch_pfn_extras.handler.BaseHandler method</i>), 84	training (<i>pytorch_pfn_extras.nn.parallel.DistributedDataParallel attribute</i>), 231
train_validation_end()	(<i>pytorch_pfn_extras.handler.BaseLogic method</i>), 86	transform() (<i>pytorch_pfn_extras.dataset.tabular.tabular_dataset.TabularDataset method</i>), 72
train_validation_end()	(<i>pytorch_pfn_extras.handler.CodeBlockLogic method</i>), 92	transform() (<i>pytorch_pfn_extras.dataset.TabularDataset method</i>), 59
train_validation_end()	(<i>pytorch_pfn_extras.handler.Handler method</i>), 96	transform_batch() (<i>pytorch_pfn_extras.dataset.tabular.tabular_dataset.TabularDataset method</i>), 72
train_validation_end()	(<i>pytorch_pfn_extras.handler.Logic method</i>), 98	transform_batch() (<i>pytorch_pfn_extras.dataset.TabularDataset method</i>), 59
train_validation_end()	(<i>pytorch_pfn_extras.runtime.BaseRuntime method</i>), 277	transposed (<i>pytorch_pfn_extras.nn.modules.lazy_conv.LazyConv1d attribute</i>), 179
train_validation_end()	(<i>pytorch_pfn_extras.runtime.PyTorchRuntime method</i>), 282	transposed (<i>pytorch_pfn_extras.nn.modules.lazy_conv.LazyConv2d attribute</i>), 182
train_validation_end()	(<i>pytorch_pfn_extras.handler.BaseHandler method</i>), 84	transposed (<i>pytorch_pfn_extras.nn.modules.lazy_conv.LazyConv3d attribute</i>), 185
train_validation_end()	(<i>pytorch_pfn_extras.handler.BaseLogic method</i>), 86	Trigger (<i>class in pytorch_pfn_extras.training.trigger</i>), 461
train_validation_end()	(<i>pytorch_pfn_extras.handler.CodeBlockLogic method</i>), 92	trigger (<i>pytorch_pfn_extras.training.Extension attribute</i>), 288, 290
train_validation_end()	(<i>pytorch_pfn_extras.handler.Handler method</i>), 96	trigger (<i>pytorch_pfn_extras.training.extension.Extension attribute</i>), 303, 305
train_validation_end()	(<i>pytorch_pfn_extras.handler.Logic method</i>), 98	trigger (<i>pytorch_pfn_extras.training.extensions.Evaluator</i>)

V

attribute), 320
trigger(*pytorch_pfn_extras.training.extensions.evaluator.Evaluator*.*attribute*), 366
trigger (*pytorch_pfn_extras.training.extensions.Slack*.*attribute*), 347
trigger(*pytorch_pfn_extras.training.extensions.slack.Slack*.*attribute*), 425
truncate() (*pytorch_pfn_extras.onnx.load.IO* method), 251
truncate() (*pytorch_pfn_extras.training.extensions.print_report.IO* method), 407
TypeVar (class in *pytorch_pfn_extras.nn.modules.extended_sequential*), 130
TypeVar (class in *pytorch_pfn_extras.nn.parallel.distributed*), 239

W

Variable (class in *pytorch_pfn_extras.nn.parallel.distributed*), 240
VariableStatisticsPlot (class in *pytorch_pfn_extras.training.extensions*), 350
VariableStatisticsPlot (class in *pytorch_pfn_extras.training.extensions.variable_statistics_plot*), 454

UninitializedParameter (class in *pytorch_pfn_extras.nn.modules.lazy*), 132
UninitializedParameter (class in *pytorch_pfn_extras.nn.modules.lazy_batchnorm*), 159
UninitializedParameter (class in *pytorch_pfn_extras.nn.modules.lazy_conv*), 187
UninitializedParameter (class in *pytorch_pfn_extras.nn.modules.lazy_linear*), 209
unlink() (*pytorch_pfn_extras.onnx.load.Path* method), 255
unlink() (*pytorch_pfn_extras.onnx.unstrip_tensor.Path* method), 262
unstrip() (in module *pytorch_pfn_extras.onnx.unstrip_tensor*), 257
update() (*pytorch_pfn_extras.nn.parallel.distributed.OrderedDict*.*method*), 239
update() (*pytorch_pfn_extras.training.extensions.profile_report.OrderedDict*.*method*), 413
update() (*pytorch_pfn_extras.training.extensions.util.ProgressBar*.*method*), 444
update_parameters() (in module *pytorch_pfn_extras.handler*), 80
update_speed() (*pytorch_pfn_extras.training.extensions.util.ProgressBar*.*method*), 444
update_via_args() (*pytorch_pfn_extras.config.Config*.*method*), 43
use_default_mempool_in_cupy() (in module *pytorch_pfn_extras.cuda*), 44
use_torch_mempool_in_cupy() (in module *pytorch_pfn_extras.cuda*), 44

values() (*pytorch_pfn_extras.nn.parallel.distributed.OrderedDict*.*method*), 239
values() (*pytorch_pfn_extras.training.extensions.profile_report.OrderedDict*.*method*), 413
Variable (class in *pytorch_pfn_extras.nn.parallel.distributed*), 240
VariableStatisticsPlot (class in *pytorch_pfn_extras.training.extensions*), 350
VariableStatisticsPlot (class in *pytorch_pfn_extras.training.extensions.variable_statistics_plot*), 454

with_converter() (in module *torch_pfn_extras.dataset.tabular.tabular_dataset.TabularDataset*), 72
with_converter() (in module *torch_pfn_extras.dataset.TabularDataset*), 60
writable() (*pytorch_pfn_extras.onnx.load.IO* method), 251
writable() (*pytorch_pfn_extras.training.extensions.print_report.IO* method), 407
write() (*pytorch_pfn_extras.onnx.load.IO* method), 251
write() (*pytorch_pfn_extras.training.extensions.print_report.IO* method), 407
write_bytes() (in module *pytorch_pfn_extras.onnx.load.Path* method), 256
write_bytes() (*pytorch_pfn_extras.onnx.unstrip_tensor.Path* method), 262
write_text() (in module *pytorch_pfn_extras.onnx.load.Path* method), 256
write_text() (*pytorch_pfn_extras.onnx.unstrip_tensor.Path* method), 262
write_text() (in module *pytorch_pfn_extras.onnx.load.Path* method), 256
writelines() (in module *pytorch_pfn_extras.onnx.load.IO* method), 251
writelines() (*pytorch_pfn_extras.training.extensions.print_report.IO* method), 407
Writer (class in *pytorch_pfn_extras.training.extensions.snapshot_writers*), 439
Writer (class in *pytorch_pfn_extras.writing*), 512
writer (*pytorch_pfn_extras.training.extension.ExtensionsManagerProtocol*.*property*), 308

```
writer(pytorch_pfn_extras.training.extensions.best_value.ExtensionsManagerProtocol
      property), 358
writer(pytorch_pfn_extras.training.extensions.evaluator.ExtensionsManagerProtocol
      property), 368
writer(pytorch_pfn_extras.training.extensions.fail_on_non_number.ExtensionsManagerProtocol
      property), 374
writer(pytorch_pfn_extras.training.extensions.log_report.ExtensionsManagerProtocol
      property), 377
writer(pytorch_pfn_extras.training.extensions.lr_scheduler.ExtensionsManagerProtocol
      property), 383
writer(pytorch_pfn_extras.training.extensions.micro_average.ExtensionsManagerProtocol
      property), 389
writer(pytorch_pfn_extras.training.extensions.parameter_statistics.ExtensionsManagerProtocol
      property), 393
writer(pytorch_pfn_extras.training.extensions.plot_report.ExtensionsManagerProtocol
      property), 398
writer(pytorch_pfn_extras.training.extensions.print_report.ExtensionsManagerProtocol
      property), 404
writer(pytorch_pfn_extras.training.extensions.profile_report.ExtensionsManagerProtocol
      property), 412
writer(pytorch_pfn_extras.training.extensions.progress_bar.ExtensionsManagerProtocol
      property), 418
writer(pytorch_pfn_extras.training.extensions.slack.ExtensionsManagerProtocol
      property), 422
writer(pytorch_pfn_extras.training.extensions.util.ExtensionsManagerProtocol
      property), 443
writer(pytorch_pfn_extras.training.extensions.value_observation.ExtensionsManagerProtocol
      property), 449
writer(pytorch_pfn_extras.training.extensions.variable_statistics_plot.ExtensionsManagerProtocol
      property), 452
writer(pytorch_pfn_extras.training.ExtensionsManagerProtocol
      property), 295
writer(pytorch_pfn_extras.training.triggers.early_stopping_trigger.ExtensionsManagerProtocol
      property), 476
writer(pytorch_pfn_extras.training.triggers.interval_trigger.ExtensionsManagerProtocol
      property), 478
writer(pytorch_pfn_extras.training.triggers.manual_schedule_trigger.ExtensionsManagerProtocol
      property), 481
writer(pytorch_pfn_extras.training.triggers.minmax_value_trigger.ExtensionsManagerProtocol
      property), 486
writer(pytorch_pfn_extras.training.triggers.once_trigger.ExtensionsManagerProtocol
      property), 489
writer(pytorch_pfn_extras.training.triggers.time_trigger.ExtensionsManagerProtocol
      property), 493
```